After Effects SDK Guide

Release 1.0.0

About

About this Document	1
Version History	3
Introduction	5
What Can I Do With This SDK?	7
Other Integration Possibilities	11
SDK Audience	13
What's New	15
How To Start Creating Plug-ins	25
Sample Projects	27
Debugging Plug-ins	31
Compatibility Across Multiple Versions?	33
Third-party Plug-in Hosts?	35
PiPL Resources	37
Exceptions	39
Where Installers Should Put Plug-ins	41
Localization	43
Next Steps	45
Effect Basics	47
Entry Point	49
Command Selectors	51
	About this Document Version History Introduction What Can I Do With This SDK? Other Integration Possibilities SDK Audience What's New How To Start Creating Plug-ins Sample Projects Debugging Plug-ins Compatibility Across Multiple Versions? Third-party Plug-in Hosts? PiPL Resources Exceptions Where Installers Should Put Plug-ins Localization Next Steps Effect Basics Entry Point Command Selectors

21	PF_InData	57
22	PF_OutData	65
23	Parameters	73
24	PF_ParamDef	77
25	PF_EffectWorld / PF_LayerDef	83
26	Errors	87
27	Effect Details	89
28	Accessing the After Effects Function Suites	91
29	Memory Allocation	93
30	Image Buffer Management Functions	95
31	Iteration Suites	97
32	Graphics Utility Suites	101
33	Interaction Callback Functions	111
34	Pixel Aspect Ratio	117
35	Parameters & Floating Point Values	119
36	Parameter Supervision	121
37	Global, Sequence, & Frame Data	125
38	Arbitrary Data Parameters	129
39	Useful Utility Functions	133
40	Motion Blur	145
41	Working With Paths	147
42	Accessing Camera & Light Information	151
43	Color Space Conversion	153
44	Changing Parameter Orders, the Nice Way	155
45	Tips & Tricks	157
46	SmartFX	163
47	Effect UI & Events	171
48	PF_EventExtra	173
49	PF_EventUnion	177
50	Custom UI & Drawbot	181

51	UI Callbacks	193
52	Tips & Tricks	195
53	Audio	197
54	Global Outflags	199
55	Audio Data Structures	201
56	Audio-Specific Float Slider Variables	203
57	Accessing Audio Data	205
58	Audio Considerations	207
59	AEGPs	209
60	What's New?	211
61	Overview	213
62	Data Types	215
63	Implementation	219
64	AEGP Suites	223
65	Cheating Effect Usage of AEGP Suites	327
66	AEGP Details	329
67	Artisans	331
68	Artisan Data Types	333
69	AEIOs	349
70	Calling Sequence	353
71	AEIO_ModuleInfo	355
72	New Kids On The Function Block	361
73	Implementation Details	393
74	Premiere Pro & Other Hosts	395
75	Plug-in Installation	397
76	Basic Host Differences	399
77	Multithreading	403
78	Bigger Differences	405
79	Plug-Ins Reloaded	407
80	Effects Presets	409

81	Custom ECW UI Over A Standard Data Type	411
82	Premiere Elements	413
83	Unsupported Features	415
84	Other Hosts	417

About this Document

This document has changed much over the years. Part encyclopedia, part how-to guide, with multiple sedimentary layers of accreted information from more than two decades of API development and refinement.

Yes, there does need to be one source of information about every last niggling detail of the After Effects APIs. However, since no human in their right mind would ever want to *read* such a document, we've tried to keep it involving and interesting.

As opportunity allows, we'll try to include more diagrams, illustrations, and purdy pickshurs explaining API intricacies

As always, your input is valued and appreciated.

1.1 Organization

The *Introduction* provides an overview of the integration possibilities with After Effects. It explains what plug-ins are, and how they work with After Effects. It describes the sample projects, and how to modify them. It explains where to install plug-ins, and what resources they use.

The basics of effect plug-ins are discussed in *Effect Basics*. This overview provides information on the function parameters passed to and from an effect plug-in's entry point. It describes capability flags, effect parameters, and image buffers.

Effect Details dives into the details of developing a complete effect plug-in using the many provided callback functions. It also provides many testing ideas to ensure the plug-in is stabile.

SmartFX is the extension to the effect plug-in API to support 32-bit floating point images.

Effect UI & Events covers events sent to effect plug-ins, how to incorporate custom user interface elements, parameter supervision, and the reliance of custom data parameter types on Custom UI messaging.

Audio effects are covered in... Audio.

AEGPs details the After Effects General Plug-in (AEGP) API. Provided callback functions, hooking into internal messaging, manipulating the current contents of open projects and handling menu commands are all covered at length.

Artisans covers specialized plug-in 3D renderer AEGPs.

AEIOs, specialized AEGPs which handle file input and output.

Premiere Pro & Other Hosts discusses issues related to compatibility with Premiere Pro and other applications that support a subset of After Effects plug-ins.

1.2 Documentation Conventions

Functions, structure names and general C/C++ code are in Courier; MyStruct and MyFunction();

Text in blue is hyperlinked.

Command selectors are italicized; *PF_Cmd_RENDER*.

1.3 A Note About Coding Style

Because we use the public APIs for our own plug-ins, our coding guidelines are apparent throughout the SDK. Here's a description of the pseudo-neo-post-Hungarian notation we use. Of course, you're welcome to code however you like. If you feel strongly that we should change our internal coding standards, please post your requests at comp.sys.programmer.better.things.to.do.with.your.time, and we'll carefully consider them before not making any changes.

1.3.1 Coding Conventions

Туре	Suffix	Example
Handle	Н	fooH
pointer (to)	P	fooP
Boolean	В	visibleB
Float	F	degreesF
Long	L	offsetL
unsigned long	Lu	countLu
short	S	indexS
char	C	digitC
unsigned char	Cu	redCu
function pointer	_func	sample_func
time value		durationT
char* (NULL-terminated C string)	Z	nameZ
rectangle	R	boundsR
fixed rectangle	FiR	boundsFiR
float rectangle	FR	boundsFR
ratio	Rt	scale_factorRt
void*	PV	refconPV
optional parameter (must be passed, can be NULL)	0	extra_flags0

Version History

Revi-	Documen-	Notes
sion	tor	
Date		
1		16.0 release
Novem-		
ber		
2018		
10	Zac Lam	15.0 release
Novem-		
ber		
2017		
12 May	Zac Lam	CC 2017.1 (14.2) release
2017		
2	Zac Lam	CC 2017 (14.0) release.
Novem-		
ber		
2016		
21 July	Zac Lam	CC 2015 (13.5) release.
2015		
12 June	Zac Lam	CC 2014 (13.0) release. Corrections for accuracy. Removed old version references.
2014		
15 July	Zac Lam	CC (12.0) release. API version changes, misc small clarifications, more details in AEIOs.
2013		
26 April	Zac Lam	CS6 (11.0) release. Big reorganization of the AEGPs and Artisans. Many additions
2012		throughout.
2 May	Zac Lam	CS5.5 (10.5) release.
2011		
28 April	Zac Lam	CS5 (10.0) release. 64-bit porting info. Drawbot.
2010		
4 May	Zac Lam	CS4 (9.0) release. Complete reorganization of first three chapters. Fleshed out documen-
2009		tation on Premiere Pro.
1 July	Bruce	CS3 (8.0) release.
2007	Bullis	
4 4 April	Bruce	Updated to reference new development system requiremeChapteK2odVepsion History
2006	Bullis	Some editing.
1 De-	Bruce	Updated for 7.0. Added SmartFX documentation. Noted current suite version numbers
cember	Bullis	throughout. Numerous editorial changes. Documented many new AEGP suite functions.

Introduction

Welcome to the Adobe® After Effects® CC Software Development Kit!

This is a living document, and is constantly being updated and edited. The latest public version of the SDK is available at: https://www.adobe.io/apis/creativecloud/aftereffects.html

While we've tried to organize this document in a logical order and provide plenty of cross references, your specific needs may vary. Searching through this document based on keywords will often lead you to your answer.

If you need more information, your question may already be answered on the After Effects SDK forum: After Effects SDK Forum

Use the search box there, and post a new question if your question hasn't already been answered.

What Can I Do With This SDK?

This SDK describes the Application Programming Interface (API) that developers use to build plug-ins. These plugins can extend the capabilities of After Effects and other applications that support the After Effects API. Plug-ins may also be used to bridge the gap between After Effects and another application.

4.1 What Plug-Ins Can I Build With This SDK?

Effect plug-ins can be applied to video or audio in a composition, to process video and/or audio data. Some examples of built-in effects are Brightness and Contast, Hue/Saturation, Gaussian Blur, and Warp Stabilizer. Effect plug-ins can provide a set of parameter controls for the user to fine-tune the effect. These parameter values can vary over time, and effects may use other layers and parameters at different times to calculate the output. It's often thought that all plug-ins are effects. But effects are just one type of plug-in used by After Effects.

See a quickstart video on building an effect (on macOS): adobe.ly/2sjMDwM

After Effects General Plug-ins (AEGPs) can read and modify nearly every element of After Effects projects and preferences. They can add menu items, 'hook' (register themselves to receive) and trigger After Effects' internal commands, and add new panels that dock and resize within the After Effects UI. They can work with markers and keyframes, and manage the render queue. They can even run scripts. Some examples of built-in AEGPs are the AAF importer, and the SWF exporter. Automatic Duck Pro Import AE is another well-known AEGP.

After Effects Input/Output (AEIO) plug-ins provide support for new media file types. Unless you need a custom setup dialog to specify interpretation settings, the *Premiere Pro Importers* API provides similar functionality, and is preferable in many cases. AEIOs use the AEGP API along with certain APIs specific to AEIOs. While After Effects still supports Photoshop format plug-ins and filters, as well as Foreign Project Format (FPF) plug-ins, these APIs have been long deprecated in favor of the AEIO API.

BlitHook plug-ins output video to external hardware for broadcast quality monitoring and playback to tape. The EMP sample project provides a starting point. In After Effects CC 2014 and later, *Mercury Transmit* is the recommended API.

Artisans provide rendered output of 3D layers, taking over 3D rendering from After Effects (which still handles all rendering of 2D layers). Artisans use the AEGP API along with certain APIs specific to Artisans.

Didn't see the type of integration you need described above? After Effects is very flexible, and there are several other ways to integrate with After Effects. See: *Other Integration Possibilities*.

4.2 Where Do Plug-ins Appear In After Effects?

Effects plug-ins appear in both the *Effect* menu and the Effects & Presets panel, in the effect category specified in their PiPL. Once they're applied, the effect's parameter controls (sliders, pop-ups, etc.) appear in the Effect Controls panel (ECP).

After Effects General Plug-ins (AEGPs) can add items to any After Effects menu, and additional panels listed in the Window menu. These menu items are indistinguishable from After Effects' own menu items.

AEIOs and Photoshop Format plug-ins can appear in the *File > Import* menu, or in the *Import File* dialog in the *Files of type* drop-down, depending on the type of importer. AEIOs and Format plug-ins can also appear as available output formats in the render queue.

BlitHook plug-ins are automatically loaded and used by AE, but do not appear in any menu or dialog. The plug-in may optionally provide a menu item that opens it's own custom settings dialog. It would register and update the menu item using the AEGP API.

It can registered to be called by After Effects to update the menu with AEGP_RegisterUpdateMenuHook(), and it can dim/activate the menu item using AEGP_EnableCommand()/DisableCommand().

Artisans appear in the Rendering Plug-in drop-down in the Advanced tab of the Composition Settings dialog.

4.3 How Does After Effects Interact With Plug-ins?

Plug-ins, written in C or C++, are bundle packages on macOS and DLLs on Windows. They must contain a Plug-in Property List (*PiPL Resources*) resource on both platforms. The plug-ins must be located in one of a few specific folders in order to be loaded and used by After Effects.

For effects plug-ins, After Effects sends command selectors (and relevant information) to the plug-in *Entry Point* designated in the effects' *PiPL Resources* resource. Selectors are sent in response to actions the user takes—applying the effect, changing parameters, scrubbing through frames in the timeline, and rendering all prompt different sequences of selectors.

After Effects creates multiple instances of effects, with settings and input data unique to each sequence. All instances share the same global data, and can share data between all frames within their sequence. After Effects doesn't process all image data as soon as the user applies an effect; it invokes effects only when their output is required.

After Effects General Plug-ins (AEGPs) have their entry point function called during application launch, and register for whatever messaging they need at that time. Further calls to the AEGP are initiated by user actions, as part of the plug-in's response to menu commands or UI events. Depending on their features, plug-ins may need to respond to OS-specific entry points as well, for UI work and thread management.

For BlitHook plug-ins, frames are pushed as they're displayed in the Composition panel. Users can initiate a RAM preview on an area of the timeline so that it is rendered to RAM, and then it all gets played out at full speed.

4.4 SDK Contents

The SDK contains headers defining the After Effects APIs, sample projects demonstrating integration features, and this SDK Guide.

They are compiled with the SDK header files, which expose various After Effects functionality to be used by the plug-in.

4.4. SDK Contents 9

Other Integration Possibilities

Although this SDK describes the majority of integration possibilities with After Effects, there are other possibilities not to be overlooked.

5.1 Scripting

Scripting is a relatively nimble and lightweight means to perform automated tasks with After Effects. ScriptUI is one way you can provide UI integration with custom dialogs and panels (see *HTML5 Panels* too). And scripting may be used in tandem with plug-in development, in the cases where a certain function is made available via scripting and not via the C APIs described in this document.

Scripting in After Effects is done using ExtendScript, based on JavaScript. After Effects includes the ExtendScript ToolKit, a convenient interface for creating and testing your own scripts. Scripts may be compiled into .jsxbin binary files, to protect intellectual property.

You can access the After Effects Scripting Guide, and find a link to the scripting forums, on the Adobe I/O website at: https://www.adobe.io/apis/creativecloud/aftereffects.html

After Effects can be driven by executing scripts from the commandline. In your script, you can open the project and run script actions on it. So for example, you can execute the following statement to run a script from the command line directly:

AfterFX -s "app.quit()"

Or you can execute this statement to run a .jsx script that includes a guit at the end:

AfterFX -r path_to_jsx_script

On Windows, AfterFX.com is the way to get feedback to the console, because AfterFX.com is a command line application.

5.2 HTML5 Panels

In CC 2014 and later, After Effects supports HTML5 panels. They are accessed in After Effects from Window > Extensions > (your panel name). Panels can be resized and docked just like any other panel in After Effects. Panels are built using HTML5, After Effects Scripting, and JavaScript. You may download the After Effects Panel SDK from the the Adobe I/O website at: https://www.adobe.io/apis/creativecloud/aftereffects.html

5.3 AERender

Closely coupled with scripting is the command line interface offered by aerender. aerender is primarily suited to allow automated renders, but can be used to execute any sequence of scripting commands from the command line. An overview is available in the After Effects help documents here: https://helpx.adobe.com/after-effects/using/automated-rendering-network-rendering.html

5.4 Premiere Pro Importers

Premiere Pro importers provide support for importing media into applications across most applications in the Adobe Creative Cloud, including Premiere Pro, Media Encoder, Prelude, and Audition. Because of this broader compatibility, unless you need very specific integration with After Effects only available via the AEIO API in this SDK, we recommend developing a Premiere Pro importer. The Premiere Pro SDK is available at: https://www.adobe.io/apis/creativecloud/premierepro.html

One advantage of MediaCore importer plug-ins over AEIOs is its priority system: The highest priority importer gets first crack at importing a file, and if the particular imported file isn't supported, the next-highest priority importer will then have the opportunity to try importing it, and so on.

5.5 Mercury Transmit

Mercury Transmit plug-ins are used for sending video to output hardware for broadcast-quality monitoring. Transmitters are supported across most applications in the Adobe Creative Cloud, including Premiere Pro, After Effects, Prelude, and Character Animator. The Mercury Transmit API is documented in the Premiere Pro SDK, available at: https://www.adobe.io/apis/creativecloud/premierepro.html

SDK Audience

You must be a proficient C/C++ programmer to write After Effects plug-ins. While we'll help with issues specific to the After Effects API, we can't help you learn your IDE or basic programming concepts.

This SDK guide assumes you understand After Effects from a user's perspective, and basic motion graphics terminology. If you don't, get the Adobe After Effects Classroom in a Book, or any of the other fine instructional books on the market. It will help you understand necessary

topics such as alpha channels, pixel aspect ratio, interlacing, color spaces, and more for After Effects.

6.1 Development Requirements

The system requirements for After Effects are here: https://helpx.adobe.com/after-effects/system-requirements.html

If you require support for obsolete versions of the application or API, use an old SDK (which we don't maintain or provide). Six months after the current version is released, we will no longer provide or support the previous version's SDK.

The SDK samples are created for Xcode 7.3 on macOS 10.11, and Microsoft Visual Studio 2015 update 3 on Windows 7 64 or Windows 10. Yes, we're being pretty stringent about using the required IDE. No, it's never pleasant to move to a new compiler, but no, we're not going to continue to help with older build environments.

In order to use Visual Studio, you may need to adjust some installation settings to install the components for compiling 64-bit plug-ins. Visual Studio Express may be used, but will also require an additional installation to compile 64-bit plug-ins, as described here: http://msdn.microsoft.com/en-us/library/9yb4317s.aspx

To compile using newer versions of Xcode on newer versions of macOS, often all that is required is to update the Base SDK in the Build Settings.

What's New

If this is your first time developing an After Effects plug-in, you can skip the What's New section and go directly to *How To Start Creating Plug-ins*.

7.1 What's New In CC 2019 (16.0)?

We've made some changes to how GPU effects are handled. See "GPU Effects Changes" for details.

7.2 What's New In 15.0?

After Effects now supports the *GPU effect rendering* previously supported in Premiere Pro. Note that unknown effects with a match name that includes "ADBE" will be excluded from GPU rendering, so make sure any of your GPU effects have your own custom match name. Effects that support GPU rendering will receive the GPU badge in the Effect panel.

The GPU effect sample projects in the Premiere Pro SDK have been updated to register as GPU effects in AE, although the render output still needs work.

A new entry point has been defined, to allow effects to register basic information with the host at runtime, without relying on legacy PiPL resources. An effect can register multiple entry points in a single binary this way. Premiere Pro is the first host to support this entry point, and After Effects will support this in a future release.

The effect sample projects have been updated to use this approach, while maintaining the PiPL for backwards compatibility.

AEGP_StreamSuite is now at version 5, where AEGP_GetExpression() and AEGP_SetExpression() have been upgraded to support Unicode.

PF_AdvTimeSuite is now at version 4, with a new call *PF_TimeCountFrames()*, that returns the index of the frame in the current comp.

The new AEGP Math Suite provides helpful calls for matrix multiplication.

The application font is now Adobe Clean. Previously, the fonts used in After Effects' UI were Tahoma on Windows and Lucida Grande on macOS X. This is a proprietary font, and we can not make it available for use in your UI.

7.3 What's New In CC 2017.1 (14.2)?

• Layer Params can include Masks and Effects

Effects that use layers as an input, such as Set Matte and Displacement Map, can now target the input layer's masks and effects, instead of only the source of the layer. This means that for there is no need to pre-compose layers just so that they can be referenced by an effect.

Where an effect includes a layer parameter, a new menu to the right of the layer selector allows you to choose whether to target the input layer from its source, masks, or effects:

- Source: targets only the source of the layer. Masks and effects are ignored.
- Masks: targets the layer after its masks are applied. Effects are ignored.
- Effects & Masks: targets the layer after its masks and effects are applied.

This control is similar to the View menu at the bottom of the Layer viewer panel, which allows you to render the layer from different positions in the rendering order: from its source, from its masks, or from its individual effects.

As this is a user-facing option, the design is intended to be transparent to the effect. From the effect's perspective, the input simply just includes the upstream effects and masks without any change to the effect. For any effect that uses layer params, here are some testing recommendations:

- Effect continues to work as expected.
- Using new control in the layer param for Source/Mask/Effects works with effect.
- Opening old projects or saving back to a previous version project does not break effect.
- Confirm that effect cannot self-reference; meaning cannot use the effects on the layer as input for the same layer.
- Suite Enhancements

PF_AdvTimeSuite is now at version 3, providing a revised *PF_GetTimeDisplayPref()* call that uses a revised PF_TimeDisplayPrefVersion parameter, that supports higher frame rates. The previous version 2 of the call can now return an error if there is a problem with the values exceeding the range supported by the structure.

Comp Suite is now at version 11, with a new call, *AEGP_ReorderCompSelection()*, to move a selection to a certain layer index. It should be used along with AEGP_SetSelection().

7.4 What's New In CC 2017 (14.1)?

Unicode support for AEGP Item Suite and AEGP Render Queue Item Suite.

7.5 What's New In CC 2017 (14.0)?

The GLator sample is back! It has been updated to demonstrate proper OpenGL context management in an effect plug-in.

7.6 What's New In CC 2015.3 (13.8)?

PF_OutFlag_I_AM_OBSOLETE is now supported in Premiere Pro. Also, effect custom UI in Premiere Pro now supports high DPI displays, such as Retina Displays.

7.7 What's New In CC 2015 (13.6)?

New AEGP Item View Suite. This provides a way to get playback time for item view. Only the composition case is implemented in this release. The time passed back should be the playback time of the view when playing and the current (needle) time otherwise.

AEGP_RenderNewItemSoundData() has been reworked and provides functionality similar to 13.2.

7.8 What's New In CC 2015 (13.5.1)?

This release fixes some audio APIs that broke in 13.5 due to threading changes. In 13.5, when called on the UI thread, AEGP_RenderNewItemSoundData() would return A_Err_GENERIC. This restores the functionality when called on the UI thread.

To avoid a deadlock, in PF_Cmd_UPDATE_PARAMS_UI only, AEGP_RenderNewItemSoundData() will now return silence. This will no longer function as before in this context, but it will continue to work properly elsewhere.

7.9 What's New In CC 2015 (13.5)?

• Separate UI and Render Threads

This release of After Effects includes major architectural changes to separate the UI (main) thread from the render thread. The render thread sends selectors such as PF_Cmd_RENDER, PF_Cmd_SMART_PRERENDER, and PF_Cmd_SMART_RENDER to effect plug-ins. The UI thread sends selectors such as PF_Cmd_SEQUENCE_SETUP, PF_Cmd_USER_CHANGED_PARAM, PF_Cmd_DO_DIALOG, and PF_EVENT_DRAW. PF_Cmd_SEQUENCE_RESETUP is

sent on both render and UI threads.

These changes are to improve interactive performance and responsiveness. At the same time, the new design introduces some new requirements and may break assumptions that existing plug-ins relied on. Here are some of the major changes:

- 1) The project can no longer be modified by the render thread (and in fact the render thread now has its own local copy of the project)
- 2) Rendering cannot pass modified sequence data back to the UI thread for custom UI updates
- 3) In general the UI thread should no longer do time-consuming operations such as synchronously rendering frames Is your plug-in affected? Test for these problems:
 - 1) Render not updating after UI parameter change because it depends on sequence_data, which may not be currently copied to render
 - 2) Render not updating during click/drag in the Composition Window (similar reasons)
 - 3) Custom Effect UI not updating because it depends on sequence_data generated in render (which is no longer available to the UI because it is in a different project, the render project is immutable, and cache contains previously-rendered frames)
 - 4) Errors telling you an operation on the render thread (or UI thread) is not expected

Generally, calculations that will persist or update the UI will now have to be pulled from the UI thread rather than pushed from the render thread. These cases can require use of new

- 13.5 APIs or different solutions than in past releases.
 - The Need For More Efficient Sequence Data Handling

PF_OutFlag2_SUPPORTS_GET_FLATTENED_SEQUENCE_DATA

PF Cmd GET FLATTENED SEQUENCE DATA

Up to version 13.2, serializing/flattening sequence_data always involved deallocating and reallocating any data structures. Starting in 13.5, as effect changes are made, serializing/ flattening happens even more often. Why? AE needs to serialize/flatten project changes to send from the UI thread to the render thread, to keep them both synchronized.

To make this process more efficient, starting in 13.5, AE can send PF_Cmd_GET_FLATTENED_SEQUENCE_DATA to request sequence data without requiring the existing data to be deallocated and reallocated. The main difference between this selector and PF_Cmd_SEQUENCE_FLATTEN is that a copy of the correct flattened state is returned without disposing the original structure(s) the effect is currently using. For a code example, refer to the PathMaster sample project.

This will eventually become required for plug-ins that are rebuilt to be thread-safe (see PF_OutFlag2_AE13_5_THREADSAFE below). The venerable PF_Cmd_SEQUENCE_FLATTEN will eventually be unsupported in future versions.

• PF OutFlag FORCE RERENDER Changes

Where possible, we recommend triggering rerenders using one of the following: GuidMixInPtr() (described in the next section), arb data, or PF_ChangeFlag_CHANGED_VALUE. All of these allow cached frames to be reused after an Undo.

Note: As of 14.0, setting PF_ChangeFlag_CHANGED_VALUE for layer or path params is not triggering a rerender. Instead, you may change set the value using AEGP_StreamSuite-

>AEGP_SetStreamValue().

FORCE_RERENDER is still needed for situations where sequence_data needs to be copied from the UI thread to the render project/effect clone to keep them matched.

FORCE_RERENDER is the trigger for this whether the render request uses the cache or not. Once we have the full set of APIs in place needed to manage render state, we will be able to deprecate FORCE_RERENDER.

FORCE_RERENDER doesn't work in every situation it did before, because it needs to synchronize the UI copy of sequence data with the render thread copy.

FORCE_RERENDER works when set during PF_Cmd_USER_CHANGED_PARAM. It also works in CLICK and DRAG events, but only if PF_Cmd_GET_FLATTENED_SEQUENCE_DATA is implemented. This is required to prevent flattening and loss of UI state in the middle of mouse operations. Without GET_FLATTENED, the new FORCE RERENDER behavior will NOT be turned on.

· GUIDs for Cached Frames

PF OutFlag2 I MIX GUID DEPENDENCIES

GuidMixInPtr()

Used by SmartFX only. Use this if custom UI or PF_Cmd_DO_DIALOG changes sequence data, or if the render result depends on anything else not factored in, and rerendering may be needed. During PF_Cmd_SMART_PRERENDER, the effect can call GuidMixInPtr() to mix any additional state that affects the render into our internal GUID for the cached frame. Using this GUID, AE can tell whether the frame already exists or if it needs to be rendered. See an example in SmartyPants sample project.

This is an improvement over the older mechanisms PF_OutFlag_FORCE_RERENDER and PF_Cmd_DO_DIALOG, which would remove the frame from the cache because the host didn't know what else the plug-in was factoring into the rendering. This can also be used rather than PF_OutFlag2_OUTPUT_IS_WATERMARKED.

• Request Frames Asynchronously Without Blocking the UI

PF OutFlag2 CUSTOM UI ASYNC MANAGER

 $PF_GetContextAsyncManager() \\ AEGP_CheckoutOrRender_ItemFrame_AsyncManager() \\ AEGP_CheckoutOrRender_LayerFrame_AsyncManager() \\$

For cases where such renders formerly were triggered by side-effect or cancelled implicity

(such as custom UI histogram drawing), and lifetime is less clear from inside the plug-in, use the new "Async Manager" which can handle multiple simultaneous async requests for effect Custom UI and will automatically support interactions with other AE UI behavior.

Note: Async retrieval of frames is preferred for handling passive drawing situations, but not when a user action will update the project state. If you are (1) responding to a specific user click, AND 2) you need to update the project as a result, the synchronous AEGP_RenderAndCheckoutLayerFrame() is recommended.

The new HistoGrid sample in the SDK shows how to do completely asynchronous custom UI DRAW event handling on the UI thread when 1 or more frame renders are needed. e.g. for calculating histograms that are shown in the effect pane. Please note there is still a known bug where drag-changing an upstream param may not refresh the histogram draw until the mouse hovers over it.

• Get Rendered Output of an Effect from its UI

Effects such as keyers or those that draw histograms of post-processed video can retrieve the needed AEGP_LayerRenderOptionsH using the new function AEGP_NewFromDownstreamOfEffect() in AEGP LayerRenderOptionsSuite. This function may only be called from the UI thread.

· AEGP Usage on Render Thread

We've tightened validation of when AEGP calls could be used dangerously (such as from the wrong thread or making a change to the project state in render). You may see new errors if code is hitting such cases. For example, making these calls on the render thread will result in an error:

```
suites.UtilitySuite5()->AEGP_StartUndoGroup() suites.StreamSuite2()->AEGP_GetStreamName() suites.StreamSuite2()->AEGP_SetExpressionState() suites.StreamSuite2()->AEGP_SetExpression() suites.StreamSuite2()->AEGP_DisposeStream() suites.EffectSuite3()->AEGP_DisposeEffect() suites.UtilitySuite5()->AEGP_EndUndoGroup()
```

The solution is to move these calls to the UI thread. Selectors for passive UI updates (such as PF_EVENT_DRAW) are not a place to make changes to project state.

Another example of more strict requirements is AEGP_RegisterWithAEGP(). The documentation has always noted that this function must be called on PF_Cmd_GLOBAL_SETUP. However in previous versions, plug-ins were able to call this function at other times without running into trouble. Not anymore in 13.5! Calling this function at other times can cause crashes!

• PF_Cmd_SEQUENCE_RESETUP Called on UI or Render Thread?

There is now a PF_InFlag_PROJECT_IS_RENDER_ONLY flag that is only valid in PF_Cmd_SEQUENCE_RESETUP that will tell you if the effect instance is for render-only purposes. If so, the project should be treated as completely read-only, and you will not be receiving UI related selectors on that effect instance. This can be used to optimize away any UI-only initialization that render does not need. If this flag is false, you should setup UI as normal. This should not be used to avoid reporting errors in render. Errors in render should be reported as usual via existing SDK mechanisms.

• Changes to Avoid Deadlocks

During development, it was noticed that deadlocks could occur in specific call usage. Seatbelts have been introduced to avoid this. The cases occur in PF_Cmd_UPDATE_PARAMS_UI when using particular calls because of deprecated synchronous behavior in these calls when used in the UI:

In PF_Cmd_UPDATE_PARAMS_UI only, PF_PARAM_CHECKOUT() for layer parameters will behave as before except that it will return a black frame of the same size, etc., rather than actual rendered pixels. Code that used this for enable/disable detection of parameters should still work as before. Code that used this for getting analysis frames, etc. outside of PF_Cmd_UPDATE_PARAMS_UI will work as before.

In PF_Cmd_UPDATE_PARAMS_UI only, PF_GetCurrentState() will now return a random GUID. This will no longer function as before in this context, but it will continue to work properly elsewhere.

The above uses should be rare, but if this affects you please contact us about workarounds.

· Deprecated

AEGP_RenderAndCheckoutFrame() (on the UI Thread). This call should generally not be used on the UI thread since synchronous renders block interactivity.

Use in the render thread is fine. The one case where this may still be useful on the UI thread is a case like a UI button that requires a frame to calculate a parameter which then updates the AE project.

For example, an "Auto Color" button that takes a frame and then adjusts effect params as a result.

A beta of a progress dialog for this blocking operation if it is slow has been implemented, but using this call on the UI thread should be limited to this special cases. The dialog design is not final.

• Flag for Thread-Safe Effects

PF OutFlag2 AE13 5 THREADSAFE

Plug-ins updated for threading should use this flag to tell AE that the plug-in is expected to be UI thread <> Render thread safe.

This flag tells AE that different threads on different AE project copies can be in the effect at the same time but not accessing the same instance. While multiple render threads are not yet in use, this will be useful in future releases.

• Support for Effect Version greater than 7 (new max is MAJOR version 127)

Effects greater than version 7 will now report properly in 13.5 if built with the current SDK headers. It is possible to use these recompiled effects in AE versions older than 13.5, but internally the version number will wrap modulo 8 (e.g. AE will internally see effect version 8 as version 0).

This can affect the version shown in error dialog display by older AE and affect usage reporting.

Since many older plug-ins were made unloadable in AE with the shift to 64-bit, it should be unlikely this wrapping would cause ambiguity with actual plug-ins in current use (unless these plug-ins have been rapidly increasing version number over the last few years).

However, building with an older SDK and using an 8 or higher version will result in the plug-in reporting an incorrect version to AE, which will then cause mismatch with the PiPL version check for the effect which will have the higher bits set. This is not supported.

If built with an older SDK, you will need to keep the effect version at 7 or below. Increase in version max has been accomplished by adding 4 new higher significant bits to the version that only AE 13.5 and above "sees". These new high version bits are not contiguous with the original, preexisting MAJOR version bits – just ignore the intermediate bits. The new version layout looks like this in hexadecimal or binary.

0x 3C38 0000

^^ original MAJOR version bits as a hex mask 0-7

^^ new HIGH bits extending the original MAJOR version bits 8-127

^^ original MAJOR version bits as a hex mask 0-7

^^ ^^ ignore / do not use

^^ ^^ new HIGH bits extend the original MAJOR version bits 8-127.

These bits are ignored in AE versions older than 13.5.

New Installer Hints for macOS

Developers can find paths to the default location of plug-ins, scripts, and presets on macOS X in a new plist file (same as the paths in the Windows registry): /Library/Preferences/ com.Adobe.After Effects.paths.plist

You can use the values in this plist to direct where your installers or scripts write files, in the same way that you would use the paths keys in the registry on Windows: HKEY_LOCAL_MACHINESOFTWAREAdobeAfter Effects13.5

Work In Progress

AEGP_RenderAndCheckoutLayerFrame_Async() AEGP_CancelAsyncRequest()

This APIs are in progress, and should not be used yet.

7.10 What's New In CC 2014.1 (13.1)?

PF CreateNewAppProgressDialog()

It won't open the dialog unless it detects a slow render. (2 seconds timeout).

7.11 What's New In CC 2014 (13.0)?

Starting in CC 2014, After Effects will now honor a change to a custom UI height made using PF_UpdateParamUI.

AEGP Effect Suite is now at version 4, adding new functions to work with effect masks. AEGP_RenderSuite is now at version 4, adding a new function AEGP_RenderAndCheckoutLayerFrame, which allows frame checkout of the current

layer with effects applied at non-render time. This is useful for an operation that requires the frame, for example, when a button is clicked and it is acceptable to wait for a moment while it is rendering.

Note: Since it is not asynchronous, it will not solve the general problem where custom UI needs to draw based on the frame.

The layer render options are specified using the new AEGP_LayerRenderOptionsSuite.

Mercury Transmit plug-ins and HTML5 Panels are now supported.

7.12 What's New In CC (12.0)?

Effect names can now be up to 47 characters long, up from 31 characters previously.

We added the *PF_AngleParamSuite*, providing a way to get floating point values for angle parameters. *PF App Suite* version 5 adds PF_AppGetLanguage to query the current language so that a plug-in can use the correct language string, as well as several new PF_App_ColorType enum values for new elements whose colors can be queried.

AEGP Persistent Data Suite is now at version 4, adding a new parameter to AEGP_GetApplicationBlob to choose between retrieving several different application blobs. There are also new functions to get/set time and ARGB values.

AEGP Composition Suite is now at version 10, adding new functions to check/modify whether layer names or source names are shown, and whether the blend modes column is shown or not. Also added are new functions to get and set the Motion Blur Adaptive Sample Limit.

AEGP Layer Suite is now at version 8, adding new functions to set/get the layer sampling quality. AEGP_CanvasSuite is also now at version 8. The new function AEGP_MapCompToLayerTime handles time remapping with collapsed or nested comps, unlike AEGP_ConvertCompToLayerTime.

AEGP_UtilitySuite is now at version 6, adding a new Unicode-aware function: AEGP_ReportInfoUnicode. Another new function, AEGP_GetPluginPaths, provides some useful paths related to the plug-in and the After Effects executable itself.

The behavior for AEGP_NewPlaceholderFootageWithPath has been updated, so that the file_type should now be properly set, otherwise a warning will appear.

AEGP_InsertMenuCommand can now insert menu items in the File>New submenu.

AEGP_IOInSuite is now at version 5, adding new functions to get/set/clear the native start time, and to get/set the drop-frame setting of footage.

7.13 What's New In CS6.0.1 (11.0.1)?

New in 11.0.1, the AE effect API version has been incremented to 13.3.

This allows effects to distinguish between 11.0 and 11.0.1.

There is a bug in 11.0 with the Global Performance Cache, when a SmartFX effect uses both PF_OutFlag2_AUTOMATIC_WIDE_TIME_INPUT & PF_OutFlag_NON_PARAM_VARY.

Calling checkout_layer during PF_Cmd_SMART_PRE_RENDER returns empty rects in PF_CheckoutResult.

The workaround is to simply make the call again. This workaround is no longer needed in 11.0.1.

7.14 What's New In CS6 (11.0)?

We've made several refinements for better parameter UI handling. PF_PUI_INVISIBLE parameter UI flag is now supported in After Effects, which is useful if your plug-in needs hidden parameters that affect rendering. Now when a plug-in disables a parameter using *PF_UpdateParamUI*, we now save that state in the UI flags so that the plug-in can check the flag in the future to see if it is disabled. A new flag, PF_ParamFlag_SKIP_REVEAL_WHEN_UNHIDDEN, allows a parameter to be unhidden without twirling open any parents and without scrolling the parameter into view in the Effect Controls panel and the Timeline panel.

Effects that render a watermark over the output when the plug-in is in trial mode can now tell After Effects whether watermark rendering mode is on or off, using the new PF_OutFlag2_OUTPUT_IS_WATERMARKED.

The new Global Performance Cache means you must tell After Effects to discard old cached frames when changing your effect's rendering.

We've removed PF_HasParamChanged and PF_HaveInputsChangedOverTimeSpan, providing PF_AreStatesIdentical instead.

Effects that provide custom UI can now receive PF_Event_MOUSE_EXITED, to gain notification that the mouse exited the layer or comp panel. PF_ParamUtilsSuite is now at version 3.

PF_GET_PLATFORM_DATA now has new selectors for getting the wide character path of the executable and resource file: PF_PlatData_EXE_FILE_PATH_W and PF_PlatData_RES_FILE_PATH_W. The previous non-wide selectors are now deprecated.

3D is a major theme of AE CS6. A new AEGP_LayerFlag_ENVIRONMENT_LAYER has been added. Many new *layer streams* were added.

Additionally, AEGP_LayerStream_SPECULAR_COEFF was renamed to AEGP_LayerStream_SPECULAR_INTENSITY, AEGP_LayerStream_SHININESS_COEFF was renamed to AEGP_LayerStream_SPECULAR_SHININESS, and AEGP_LayerStream_METAL_COEFF was renamed to just AEGP_LayerStream_METAL.

A new suite, *AEGP_RenderQueueMonitorSuite*, provides all the info a render queue manager needs to figure out what is happening at any point in a render.

AEGP Mask Suite is now at version 6, and provides functions to get and set the mask feather falloff type. AEGP Mask Outline Suite is now at version 3, and provides access to get and set mask outline feather information.

Effects that depend on masks now have a new flag available, PF_OutFlag2_DEPENDS_ON_UNREFERENCED_MASKS.

AEGP Composition Suite is now at version 9. AEGP_CreateTextLayerInComp and

AEGP_CreateBoxTextLayerInComp now have a new parameter, select_new_layerB.

AEGP Render Suite is now at version 3, adding a new function to get the GUID for a render receipt.

Finally, we have added two new read-only *Dynamic Stream* flags: AEGP_DynStreamFlag_SHOWN_WHEN_EMPTY and AEGP_DynStreamFlag_SKIP_REVEAL_WHEN_UNHIDDEN.

For effects running in Premiere Pro CS6, we have added the ability to get 32-bit float and YUV frames from PF_CHECKOUT_PARAM.

7.15 ... and what was new before CS6?

For history this far back, see obsolete copies of the SDK (which we don't provide; if someone wants you do develop for antique software, they'd best provide the SDK).

How To Start Creating Plug-ins

8.1 Play!

Before you write a line of code, Spend some significant time playing with After Effects, and with the *Sample Projects*. Build the plug-ins into the right folder. Set lots of breakpoints, read the amusing and informative comments.

See a quickstart video on building an effect (on macOS): adobe.ly/2sjMDwM

8.2 Plan!

Be clear on what your plug-in will attempt to do.

8.3 Hack!

After experimenting with the samples, find one that does something *like* what you want to do. The temptation to start from scratch may be strong; fight it! For effects, use the Skeleton template project. Avoid the headache of reconstructing projects (including the troublesome custom build steps for Windows PiPL resource generation) by grafting your code into an existing project.

8.4 Steal!

To make the Skeleton sample your own, copy the entire \Skeleton directory, renaming it to (for example) \WhizBang. Using your text editor of choice, search \WhizBang*.* (yes, that includes .NET and Xcode project files) for occurrences of Skeleton and SKELETON, and replace them with WhizBang and WHIZBANG.

You now have a compiling and running plug-in that responds to common commands, handles 8 and 16-bpc color, uses our AEGP SuiteHandler utility code, and responds to 3D light and camera information. There, was that so hard?

AEGP developers will do well to start with Projector (for After Effects project creation support), Easy Cheese for a keyframe assistant, IO for media file format support, and Persisto for a simple menu command and working with preferences.

8.5 Test!

If only for testing convenience, you should have a project saved with your effect applied, and all its parameters keyframed to strange values. Between these projects which stress your plug-in, and the tools provided by your development environment, you're well on your way to shipping some tested code.

8.6 Blame!

If you run into behavior that seems wrong, see if you can reproduce the behavior using one of the unmodified sample projects. This can save you a lot of time, if you can determine whether the bug behavior was introduced by your modifications, or was already there to begin with.

8.7 Developers Matter

Third party developers drive API and SDK improvement and expansion. Your products enable After Effects to do things we'd never considered. Your efforts make After Effects better; keep it up!

We work hard on the SDK, and welcome your comments and feedback. Almost every change we make to the API is suggested by developers like you. Talk to us.

Sample Projects

There is at least one sample of every type of plug-in supported by the current API, as well as projects to illustrate particular concepts.

In the sample projects, we've kept the code as simple as possible. A showy implementation might get us good grades in a programming class, but won't help you understand how to use API features.

After the break, we explain how to build the sample projects, so keep reading below!

9.1 Sample Project Descriptions

Project	Description
AEGPs	AEGPs hook directly into After Effects' menus and
	other areas in the UI. See below for specifics on where
	the AEGP appears in the UI.
Artie	Artie the Artisan takes over rendering of all 3D layers in
	a given composition. This is the same API used by our
	internal 3D renderers; it is very complex, and exposes
	a great deal of tacit information about the After Effects
	rendering pipeline. Unless you have a compelling rea-
	son to replace the way After Effects handles 3D render-
	ing, you need never work with this sample. Artisans
	appear in Composition > Composition Settings, in the
	Advanced tab, in the Rendering Plug-in drop-down.
Easy Cheese	A keyframer (which shows up on the Animation >
	Keyframe Assistant submenu), Easy Cheese shows how
	to manipulate various characteristics of keyframes (in
	a way that, uncannily, resembles our shipping plug-in,
	Easy Ease)

Continued on next page

Table 1 – continued from previous page

Project	Description
FBIO	Exercises the After Effects Input/Output (AEIO) API.
TBIO	Similar to the IO sample, but supports the frame-based
	.ffk file format. Note that we now recommend develop-
	ing a <i>Premiere Pro Importers</i> instead.
Grabba	Gets frames (formatted as the plug-in requests) from any
Graoba	composition in the project.
IO	Exercises the After Effects Input/Output (AEIO) API.
	Supports the fictitious
	.fak file format, and handles all requests from After Ef-
	fects for retrieving data from or outputting to such files.
	Note that we now recommend developing a <i>Premiere</i>
	Pro Importers instead.
Mangler	Mangler is a keyframer demonstrating the use of an
C	ADM palette, just like our own.
Panelator	Creates a panel that can be docked along with the rest of
	the standard panels. Note: It is far more work to create
	a panel this way than using the HTML5 Panel SDK. We
	recommend starting with that SDK instead.
Persisto	Shows how to read and write information from the After
	Effects preferences file.
ProjDumper	Creates a text file representing every element in an After
	Effects project.
Projector	Imports the (fictitious) .sdk file format, and creates a
	project using AEGP API calls. Whenever you're won-
	dering how to get or set some characteristic of a project
	element, look here first. Note: There are some hard-
	coded paths in Projector.h. If you don't set these to re-
	fer to actual media on disk, you WILL get errors while
	running this plug-in. Don't blame us; change them!
QueueBert	Pronounced "Cue-BARE!", QueueBert manipulates all
	aspects of render queue items and the output modules
	associated with them.
Streamie	Manipulates streams, both dynamic and fixed.
Sweetie	Sweetie uses the PICA (or "Suite Pea") API to provide
	a function Suite, for use by other plug-ins. If you're
	writing multiple plug-ins that rely on the same image
	processing library, you could provide the library func-
T . T . 1 II	tionality using such a suite.
Text Twiddler	Manipulates text layers and their contents.
Effects	All effects appear in the Effects & Presets panel, and in
Charles	the Effect menu.
Checkout	Checks out (of After Effects' frame cache) a frame of
	input from another layer, at a specified time. This is an
	important concept for all effects with layer parameters.
Consolution	Premiere Pro compatible.
Convolutrix	Exercises our image convolution callbacks. Premiere
	Pro compatible.

Continued on next page

Table 1 – continued from previous page

Project	1 – continued from previous page Description
Gamma Table	Shows how to manage sequence data, and uses our iter-
	ation callbacks. For nostalgia's sake, we're leaving this
	one sample in C; it's also compatible with many third-
	party plug-in hosts, due to its reliance on version 3.x
	API features.
GLator	New for CC 2017. Demonstrates proper OpenGL con-
	text management in an effect plug-in.
Paramarama	Exercises wayward param types not used in other sam-
	ple. Premiere Pro compatible.
PathMaster	Shows how to access paths from within an effect.
Portable	Shows how to detect and respond to several different
	plug-in hosts. Premiere Pro compatible.
Resizer	Resizer resizes (surprise!) the output buffer. This is
	useful for effects like glows and drop shadows, which
	would be truncated at the layer's edges if they didn't
	expand the output buffer. Premiere Pro compatible.
SDK Backwards	Reverses a layer's audio, and mixes it with a keyframe-
	able sine wave.
SDK Noise	Premiere Pro compatible, demonstrates 32-bit and YUV
	rendering in Premiere Pro.
Shifter	Shifts an image in the output buffer, and exercises our
	transform_world and subpixel sampling functions.
SmartyPants	Demonstrates the SmartFX API, required for support of
	floating point pixels.
Transformer	Exercises our image transformation callbacks.
Effect Template	
Skeleton	Skeleton is the starting point for developing effects. Pre-
	miere Pro compatible.
Effects with Custom UI	
CCU	Implements a custom user interface in the composition
	and layer windows, supporting pixel aspect ratio and
	downsample ratios. Premiere Pro compatible.
ColorGrid	Shows how to use arbitrary data type parameters. Also
	has a nice custom UI. Premiere Pro compatible.
Custom ECW UI	Implements a very boring custom user interface in the
	effect controls window, and shows how to respond to
	numerous UI events.
Histogrid	New for CC 2015 (13.5). An example of how cus-
	tom UI can access asynchronously-rendered upstream
	frames for lightweight processing in CC 2015 and later.
	This effect calculates a sampled 10x10 color grid from
	the upstream frame, and displays a preview of that color
	grid. In render, a higher-quality grid is calculated and
	used to modify the output image, creating a blend of a
	color grid with the original image.
	Shows how to control parameters (both values and UI)
Supervisor	
Supervisor	<u> </u>
Supervisor	based on the value of other parameters. Premiere Procompatible.

Continued on next page

Table 1 – continued from previous page

Project	Description
EMP	External Monitor Preview. Use this as a starting point
	for adding support to output video from the composition
	panel to video hardware.

9.2 Building The Sample Projects

We've combined the sample projects into a single master project, stored in the Examples folder of the SDK. For macOS, it is Buildall.xcodeproj; for Windows, it is BuildAll.sln.

In your IDE, you'll need to change the output folder of your project to build into After Effects' plug-in folder.

For development, we recommend using the following path for macOS: /Library/Application Support/Adobe/Common/Plug-ins/[version]/MediaCore/

Version is locked at 7.0 for all CC versions, or CSx for earlier versions.

for example: /Library/Application Support/Adobe/Common/Plug-ins/7.0/MediaCore/

or:/Library/Application Support/Adobe/Common/Plug-ins/CS6/MediaCore/

 $and the following path for Windows: \verb|[Program Files] \land Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land Toronto Adobe \land Common \land Plug-ins \land [version] \land MediaCore \land [version] \land [ver$

for example: C:\Program Files\Adobe\Common\Plug-ins\7.0\MediaCore\

or: C:\Program Files\Adobe\Common\Pluq-ins\CS6\MediaCore\

Note that this Windows path is only recommended for development purposes. Windows installers should follow the guidelines here: *Where Installers Should Put Plug-ins*.

In Xcode, you can set this path once for all projects in the Xcode Preferences > Locations > Derived Data > Advanced. Under *Build Location* choose *Custom*, and fill in the path.

In Visual Studio, for convenience, we have specified the output path for all sample projects using the environment variable AE_PLUGIN_BUILD_DIR. You'll need to set this as a user environment variable for your system. On Windows 7, right-click *My Computer* > *Properties*

>and in the left sidebar choose *Advanced System Settings*. In the new dialog, hit the *Environment Variables* button. In the User variables area, create a New variable named AE_PLUGIN_BUILD_DIR, and with the path described above. Log out of Windows and log back in so that the variable will be set.

Alternatively, you can set output path for each project individually in Visual Studio by right-clicking a project in the Solution Explorer, choosing Properties, and then in Configuration Properties > Linker > General, set the Output File.

When compiling the plug-ins, if you see a link error such as:

"Cannot open file "[MediaCore plug-ins path]plugin.prm", make sure to launch Visual Studio in administrator mode. In your Visual Studio installation, right-click devenv.exe, Properties > Compatibility > Privilege Level, click "Run this program as an administrator".

Debugging Plug-ins

The best way to learn the interaction(s) between After Effects and plug-ins is running the samples in your debugger. Spending some quality time in your compiler's debugger, and a sample project that closely resembles your plug-in, can really pay off.

Once you've got the plug-in building directly into the plug-ins folder as explained above, here's how to specify After Effects as the application to run during debug sessions:

On Windows:

- 1) In the Visual Studio solution, in the Solution Explorer panel, choose the project you want to debug
- 2) Right-click it and choose Set as StartUp Project
- 3) Right-click it again and choose Properties
- 4) In Configuration Properties > Debugging > Command, provide the path to the executable file of the host application the plug-ins will be running in (this may be After Effects or Premiere Pro)
- 5) From there you can either hit the Play button, or you can launch the application and later at any point choose Debug > Attach to Process...

On macOS:

- 1) In Xcode, in the Project Navigator, choose the xcodeproj you want to debug
- 2) Choose Product > Scheme > Edit Scheme...
- 3) Under Run, in the Info tab, for Executable, choose the host application the plug-ins will be running in (this may be After Effects or Premiere Pro)
- 4) From there you can either hit the Play button to build and run the current scheme, or you can launch the application and later at any point choose Debug > Attach to Process.

10.1 Deleting Preferences

During the course of developing a plug-in, your plug-in may pass settings information to After Effects, which is then stored in its preferences file.

You may delete the preferences and restart After Effects with a clean slate by holding down Ctrl-Alt-Shift / Cmd-Opt-Shift during launch.

On Windows, the preferences are stored here: [user folder] $\AppData\Roaming\Adobe\After Effects [version]-x64 Prefs.txt$

On macOS, they are stored here: ~/Library/Preferences/Adobe/After Effects/[version]/ Adobe After Effects [version]-x64 Prefs

Compatibility Across Multiple Versions?

Generally, you should compile your plug-ins with the latest After Effects SDK headers. This makes the latest suites and API functionality available to your plug-ins. When a new version of After Effects is released, you generally will not need to provide a new version unless you wish to take advantage of new functionality exposed through the new SDK. However, you should always test your plug-in in new versions of After Effects before claiming compatibility with new versions.

You should test your plug-in thoroughly in each version of After Effects supported by your plug-in. If you need to add a conditional block of code to be run only in specific versions of After Effects, you can always check the API version in *PF_InData*.version for effects, or in the major and minor_versionL passed into your AEGP in the *Entry Point*.

For even more precise version checking, a plug-in can run a script using AEGP_ExecuteScript (AEGP_UtilitySuite6), querying one of the following attributes:

```
app.version - e.g. 11.0.1x12
app.buildNumber - e.g. 12.
```

11.1 API Versions

Release	Effect API Version	AEGP API
15.0	13.15	Version
CC 2017.1 (14.2)	13.14	
CC 2017 (14.0)	13.13	114.0
CC 2015.3	13.11	113.8
(13.8)		
CC 2015 (13.7)	13.10	113.7
CC 2015 (13.6)	13.10	
CC 2015 (13.5,	13.9	113.5
13.5.1)		
CC 2014 (13.0-	13.7	113
13.2)		
CC (12.2)	13.6	112.2
CC (12.1)	13.5	112.1
CC (12.0)	13.4	112.0
CS6.0.1	13.3	111.0
(11.0.1)		
CS6 (11.0)	13.2	111.0
CS5.5 (10.5)	13.1	17.0
CS5 (10.0)	13.0	17.0
CS4 (9.0)	12.14	16.24
CS3 (8.0)	12.13	16.24
7.0	12.12	
6.5, 6.0	12.10 (Check for the presence of updated AEGP suites, should you need to	
	differentiate between 6.0 and 6.5.)	
5.0	12.5	
4.1	12.2	
3.1	11.6	

Third-party Plug-in Hosts?

Some developers are wary of using each After Effects release's new API features, to maintain compatibility with hosts with partial implementations. You can distinguish between host applications by checking *PF_InData*>appl_id. After Effects uses the appl_id 'FXTC'.

Premiere Pro uses 'PrMr'. As of this writing, no third party hosts support SmartFX, or our AEGP functions.

Also, see the Premiere Pro & Other Hosts section.

PiPL Resources

Originating in Adobe Photoshop over two decades ago, Plug-In Property Lists, or PiPLs, are resources which provide basic information about a plug-in's behavior, without executing the plug-in. PiPLs have been largely supplanted within After Effects by PF_Cmd_GLOBAL_SETUP (see *Global Selectors*) and dynamic outflags. However, for archaeological reasons, the behaviors indicated during PF_Cmd_GLOBAL_SETUP must agree with those in the PiPL.

A PiPL specifies the entry point of a plug-in, the display name, as well as the plug-in's match name. The match name is a unique, constant identifier, unlike a plug-in's display name, which may be changed dynamically. Starting in CC, display names can be up to 47 characters long. Previously, they were limited to 31 characters.

In the interest of cross-platform compatibility, use a single .r file for both macOS and Windows versions of your plug-in, like the samples do. PiPL properties must always be in macOS-specific byte order. On Windows, PiPLs are compiled by processing a .r file through pipltool.exe, which converts the .r file into a binary .rc file. The Windows sample projects all contain custom build steps which generate a .rc file, using a cross-platform .r file and our crytpipl.exe command line utility. Base your development on an existing sample plug-in and the build step will be correctly implemented.

13.1 Entry Point

Your plug-in's entry point is exported through the PiPL on Windows and macOS. If the plug-in supports multiple platforms, then multiple entry points must be defined in the PiPL. There is no need for a Windows .def file or manual exports, unless you're also designating some other OS-specific entry point.

The macros defined in entry.h (in the \SDKExamplesHeaders directory) take care of exporting each sample's entry point function. All the sample project entry point functions are EffectMain() for effects, or EntryPointFunc()for AEGPs.

13.2 PiPL Resources And Microsoft Visual Studio

To use resources from Microsoft Visual Studio .NET with pipltool-generated resources,

#include the output of the custom build steps into the Microsoft-generated .rc file.

```
// in file WhizBang.rc, generated by .NET.
#include "WhizBang_PiPL_temp.rc" // pipltool.exe's output
```

If modifying a sample plug-in, change the name of the file generated by pipltool.exe to something like WhizBang_PiPL_temp.rc, or it will overwrite the Microsoft resources each time you build; not good.

13.3 Multiple PiPLs

It is possible, but not recommended, to include multiple plug-ins (both AEGPs and effects) in the same file, using multiple PiPLs. If there are PiPLs for both AEGPs and effects in the same file, the AEGPs must come first!

No other hosts (not even Premiere Pro) support multiple PiPLs pointing to multiple effects within the same .dll or code fragment. Also, if you need to update one plug-in, do you really want to ship a new build of all your plug-ins? We recommend one PiPL, and one plug-in, per code fragment.

13.4 Super Secret PiPL Bit

For those of you who use C++ and simply *must* keep your plug-ins loaded all the time (to avoid having your v-tables trashed, among other hazards), set the PiPL's AE_Reserved_Info member to 8. Over the years we've been quite stringent, insisting that plug-ins be good memory citizens and respond gracefully to getting unloaded. We know there are cases in which being unloaded with no warning can really ruin a plug-in's day (and v-tables), and so have provided this work-around. Be nice, perform scrupulous memory management, and only use your powers for good.

13.5 Why Do I Need To Know All This?

You don't; After Effects does. If you follow our advice and base your projects on the SDK samples, you can simply change the .r file containing your PiPL definition(s), and your plug-in's resources will be automagically updated the next time you build. Feel the love. Or, if you ever tinker with the custom build steps, feel the pain.

Exceptions

Handle all exceptions generated by your plug-in's code, *within* your plug-in. Pass those which didn't originate in your plug-in's code to After Effects.

After Effects' APIs are designed for plug-ins written in C, and don't expect exceptions. After Effects will crash immediately if one is thrown from within a plug-in.

The effect samples use a firewall around the switch statement in the main() function, and the AEGPs wrap their function hooks in try/catch blocks.

Where Installers Should Put Plug-ins

Installing your plug-ins in the common location will allow them to be loaded by Premiere Pro, if installed.

On Windows, the common plug-ins folder can be found (as an explicit path) in the following registry entry: HKLM\SOFTWARE\Adobe\After Effects\[version]\CommonPluginInstallPath

On Mac, the common plug-ins folder is at: /Library/Application Support/Adobe/Common/Plug-ins/[version]/MediaCore

Version is locked at 7.0 for all CC versions, or CSx for earlier versions. For example: /Library/Application Support/Adobe/Common/Plug-ins/7.0/MediaCore/

Do not use macOS aliases or Windows shortcuts, as these are not traversed by Premiere Pro.

15.1 Do I Have To Install The Plug-ins To The Common Folder?

You may have good reason to install your plug-in for only After Effects, for example, if your plug-in depends on suites and functionality not available in Premiere Pro. We strongly recommend that you use the common folder whenever possible, but for certain cases, the AE-specific plug-in folder is still available.

On Windows, the app-specific plug-ins folder can be found (as an explicit path) in the following registry entry: \\HKEY_LOCAL_MACHINE\SOFTWARE\Adobe\After Effects\(version)\PluginInstallPath

On macOS, the app-specific plug-ins folder is at: /Applications/Adobe After Effects [version]/ Plug-ins/

When launched, After Effects recursively descends 10 levels deep into subdirectories of its path. macOS aliases are traversed, but Windows shortcuts are not. Directories terminated by parentheses or preceded by the symbols \neg (macOS) or \sim (Windows) are not scanned.

Try as you might to build a fence between AE and Premiere Pro, users will still find ways to get across using our lovely integration goodness - Your effects will still be available to Premiere Pro users who create a dynamically linked AE composition with your effect, and put it in a Premiere Pro sequence.

Localization

Starting in CC, PF App Suite (*Useful Utility Functions*) adds PF_AppGetLanguage () to query the current language so that a plug-in can use the correct language string.

When passing strings to AE, some parts of the API accept Unicode. In other areas, for example when specifying effect parameter names during PF_Cmd_PARAM_SETUP, you'll need to pass the names in a char string. For these non-Unicode strings, AE interprets strings as being multi-byte encoded using the application's current locale. To build these strings, on Windows you can use the WideCharToMultiByte() function, specifying CP_OEMCP as the first argument. On macOS, use the encoding returned by GetApplicationTextEncoding().

Testing with different languages in AE doesn't require an OS reinstallation, but it does require a reinstallation of AE:

For Win, change the system locale to the targeted language (control panel > region and language > administrative tab > change system locale), restart machine, and then install AE in the according language.

For Mac, set targeted language to the primary language in the preferred language list, and then install AE in the according language.

$\mathsf{CHAPTER}\ 17$

Next Steps

You now have an understanding of what plug-ins are, what they can do, and how After Effects communicates with them.

Next, we will cover the basics of effects plug-ins.

Effect Basics

This chapter will provide all the information you need to know to understand how a basic effect plug-in works.

These details are fundamental to every effect plug-in.

By the time you finish this chapter, you'll be ready for the fun stuff; modifying pixels!

Entry Point

All communication between After Effects and an effect plug-in is initiated by After Effects, and it all happens by the host (After Effects) calling a single entry point function.

For all effect plug-ins, the entry point function must have the following signature:

The name of the entry point function above is "main", but it can be whatever is specified in *PiPL Resources*.

Before each call to the entry point function, After Effects updates *PF_InData* and the plug- in's parameter array PF_ParamDef[] (except as noted).

After the plug-in returns from its call, After Effects checks *PF_OutData* for changes and, when appropriate, uses the PF_LayerDef the effect has rendered.

19.1 Entry Point Function Parameters

Ar-	Purpose		
gu-			
ment			
cmd	After Effects sets the <i>Command Selectors</i> to tell the plug-in what to do.		
in_da	tanformation about the application's state and the data the plug-in is being told to act upon.		
	Pointers to numerous interface and image manipulation functions are also provided.		
out_d	aRass back information to After Effects by setting fields within out_data.		
paran	nAn array of the plug-in's parameters at the time provided in in_data> current_time.		
	params [0] is the input image (a PF_EffectWorld / PF_LayerDef) to which the effect should be applied.		
	These values are only valid during certain selectors (this is noted in the <i>selector descriptions</i>).		
	Parameters are discussed at length here: <i>PF_ParamDef</i> .		
out-	The output image, to be rendered by the effect plug-in and passed back to After Effects.		
put	Only valid during certain selectors.		
ex-	The extra parameter varies with the command sent or (in the case of <i>PF_Cmd_EVENT</i>) the <i>event type</i> .		
tra	Used primarily for event management and <i>Parameter Supervision</i> .		

Command Selectors

Commands are, simply, what After Effects wants your effect to do.

Responses to some selectors are required; most are optional, though recall that we did add them for a reason...

With each command selector sent, effects receive information from After Effects in *PF_InData*, input and parameter values in PF_ParamDef[] (an array of parameter descriptions including the input layer), and access to callbacks and function suites.

They send information back to After Effects in *PF_OutData*, and (when appropriate) render output to a PF_LayerDef, also called a *PF_EffectWorld*.

During events, they receive event-specific information in *PF_EventExtra*.

20.1 Calling Sequence

Only the first few command selectors are predictable; the rest of the calling sequence is dictated by user action.

When first applied, a plug-in receives PF_Cmd_GLOBAL_SETUP, then PF_Cmd_PARAM_SETUP. Each time the user adds the effect to a layer, PF_Cmd_SEQUENCE_SETUP is sent.

For each frame rendered by a basic non-SmartFX effect, After Effects sends PF_Cmd_FRAME_SETUP, then PF_Cmd_RENDER, then PF_Cmd_FRAME_SETDOWN.

All effect plug-ins must respond to PF_Cmd_RENDER

For SmartFX, PF_Cmd_SMART_PRE_RENDER may be sent any number of times, before a single PF_Cmd_SMART_RENDER is sent.

PF_Cmd_SEQUENCE_SETDOWN is sent on exit, when the user removes an effect or closes the project. PF_Cmd_SEQUENCE_RESETUP is sent when a project is loaded or when the layer to which it's applied changes. PF_Cmd_SEQUENCE_FLATTEN is sent when the After Effects project is written out to disk.

PF Cmd ABOUT is sent when the user chooses About... from the Effect Controls Window (ECW).

PF_Cmd_GLOBAL_SETDOWN is sent when After Effects closes, or when the last instance of the effect is removed. Do not rely on this message to determine when your plug-in is being removed from memory; use OS-specific entry points.

20.2 Command Selectors Table

20.2.1 Global Selectors

All plug-ins must respond to these selectors.

Selector	Response
PF_Cmd_AF	Display a dialog describing the plug-in. Populate out_data>return_msg and After Effects will display
	it in a simple modal dialog.
	Include your plug- in's version information in the dialog. On macOS, the current resource file will
	be set to your effects module during this selector.
PF_Cmd_GI	CSEA any required flags and PF_OutData fields (including out_data>my_version) to describe your
	plug-in's behavior.
PF_Cmd_GI	্রেন্স্টের als ছাটে ক্রিম্বার্ক (only required if you allocated some).
PF_Cmd_PA	FDosc file your parameters and register them using PF_ADD_PARAM.
	Also, register custom user interface elements.
	Set PF_OutData>num_params to match your parameter count.

20.2.2 Sequence Selectors

These control sequence data handling.

Se-	Response		
lec-			
tor			
PF_Cmc	ASTROMENTALIZE any sequence-specific data. Sent when the effect is first applied. PF_InData is		
	initialized at this time.		
PF_Cmc	RECUENTE (HSUMHS HINTERTEN) sequence data. Sent after sequence data is read from disk, during pre-		
	composition, or when the effect is copied;		
	After Effects flattens sequence data before duplication. During duplication,		
	PF_Cmd_SEQUENCE_RESETUP is sent for both the old and new sequences.		
	Don't expect a PF_Cmd_SEQUENCE_FLATTEN between PF_Cmd_SEQUENCE_RESETUPs.		
PF_Cmc	F_Cmd SenowhercsavingAandEwhen duplicating the sequence. Flatten sequence data containing pointers or han-		
	dles so it can be written to disk.		
	This will saved with the project file. Free the unflat data and set the out_data>sequence_data to		
	point to the new flattened data. Flat data must be correctly byte-ordered for file storage.		
	As of 6.0, if an effect's sequence data has recently been flattened, the effect may be deleted without		
	receiving an additional PF_Cmd_SEQUENCE_SETDOWN.		
	In this case, After Effects will dispose of your flat sequence data.		
PF_Cmc	! Freqai Es equ<u>e</u>rse tiata wn		

20.2.3 Frame Selectors

Passed for each frame (or set of audio samples) to be rendered by your plug-in.

Selector	Response
PF_Cmd_FRAME_SETUP	Allocate any frame-specific data. This is sent immedi-
	ately before each frame is rendered, to allow for frame-
	specific setup data. If your effect changes the size of its
	output buffer, specify the new output height, width, and
	relative origin. All parameters except the input layer are
	valid. If you set width and height to 0, After Effects ignores
	your response to the following <i>PF_Cmd_RENDER</i> .
	NOTE: If $PF_Outflag_I_EXPAND_BUFFER$
	is set, you will receive this selector (and
	PF_Cmd_FRAME_SETDOWN) twice, once with-
	out <i>PF_Cmd_RENDER</i> between them.
	This is so we know whether or not the given layer will
	be visible.
	Frame data dates from the days when machines might
	have 8MB of RAM. Given the calling sequence (above), it's much more efficient to just allocate during
	PF_Cmd_RENDER.
PF Cmd RENDER	Render the effect into the output, based on the input
	frame and any parameters.
	This render call can only support 8-bit or 16-bit per
	channel rendering. 32-bit per channel rendering must
	be handled in PF_Cmd_SMART_RENDER.
	All fields in PF_InData are valid.
	If your response to this selector is interrupted (your
	calls to PF_ABORT or PF_PROGRESS returns an error code), your results will not be used.
	You cannot delete frame_data during this selector; you
	must wait until PF_Cmd_FRAME_SETDOWN.
PF_Cmd_FRAME_SETDOWN	Free any frame data allocated during
	PF_Cmd_FRAME_SETUP.
PF_Cmd_AUDIO_SETUP	Sent before every audio render. Request a time span
	of input audio. Allocate and initialize any sequence- specific data.
	If your effect requires input from a time span other than
	the output time span, update the startsampL and end-
	sampL field in PF_OutData.
PF_Cmd_AUDIO_RENDER	Populate <i>PF_OutData.dest_snd</i> with effect-ed audio.
	All fields in PF_InData are valid.
	If your response to this selector is interrupted (your
	calls to PF_ABORT or PF_PROGRESS returns an error
PF_Cmd_AUDIO_SETDOWN	code), your results will not be used. Free memory allocated during
II_CMd_AODIO_SEIDOWN	PF_Cmd_AUDIO_SETUP.
PF_Cmd_SMART_PRE_RENDER	SmartFX only. Identify the area(s) of input the effect
	will need to produce its output, based on whatever cri-
	teria the effect implements.
	maybe sent up to twice when MediaCore is hosting. The
	first will come during GetFrameDependencies to collect
	the inputs. The source checkouts can return full frame dimensions
	here. Once the sources are rendered, if they are different
	in size than the first call then this selector will be emitted
	a second time with the actual source sizes in order to get
20.2. Command Selectors Table	a correct output size. 53
	Note that MediaCore wants all of the output, so
	PF_PreRenderOutput::max_result_rect will be used.
	New in 16.0

20.2.4 Messaging

The communication channel between After Effects and your plug-in.

Selector	Response	
PF_Cmd_EVENT	T This selector makes use of the extra parameter; the ty	
	of event to be handled is indicated by the e_type field, a	
	member of the structure pointed to by extra.	
	See Effect UI & Events.	
PF_Cmd_USER_CHANGED_PARAM	The user changed a parameter value. You will	
	receive this command only if you've set the	
	PF_ParamFlag_SUPERVISE flag.	
	You modify the parameter to control values, or make	
	one parameter's value affect others. A parameter can be	
	modified by different actions.	
	in_data.current_time is set to the time of the	
	frame that the user is looking at in the UI (internally,	
	the current time of the comp converted into layer time)	
	while they are changing the param that triggered the	
	PF_Cmd_USER_CHANGED_PARAM.	
	It's also the time of a keyframe that is added automat-	
	ically (if there isn't one already, and the stopwatch is	
	enabled).	
	This is usually the same as the value passed for the	
	PF_Cmd_RENDER that follows immediately after (un-	
	less caps lock is down), but not necessarily – there could	
	be other comp windows open that cause a render at a	
	different time in response to the changed param.	
PF_Cmd_UPDATE_PARAMS_UI	The effect controls palette (ECP) needs to be updated.	
	This might occur after opening the ECP or moving to a	
	new time within the composition.	
	You can modify parameter characteristics (en-	
	abling or disabling them, for example) by calling	
	PF_UpdateParamUI().	
	Only cosmetic changes may be made in response to	
	this command. Don't change parameter values while	
	responding to PF_Cmd_UPDATE_PARAMS_UI; do so	
	during PF_Cmd_USER_CHANGED_PARAM instead.	
	This command will only be sent regularly if	
	PF_OutFlag_SEND_UPDATE_PARAMS_UI was	
	set in the PiPL, and during PF_Cmd_GLOBAL_SETUP.	
	NOTE: Never check out parameters during this selector.	
	Recursive badness is almost guaranteed to result.	
PF_Cmd_DO_DIALOG	Display an options dialog. this is sent when the Op-	
	tions button is clicked (or a menu command has been	
	selected).	
	This selector will only be sent if the effect has previ-	
	ously indicated that it has a dialog	
	(by setting the global PF_OutFlag_I_DO_DIALOG	
	flag in response to PF_Cmd_GLOBAL_SETUP).	
	In version 3.x, the params passed with	
	PF_Cmd_DO_DIALOG were invalid.	
	This is no longer the case; plug-ins can access non-layer	
	parameters, check out parameters at other times, and	
	perform UI updates during PF_Cmd_DO_DIALOG.	
	They still may not change the parameter's values.	
PF_Cmd_ARBITRARY_CALLBACK	Manage your arbitrary data type. You'll only receive	
PF_Cmd_ARBITRARY_CALLBACK	Manage your arbitrary data type. You'll only receive this if you've registered a custom data type parameter.	
	Manage your arbitrary data type. You'll only receive this if you've registered a custom data type parameter. The extra parameter indicates which handler function is	
	Manage your arbitrary data type. You'll only receive this if you've registered a custom data type parameter. The extra parameter indicates which handler function is being called. 55	
	Manage your arbitrary data type. You'll only receive this if you've registered a custom data type parameter. The extra parameter indicates which handler function is being called. 55 Custom data types are discussed further in <i>Implement</i> -	
PF_Cmd_ARBITRARY_CALLBACK 0.2. Command Selectors Table PF_Cmd_GET_EXTERNAL_DEPENDENCIES	Manage your arbitrary data type. You'll only receive this if you've registered a custom data type parameter. The extra parameter indicates which handler function is being called. 55	

20.3 What's The Difference?

There is a subtle difference between PF_Cmd_USER_CHANGED_PARAM and PF_Cmd_UPDATE_PARAMS_UI.

Effects need to distinguish between the user actually changing a parameter value (PF_Cmd_USER_CHANGED_PARAM), and just scrubbing around the timeline (PF_Cmd_UPDATE_PARAMS_UI), which is also sent when the plug-in is first loaded).

Only the first few command selectors are predictable; the rest of the calling sequence is dictated by user action.

When first applied, a plug-in receives PF_Cmd_GLOBAL_SETUP, then PF_Cmd_PARAM_SETUP. Each time the user adds the effect to a layer, PF_Cmd_SEQUENCE_SETUP is sent.

For each frame rendered by a basic non-SmartFX effect, After Effects sends PF_Cmd_FRAME_SETUP, then PF_Cmd_RENDER, then PF_Cmd_FRAME_SETDOWN. All effect plug-ins must respond to PF_Cmd_RENDER.

For SmartFX, PF_Cmd_SMART_PRE_RENDER may be sent any number of times, before a single PF_Cmd_SMART_RENDER is sent.

PF_Cmd_SEQUENCE_SETDOWN is sent on exit, when the user removes an effect or closes the project. PF_Cmd_SEQUENCE_RESETUP is sent when a project is loaded or when the layer to which it's applied changes. PF_Cmd_SEQUENCE_FLATTEN is sent when the After Effects project is written out to disk.

PF_Cmd_ABOUT is sent when the user chooses About... from the Effect Controls Window (ECW).

PF_Cmd_GLOBAL_SETDOWN is sent when After Effects closes, or when the last instance of the effect is removed. Do not rely on this message to determine when your plug-in is being removed from memory; use OS-specific entry points.

PF_InData

After Effects communicates system, project, layer and audio information using PF_InData. This structure is updated before each command selector is sent to a plug-in.

Fields valid only during specific *PF_Cmds* are noted.

Also, don't worry; although PF_InData is dauntingly large, you need not memorize each member's purpose; you'll use some of the fields some of the time.

21.1 PF_InData Members

Name	Description	
inter	Callbacks used for user interaction, adding parameters,	
	checking whether the user has interrupted the effect, dis-	
	playing a progress bar, and obtaining source frames and	
	parameter values at times other than the current time be-	
	ing rendered.	
	This very useful function suite is described in <i>Interac</i> -	
	tion Callback Functions.	
utils	Graphical and mathematical callbacks. This pointer is	
	defined at all times.	
effect_ref	Opaque data that must be passed to most of the various	
	callback routines.	
	After Effects uses this to identify your plug-in.	

Table 1 – continued from previous page

Name	Description
quality	The current quality setting, either PF_Quality_HI or
1 1	PF_Quality_LO.
	Effects should perform faster in LO, and more accu-
	rately in HI.
	The graphics utility callbacks perform differently be-
	tween LO and HI quality; so should your effect!
	This field is defined during all frame and sequence se-
	lectors.
version	Effects specification version, Indicate the ver-
	sion you need to run successfully during
	PF_Cmd_GLOBAL_SETUP.
serial_num	The serial number of the invoking application.
appl_id	The identifier of the invoking application.
	If your plug-in is running in After Effects, appl_id
	contains the application creator code 'FXTC'.
	If it is running in <i>Premiere Pro & Other Hosts</i> it will be
	'PrMr'.
	Use this to test whether your plug-in, licensed for use
	with one application, is being used with another.
num_params	Input parameter count.
what_cpu	Under macOS this contains the Gestalt value for CPU
	type (see Inside Macintosh, volume 6). Undefined on
	Windows.
what_fpu	Under macOS this contains the Gestalt value for FPU
	type.
	Undefined on Windows.
current_time	The time of the current frame being rendered, valid dur-
	ing <i>PF_Cmd_RENDER</i> . This is the current time in the
	layer, not in any composition. If a layer starts at other
	than time 0 or is time-stretched, layer time and composition time are distinct.
	The current frame number is current_time di-
	vided by time_step. The current time in seconds is
	current_time divided by time_scale.
	To handle time stretching, composition frame rate
	changes, and time remapping, After Effects may ask
	effects to render at non-integral times (between two
	frames).
	Be prepared for this; don't assume that you'll only be
	asked for frames on frame boundaries.
	NOTE: As of CS3 (8.0), effects may be asked to render
	at negative current times. Deal!

Table 1 – continued from previous page

Name	Description	
time_step	The duration of the current source frame being rendered. In several situations with nested compositions, this source frame duration may be different than the time span between frames in the layer (local_time_step). This value can be converted to seconds by dividing by time_scale. When calculating other source frame times, such as for PF_CHECKOUT_PARAM, use this value rather than local_time_step. Can be negative if the layer is time-reversed. Can vary from one frame to the next if time remapping is applied	
	on a nested composition. Can differ from local_time_step when source material is stretched or remapped in a nested composition. For example, this could occur when an inner composition is nested within an outer composition with a different frame rate, or time remapping is applied to the outer composition. This value will be 0 during PF_Cmd_SEQUENCE_SETUP if it is not constant for all frames. It will be set correctly during PF_Cmd_FRAME_SETUP and PF_Cmd_FRAME_SETUP and PF_Cmd_FRAME_SETDOWN selectors. WARNING: This can be zero, so check it before you divide.	
total_time	Duration of the layer. If the layer is time-stretched longer than 100%, the value will be adjusted accordingly; but if the layer is time-stretched shorter, the value will not be affected. If time remapping is enabled, this value will be the duration of the composition. This value can be converted to seconds by dividing by time_scale.	
local_time_step	Time difference between frames in the layer. Affected by any time stretch applied to a layer. Can be negative if the layer is time-reversed. Unlike time_step, this value is constant from one frame to the next. This value can be converted to seconds by dividing by time_scale. For a step value that is constant over the entire frame range of the layer, use local_time_step, which is based on the composition's framerate and layer stretch.	

Table 1 – continued from previous page

Name	Description		
time scale	The units per second that current_time,		
	time_step, local_time_step and		
	total_time are in.		
	If time_scale is 30, then the units		
	of current_time, time_step,		
	local_time_step and total_time are in		
	30ths of a second.		
	The time_step might then be 3, indicating that the		
	sequence is actually being rendered at 10 frames per		
	second. total_time might be 105, indicating that		
	the sequence is 3.5 seconds long.		
field	Valid only if PF_OutFlag_PIX_INDEPENDENT was		
	set during PF_Cmd_GLOBAL_SETUP.		
	Check this field to see if you can process just the upper		
	or lower field.		
shutter_angle	Motion blur shutter angle. Values range from 0 to 1,		
_ 3	which represents 360 degrees.		
	Will be zero unless motion blur is enabled and checked		
	for the target layer.		
	shutter_angle == 180 means the time interval		
	between current_time and current_time +		
	1/2 time_step.		
	Valid only if PF_OutFlag_I_USE_SHUTTER_ANGLE		
	was set during <i>PF_Cmd_GLOBAL_SETUP</i> .		
	See the section on <i>Motion Blur</i> for details on how to		
	implement motion blur in your effect.		
width	Dimensions of the source layer, which are not necessar-		
	ily the same as the width and height fields in the input		
	image parameter.		
	Buffer resizing effects can cause this difference. Not		
	affected by downsampling.		
height			
extent_hint	The intersection of the visible portions of the input and		
	output layers; encloses the composition rectangle trans-		
	formed into layer coordinates.		
	Iterating over only this rectangle of pixels can speed		
	your effect dramatically. See extent_hint Usage later in		
	this chapter regarding proper usage.		
output_origin_x	The origin of the output buffer in the input buffer. Non-		
	zero only when the effect changes the origin.		
output_origin_y			

Table 1 – continued from previous page

Name	Description
downsample_x	Point control parameters and layer parameter dimen-
downsampro_x	sions are automatically adjusted to compensate for a
	user telling After Effects to render only every nth pixel.
	Effects need the downsampling factors to interpret
	scalar parameters representing pixel distances in the im-
	age (like sliders).
	For example, a blur of 4 pixels should be interpreted
	as a blur of 2 pixels if the downsample factor is 1/2 in
	each direction (downsample factors are represented as
	ratios.)
	Valid only during
	• PF_Cmd_SEQUENCE_SETUP,
	·-
	• PF_Cmd_SEQUENCE_RESETUP,
	• PF_Cmd_FRAME_SETUP,
	• PF_Cmd_RENDER
downsample_y	
pixel_aspect_ratio	Pixel aspect ratio (width over height).
in_flags	Unused.
global_data	Data stored by your plug-in during other selectors.
J 111 _111	Locked and unlocked by After Effects before and after
	calling the plug-in.
sequence_data	
frame_data	
start_sampL	Starting sample number, relative to the start of the audio
	layer.
dur_sampL	Duration of audio, expressed as the number of samples.
	Audio-specific.
total_sampL	Samples in the audio layer; equivalent to total_time ex-
	pressed in samples.
src_snd	PF_SoundWorld describing the input sound. Audio-
	specific.
pica_basicP	Pointer to the PICA Basic suite, used to acquire other
	suites.
pre_effect_source_origin_x	Origin of the source image in the input buffer. Valid
	only when sent with a frame selector.
	Non-zero only if one or more effects that preceded this
	effect on the same layer resized the output buffer and
	moved the origin.
	Check for both the resize and the new origin to deter-
	mine output area.
	This is useful for effects which have implicit spatial op-
	erations (other than point controls), like flipping a file
	around an image's center.
	NOTE: Checked-out point parameters are adjusted for
	the pre-effect origin at the current time, not the time be-
	ing checked out.
pre_effect_source_origin_y	
shutter_phase	Offset from frame time to shutter open time as a per-
	centage of a frame duration.

21.2 extent hint Usage

Note: hint rectangles are much more effective... and complicated... for *SmartFX*.

Use extent_hint to process only those pixels for which output is required; this is one of the simplest optimizations you can make.

Tell After Effects you use in_data>extent_hint by setting PF_OutFlag_USE_OUTPUT_EXTENT in PF_OutData during PF_Cmd_GLOBAL_SETUP (and in your PiPL).

Disable caching from the preferences menu before testing extent_hint code, so After Effects renders your effect whenever anything in your composition changes.

Otherwise, the caching mechanism would obscure your plug-in's (possibly incorrect) output.

Move the layer within the composition so it's cropped. The output>extent_hint is the portion of the layer which is visible in the composition.

Add a mask to your layer and move it around.

This changes the extent_hint, which encloses all of the non-zero alpha areas of the image.

The in_data>extent_hint is the intersection of these two rectangles (the composition and the mask), and changes whenever they do.

Extent rectangles are computed in the coordinate space of the original input layer, before resizing and origin shifting, to simplify rectangle intersection between the input and output extents for effects which set $PF_OutFlag_PIX_INDEPENDENT$.

To get the output extent in the coordinate system of the output buffer, offset the extent_hint by the PF_InData->output_origin_x and y fields.

Account for downsampling when computing output size; users must be able to render at full resolution.

If the output buffer exceeds 30,000 by 30,000, clamp it to that size, and consider displaying an alert dialog.

Once your code behaves correctly, enable the cache and see how frequently the effect needs to re-render.

Consider a drop shadow; users frequently apply a static drop shadow to a still image.

The output>extent_hint is ignored, so the cache is used more often.

For buffer-expanding effects, intersect the output>extent_hint with your plug-in's transformed bounds and sets the size accordingly during *PF_Cmd_FRAME_SETUP*.

21.3 Now with 20% More Pixels!

As of 6.0, the extent_hints passed are 20% larger than the layer itself, to help with our predictive rendering decisions. Numerous effects expand the buffer "just a touch", and After Effects often uses the hint rectangles later.

21.4 Point Controls And Buffer Expansion

Effects which expand the output buffer position the original layer's upper left corner by setting set output_origin_x/y in PF_InData during PF_Cmd_FRAME_SETUP.

This shift is reported to subsequent effects in the pre_effect_source_origin_x/y. Point parameters are adjusted for this shift automatically.

Apply a buffer expander such as Gaussian Blur or the Resizer SDK sample, *before* your effect, and use a large resize value

If your effect is not handling pre_effect_source_origin_x/y correctly, turning the blur on and off will shift the position of the output.

All point parameter values (at any time) have shift values described by pre_effect_source_origin_x/y. For most effects this works transparently.

However, if a buffer expansion changes over time (as with an animated blur amount), the origin shift will move non-animated points.

Consider this when designing effects which cache point parameter values between frames.

		20
CHAPI	ΈR	22

PF_OutData

 $Communicate \ changes \ made \ by \ your \ plug-in \ to \ After \ Effects \ using \ \texttt{PF_OutData}. \ Valid \ times \ for \ altering \ these \ fields \ are \ noted.$

22.1 PF_OutData Members

Field	Description
my_version	Set this flag (using the PF_VERSION macro) to the version of your plug-in code.
	After Effects uses this data to decide which of duplicate effects to load.
name	Unused.
global_dat	aHandle which will be returned to you in <i>PF_InData</i> with every call.
	Use After Effects' memory allocation functions.
num_params	After Effects checks this field against the number of calls made to
	PF_ADD_PARAM, as well as the implicit input layer.
sequence_daAllocatable upon receiving PF_Cmd_SEQUENCE_SETUP, this handle will be passed back to you	
	in <i>PF_InData</i> during all subsequent calls.
flat_sdata	_Universed (After Effects knows the size, because you used its allocation functions to get the memory
	in the first place).
frame_data	Handle you (might have) allocated during <i>PF_Cmd_FRAME_SETUP</i> .
	This is never written to disk; it was used to pass information from your <i>PF_Cmd_FRAME_SETUP</i>
	response to your PF_Cmd_RENDER or PF_Cmd_FRAME_SETDOWN (which you must do if you
	resize the output buffer).
	Otherwise, this memory is rarely used.
width,	Set during <i>PF_Cmd_FRAME_SETUP</i> if the output image size differs from the input.
height,	width and height are the size of the output buffer, and origin is the point the input should
origin	map to in the output.
	To create a 5-pixel drop shadow up and left, set origin to (5, 5).
out_flags	Send messages to After Effects. OR together multiple values.
return_msg	After Effects displays any C string you put here (checked and cleared after every command selec-
	tor).
start_sampLUsed only for Audio commands	
dur_sampL,	
dest_snd	
out_flags2	Send messages to After Effects. OR together multiple values.

22.2 PF_OutFlags

These flags communicate capability and status information to After Effects. In previous versions they were also used to send rudimentary messages, e.g. refresh the UI, send an error message.

These capabilities have been supplanted by function suites, and all new messaging functions will come in that format. However, capability flags are still contained in the *PiPL*.

Update both the PiPL and your source code when you make a change. Many of these flags can be changed during an After Effects session.

Flag	Indicates
PF_OutFlag_KEEP_RESOURCE_OPEN	The plug-in's resources must be available during all
	commands.
	During <i>PF_Cmd_GLOBAL_SETUP</i> , the plug-in's re-
	sources are always open, but unavailable at all
	other times (except during <i>PF_Cmd_ABOUT</i> and
	PF_Cmd_DO_DIALOG), unless this flag has been set.
	Set if you need access to resources at any time other
	than during PF_Cmd_GLOBAL_SETUP.
	NOTE: We recommend the plug-in load and store the
	necessary resources in global data, rather than keeping
	the file's resources open.
PF_OutFlag_WIDE_TIME_INPUT	The effect checks out a parameter at a time other than
	current_time.
	If you use a parameter (including layer parameters)
	from another time, set this flag.
	Otherwise, After Effects won't correctly invalidate
	cached frames used by your effect.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> .
	If you set this flag, we strongly recommend you also set
	PF_OutFlag2_AUTOMATIC_WIDE_TIME_INPUT
	for better performance.
PF_OutFlag_NON_PARAM_VARY	With this flag set, After Effects will not cache output
	when the effect is applied to a still.
	Otherwise, After Effects will cache your output to be
	used to render other frames, if possible.
	Set this flag if output varies based on something besides
	a parameter value.
	If the effect produces changing frames when applied to a
	still image and all parameters are constant, that's a sure
	sign that this bit should be set (e.g. Wave Warp).
	Particle effects, for example, will need this.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> .
	Can be overridden dynamically if needed during
	PF_Cmd_QUERY_DYNAMIC_FLAGS.
	Turn this off whenever possible to improve perfor-
	mance.
PF_OutFlag_RESERVED6	Unused. Formerly
11 <u>-</u> 0401 149 <u>-</u> 111011111120	PF_OutFlag_SEND_PARAMS_UPDATE. Replaced
	by PF_OutFlag_REFRESH_UI.
PF OutFlag SEOHENCE DATA NEEDS FLAT	TEN I Bo th After Effects and Premiere Pro assume this flag is
1.1oger tgd_on&onigon_bitti_ignnpo_t nyt	set.
	Flattening is necessary when sequence data contains ref-
	erencing items (pointers, handles), which must be flat-
	tened for storage and unflattened for use.
	See <i>PF_Cmd_SEQUENCE_RESETUP</i> .
	SEE FF_CHIM_SEQUENCE_KESEIUF.

Continued on next page

22.2. PF_OutFlags 67

Table 1 – continued from previous page

Flag	Indicates
PF_OutFlag_I_DO_DIALOG	Effect displays a dialog in response to
II_Outriag_I_DO_DIADOG	PF_Cmd_DO_DIALOG.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> , checked during
	PF_Cmd_SEQUENCE_SETUP.
	Note: the effect's response to
	PF_OutFlag_I_DO_DIALOG is not undoable. You
	can use arbitrary data with a custom UI, should such
	changes become necessary.
PF_OutFlag_USE_OUTPUT_EXTENT	Effect honors the output extent_rect. Set during
	PF_Cmd_GLOBAL_SETUP.
	See details at the end of the chapter for proper usage.
	Note: Obsolete for SmartFX.
PF_OutFlag_SEND_DO_DIALOG	Effect must show dialog to function (added for compat-
	ibility with Photoshop plug-ins).
	After Effects sends PF_Cmd_DO_DIALOG after
	PF_Cmd_SEQUENCE_SETUP.
	Set during <i>PF_Cmd_SEQUENCE_RESETUP</i> , not dur-
	ing PF_Cmd_GLOBAL_SETUP.
PF_OutFlag_DISPLAY_ERROR_MESSAGE	Display the contents of return_msg in an error dia-
	log.
	Whenever return_msg is non-NULL, After Effects dis-
	plays the contents in a dialog, which will be an error
	dialog if this flag is set.
	Set after any command, and can be used during debug-
	ging.
	This is also a good way to implement nag messages for
	tryout versions.
PF_OutFlag_I_EXPAND_BUFFER	Effect expands the output buffer.
-	Set during PF_Cmd_GLOBAL_SETUP.
	Set this flag and PF_OutFlag_USE_OUTPUT_EXTENT
	to use the intersection of the output extent_rect and
	your new buffer size during <i>PF_Cmd_FRAME_SETUP</i> .
	Use pre_effect_source_origin fields to detect
	other transformations.
	Note: Only set this flag if you need to; it drastically
	reduces caching efficiency.
	Note: Obsolete for SmartFX.
PF_OutFlag_PIX_INDEPENDENT	A given pixel is independent of the pixels around it.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> or
	PF_Cmd_QUERY_DYNAMIC_FLAGS.
	As an example, color correction effects are typically
	pixel independent, distortions are not.
	NOTE: If your effect doesn't use the color values of one
	pixel to affect those of adjacent pixels, set this outflag!
	It can provide dramatic performance improvements.
PF_OutFlag_I_WRITE_INPUT_BUFFER	The effect writes into the input buffer.
rr_outriag_r_wkrrz_rnrur_burrzk	This is of limited use; while saving an allocation,
	it invalidates some pipeline caching. Set during
	PF_Cmd_GLOBAL_SETUP.

Continued on next page

Table 1 – continued from previous page

Flag	Indicates
PF_OutFlag_I_SHRINK_BUFFER	The effect shrinks its buffer based on the
Pr_Outriag_i_Shrink_Borrer	extent_rect in order to be more memory effi-
	cient.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> whenever pos-
	sible.
	Note: Obsolete for SmartFX.
PF_OutFlag_WORKS_IN_PLACE	Unused.
PF_OutFlag_SQUARE_PIX_ONLY	Unused.
PF_OutFlag_CUSTOM_UI	The effect has a custom user interface and requires
FF_OUCFIAG_COSTOM_OT	PF_Cmd_EVENT messages.
	Set during <i>PF_Cmd_GLOBAL_SETUP</i> .
PF_OutFlag_RESERVED5	Unused.
PF_OutFlag_REFRESH_UI	Refresh the entire effect controls, composition, and
Pr_Outriag_REFRESH_OI	layer windows.
	Set during <i>PF_Cmd_EVENT</i> , <i>PF_Cmd_RENDER</i> , and
	PF_Cmd_DO_DIALOG.
	If refreshing custom UI during PF_Cmd_EVENT, we
	recommend using the <i>new redraw mechanism</i> with finer
	granularity.
PF_OutFlag_NOP_RENDER	Set this flag during <i>PF_Cmd_FRAME_SETUP</i> to inval-
11_04011490121321	idate the current render.
PF_OutFlag_I_USE_SHUTTER_ANGLE	Indicates rendered images depend upon the value of
11_0001109_1_002_00011210_111022	shutter_angle.
PF_OutFlag_I_USE_AUDIO	Effect's parameters depend on audio data, obtained us-
_	ing PF_CHECKOUT_LAYER_AUDIO.
PF_OutFlag_I_AM_OBSOLETE	Effect is available for use when working with an old
-	project in which it was originally applied, but doesn't
	appear in the effect menu.
PF_OutFlag_FORCE_RERENDER	Effect made a change that requires a re-render.
	PF_ChangeFlag_CHANGED_VALUE also forces a re-
	render.
PF_OutFlag_PiPL_OVERRIDES_OUTDATA_OUT	FLAGER Effects will use PiPL outflags, and ignore those
	set during <i>PF_Cmd_GLOBAL_SETUP</i> .
PF_OutFlag_I_HAVE_EXTERNAL_DEPENDENCI	
	If set, After Effects sends
	PF_Cmd_GET_EXTERNAL_DEPENDENCIES.
PF_OutFlag_DEEP_COLOR_AWARE	The effect handles 16-bpc color.
PF_OutFlag_SEND_UPDATE_PARAMS_UI	Set this flag during PF_Cmd_GLOBAL_SETUP to re-
	ceive PF_Cmd_UPDATE_PARAMS_UI.
PF_OutFlag_AUDIO_FLOAT_ONLY	Effect requires audio data in PF_SIGNED_FLOAT for-
	mat.
	After Effects will perform any required format conver-
	sion.
	You must also set either
	PF_OutFlag_AUDIO_EFFECT_TOO or
	PF_OutFlag_AUDIO_EFFECT_ONLY.

Continued on next page

22.2. PF_OutFlags 69

Table 1 – continued from previous page

Flag	Indicates
PF_OutFlag_AUDIO_IIR	Set during <i>PF_Cmd_GLOBAL_SETUP</i> if the (audio) ef-
	fect is an Infinite Impulse Response filter.
	This is true if output at a given time depends on output
	from previous times.
	When an IIR filter receives
	PF_Cmd_AUDIO_RENDER, the input audio time
	span is the same as the output audio time span (when
	they intersect with the output time span requested in
	PF_Cmd_AUDIO_SETUP).
	In response to <i>PF_Cmd_AUDIO_SETUP</i> , the filter can
	request audio from earlier times (as for delay effects).
	The filter can access parameters from that earlier time,
	and should cache them (along with interim audio) in se-
	quence data.
	If the audio generated does not correspond to the re-
	quested output audio's time, the output audio duration
	should be set to zero.
	The filter can update its delay line using the parameters
	and the input audio.
	Having cached its delay line, request more input au-
	dio during PF_Cmd_AUDIO_SETUP based on the last
	cached delay line. Use PF_HasParamChanged to de-
	termine whether or not your cache is valid.
PF_OutFlag_I_SYNTHESIZE_AUDIO	Set during <i>PF_Cmd_GLOBAL_SETUP</i> time if the ef-
	fect generates audio, even when passed silence. You must also set either
	PF_OutFlag_AUDIO_EFFECT_TOO or PF_OutFlag_AUDIO_EFFECT_ONLY.
DE Outelog MIDIO ERRECT TOO	Set during PF_Cmd_GLOBAL_SETUP if the effect al-
PF_OutFlag_AUDIO_EFFECT_TOO	ters audio.
DE Outelog MIDIO EFFECT ONLY	Set during <i>PF_Cmd_GLOBAL_SETUP</i> if the effect al-
PF_OutFlag_AUDIO_EFFECT_ONLY	ters only audio output.
	ters only audio output.

22.3 PF_OutFlags2

We added a second set of outflags in After Effects 5.0; partly for room to expand in the future, and partly to break ourselves of the bad habit of repurposing existing flags.

As with PF_OutFlags, many of these flags can be changed during an After Effects session.

And don't forget to update both the *PiPL* and your source code when you make a change.

Flag	Indicates
	F Nothing yone
	FTherefeffectpresponds over one and during
11_000	PF_Cmd_GLOBAL_SETUP.
DF Out	F The effect usies sen 3 December information.
	F Thejeffect usiesses 3DIGHtting information.
	F This Alag Ar Aselfarosof to control the atale of the parane group twirlies.
11_000	The initial collapse state of each individual parameter group is set during <i>PF_Cmd_PARAM_SETUP</i> , by
	setting the <i>PF_ParamFlag_START_COLLAPSED</i> flag in <i>PF_ParamFlags</i> . but those individual settings
	will not be honored unless the effect sets this bit.
	Otherwise, all parameter groups will be collapsed by default.
	Remember to set this flag in both the PiPL and here during <i>PF_Cmd_GLOBAL_SETUP</i> .
PF Out	FCurrently Alvis Telesca Dockshing. If this sounds interesting to you, you may be interested in
11_000	PF_OutFlag2_PPRO_DO_NOT_CLONE_SEQUENCE_DATA_FOR_RENDER, described below.
PF Out	F Originally, is determined the state of the
	F Added for render optimizations yshrinks the input buffer passed to the effect to exclude any empty pixels
11_000	(where empty means "zero alpha" unless PF_OutFlag2_REVEALS_ZERO_ALPHA is set, in which
	case RGB must be zero as well).
	Set during PF_Cmd_GLOBAL_SETUP or PF_Cmd_QUERY_DYNAMIC_FLAGS.
	The origin of the trimmed buffer can be found in in_data>pre_effect_source_origin.
	Effects with both this flag and PF_OutFlag_I_EXPAND_BUFFER set may get called with a null input
	buffer if their input is completely empty, and must be able to handle this case without crashing.
	Note: this flag can cause the size of the output buffer to change.
	Note: Obsolete for SmartFX.
PF Out	F This âs the vea flag implementers need to pay most attention to since it represents a change in the default
	behavior.
	Set this flag if the effect can take pixels with zero alpha and reveal the RGB data in them (like our Set
	Channels effect).
	This tells After Effects not to trim such pixels when determining the input for the effect.
	This flag can be changed during <i>PF_Cmd_QUERY_DYNAMIC_FLAGS</i> .
	Note that, while this flag can cause changes to the size of the extent_hint, it will not change the
	image buffer size.
	As of 6.0, pixels outside the mask's bounding box are zeroed.
	If your effect can reveal such pixels, tell AE not to throw away these RGB values by setting this flag.
	If your effect does not always reveal such pixels, set this bit dynamically.
	To see if your effect needs this bit set, apply a mask significantly smaller than the layer to a solid, then
	apply the effect and set it to its alpha-modifying state.
	If the rectangular bounding box of the mask becomes visible, this bit needs to be set.
	F Pregerve Hrise pixels! FULLY_OPAQUE_PIXELS
	FThe effect dreams Samarx Applinder
PF_Out	FThe effect supports 32 topa Marting point color representation.
	NOTE: PF_OutFlag2_SUPPORTS_SMART_RENDER must also be set.
PF_Out	F This âs for effects which septimized nondifference of spaces in Premiere Pro. See the Premiere Pro SDK
	for more details.
PF_Out	F Setting Ihis Munimp RECAMEDGLOBAL_SETUP puts the effect in the localized "Obsolete" folder in the
	Effects panel.
DE 0 1	Compare to PF_OutFlag_I_AM_OBSOLETE.
PF_Out	F Supported no Premiero Pro, Landinos in Quiter Effects TA_FOR_RENDER
DE Out	This affects how Premiere Pro drives the plug-in using Multithreading.
rr_Out	F Setgining POMADUL CHIPPA/TIME UPNPUT Requires setting of RE Out Flag MIDE TIME INDUT (which allows you to support old hosts) but
	Requires setting of PF_OutFlag_WIDE_TIME_INPUT (which allows you to support old hosts), but effectively overrides that flag.
	When set, all parameter checkouts are tracked so over-time dependencies are known by the host, and
	much more efficient.
	For example if you set only the old DE Outelow WIDE TIME INDUT anytime anything abandon
22.3. PF	For example, if you set only the old PF_OutFlag_WIDE_TIME_INPUT, anytime anything changes outFlags2 at any time upstream from your effect, you will be called to re-render.
	With this flag set, if a given frame 17 has checked out things from times 0-17, AE will know that any
	changes at frames 18+ will not affect that cached frame.
	Note that if you use this new flag, you must not cache any time-dependent data in your sequence
	I wote that it you use this new mag, you must not cache any time-dependent data in your sequence

Parameters

Parameters are streams of values that vary with time; the source image, sliders, angles, points, colors, paths, and any arbitrary data types the user can manipulate.

They are passed to the plug-in as an array of PF_ParamDefs, though the values in the array are only valid during certain selectors.

One of the best aspects of the After Effects effect API is the parameter interpolation and management.

How much does the shutter angle change during one-fourth of a 29.97 fps frame? Not your problem; leave it to After Effects.

Describe your plug-in's parameters during PF_Cmd_PARAM_SETUP, using PF_ADD_PARAM.

You may have up to (approximately) 38 kajillion parameters, or as many as your users are willing to sift through before demanding a refund. Choose wisely.

Avoid countless problems by clearing *PF_ParamDefs* with *AEFX_CLR_STRUCT* (defined in *AE_Macros.h*) before registering them.

23.1 Parameter Types

Da	Do	חרו	D-13	DD# Institution
Pa-	Pa-			Description
ram-	ram-		1- Value	
eter	e-	ber	Data	
Type	ter		Type	
	Туре			
PF_Pá	ar <i>Pal</i> fin_ <i>I</i>	Idaja kontiji	<i>ef</i> A_1o	rignage and audio layers in the composition. All effects automatically have at least 1
				layer parameter, param[0], the layer to which they are applied.
				When used as effect parameters, these appear as a pull-down menu with which the
				user selects a layer within the current composition.
				The pull-down menu contents are generated by After Effects.
				NOTE: This is a reference to a layer which contains pixels and audio samples, not
				actual pixels and audio samples.
PF Pá	arPalm S	Sisidde	Rlefic	No longer used.
				Example Cated. For many years, we promoted fixed sliders. We now recommend
				PF_Param_FLOAT_SLIDERs.
				The additional precision helps in many situations, and isn't as expensive as it once
				was. Plus, we're just tired of low byte / high byte silliness.
				FIX_SLIDERS provide higher precision than PF_Param_SLIDER. Specify the UI
				decimal places independently. Ignore the low word of the PF_Fixed to get integral
				results.
PF P:	an Palim li	⋤ ॗऻऻढ़ ॎॶऒऻॱॿ	rs ienata	Estates. ESTATE SELIDERS contain values for phase, pre-
c				cision, and curve tolerance for use by audio filters.
				Specify a minimum and maximum value, and the user can move a slider or types a
				number to specify the setting.
				PF_Param_FLOAT_SLIDERs also respond to slider flags discussed in <i>Audio Fil</i> -
				ters.
ם מת	- 20-Teb 7	MARKETT A.	7 3 4 4 7	iAngles in (fixed point) degrees, accurate to small fractions of a degree.
PF_Pc	al leani <u>l</u>	eripanam es	Der -	
DE D	DE C	MALIE CAL	ADENTA I	Users can specify multiple revolutions, resulting in values greater than 360.
				#REL Dear amFlag_CANNOT_INTERP is forced on for all checkboxes.
PF_Pa	anam (DEE_P	iRGB value (alpha is not used) that the user can choose either with the standard color
				picker or with an eye dropper tool.
		1-2		For floating point accuracy, use <i>PF_ColorParamSuite1</i> to retrieve the values.
PF_Pá	arban I	Podiant	D€£_£	iA two-dimensional point. The point provides x and y values in destination layer space.
				The origin of the layer is the upper-left hand corner, with x increasing to the right, y
				increasing down.
				Starting in CS5.5, for floating point accuracy, use <i>PF_PointParamSuite1</i> to retrieve
				the values.
				Dusty history lesson to follow: Prior to API specification version 12.1 (After Effects
				4.0), the default value for the point was between 0 and 100 in fixed point with the
				radix point at bit 16 (i.e. standard fixed point).
				Specifying (50,50) in fixed point yields the center of the image. The value you are
				returned for a point control is in absolute pixels with some number of bits of fixed
				point accuracy.
				Thus, if you gave (50,50) as the default position and the user applied the effect to a
				640 by 480 layer, the default value you would be sent would be (320, 240) in Fixed
				point.
				Plug-ins which specify API versions before 12.1 will still get the old behavior.
PF_Pa	arPalm <u>I</u>	Popoliți	P <u>af</u> l∮	racist of choices. Build a string in namesptr containing a list of (read-only) pop-up
				entries ("Entry1 / Entry2 / Entry3").
				After Effects copies the data and creates a pop-up menu.
				These entries cannot be modified once the parameter is added.
	<u></u>			An entry of "(-" will result in a separator being drawn between previous and subse-
23.1. F	arame	eter Tv	vpes	quent entries. 75
PF_Pa	arBalin Z	Avilloni libri	hrafairyad	<u></u> ∰ATST ®m data type.
			?	Arbitrary Data Parameters contain an ID (you can use more than one custom data
		1	1 1	type in a given effect), a default value (so After Effects knows what your data type

type in a given effect), a default value (so After Effects knows what your data type

should start as) and a handle to your actual parameter

23.2 Slider Range Issues?

If your slider seems disabled but not grayed out, check the valid_min, slider_min, valid_max and slider_max fields. Is the param a PF_Param_FIX_SLIDER? If so, did you convert your mins and maxs to reasonable fixed values? If you're using the macros provided in AE_Macros.h, they're expecting to receive ints; passing fixed point values won't work.

23.3 Point Parameter Origin

After Effects modifies any point parameter to account for origin offset, introduced by "upstream" effects that modify the output dimensions. Even if the ECP UI indicates the value of the point parameter is (0,0), the offset has already been factored in.

PF_ParamDef

After Effects passes effects an array of PF_ParamDefs with each selector, describing the plug-in's parameters at the current time. The values in the params array are only valid during some selectors (this is noted in the *selector descriptions*).

24.1 Param Zero

The first parameter, params[0], is the input image (a *PF_EffectWorld / PF_LayerDef*) to which the effect should be applied.

24.2 The Rest Of The Parameters

All parameter types are represented by a PF_ParamDef. Unions are used, so that only the pertinent parts of the PF_ParamDef need be (or should be) populated.

24.3 PF_ParamDef Members

Data	Name	Description		
Type				
A_long	id	The ID of this parameter. You can re-order parameters in future versions of your plug-in and		
		not cause users to re-apply your effect,		
		if you maintain the parameter's ID across versions.		
PF_Chan	gehange	e_Set if 9xou've changed a parameter value. Only valid during drag (not click!) events,		
		PF_Cmd_USER_CHANGED_PARAM or PF_Cmd_UPDATE_PARAMS_UI.		
PF_Paran	UIE <u>la</u> gka	Specify a parameter's UI behavior before adding; only		
		PF_PUI_DISABLED may be set during event handling.		
A_short	A_short ui_wi@tWidth of the parameter's user interface (for non-standard parameters only).			
A_short	ui_he:	4 Height of the parameter's user interface (for non-standard parameters only).		
PF_Paran	Tppæram_	tType of parameter.		
A_char[3 1 14 mè	Name of parameter. Can be changed during event handling.		
		Yes, longer parameter names have been requested since After Effects 1.0.		
		Think of adequately describing your world-altering effect in 31 mere characters as a language		
		challenge, like haiku.		
PF_Paran	<i>Ffdg</i> args	Specify a parameter's UI behavior before adding; only		
		PF_ParamFlag_COLLAPSE_TWIRLY may be set during event handling.		
PF_Para	mDefUn	cAn union of all possible <i>Parameter Types</i> .		
		Only the type specified by param_type contains meaningful data.		

24.4 Parameter UI Flags

Control a parameter's user interface with these flags.

Don't confuse UI flags with behavior flags; they reside in different fields within your parameter's definition, and will cause unpredictable behavior if misapplied.

Flag	Description
PF_PUI_TOPIC	Set this flag if you handle PF_Cmd_EVENTs for the
	"topic" of the parameter.
	The "topic" is the portion of the param UI in the Effect
	Controls Window (ECW) that is still visible when the
	twirly-arrow is twirled up for that param.
	set PF_OutFlag_CUSTOM_UI at
	PF_Cmd_GLOBAL_SETUP time.
PF_PUI_CONTROL	Set this flag if you handle PF_Cmd_EVENTs for the
	control area (area that becomes invisible when you twirl
	up a parameter's spinner) in the ECP.
	If you set this flag, you must also
	set PF_OutFlag_CUSTOM_UI at
	PF_Cmd_GLOBAL_SETUP time.
	See Effect UI & Events for more details.
PF_PUI_STD_CONTROL_ONLY	Set this flag if you want the standard control only –
	No data stream will be associated with this parameter,
	and thus no keyframes will be available in the Timeline
	panel.
	You might want to do this to control something in your
	sequence data with a standard control.
	Or in your arb data, or custom UI in the comp window,
	or to group-set multiple other controls.
	This flag cannot be used with:
	• PF_Param_CUSTOM,
	• PF_Param_NO_DATA,
	• PF_Param_LAYER,
	• PF_Param_ARBITRARY_DATA,
	• PF_Param_PATH.
	If you set this flag, you must also set
	PF_ParamFlag_SUPERVISE (otherwise you
	would never find out about value changes, and the
	setting would never be used for anything).
	This flag does not require that the
	PF_OutFlag_CUSTOM_UI flag be set.
	PF_Param_ARBITRARY_DATA, just add one
	(or more) using PF_PUI_STD_CONTROL_ONLY with
	the supported param types, and then when handling
	PF_Cmd_USER_CHANGED_PARAM you can modify
	your arb data.
PF_PUI_NO_ECW_UI	Set this flag if you want no UI to appear in the Effect
	Controls Window.
	Presumably, you are setting the value of the pa-
	rameter through some other method (e.g. cus-
	tom UI in the comp window, or while handling
	PF_Cmd_USER_CHANGED_PARAM for a different
	param with PF_ParamFlag_SUPERVISE set).
	In AE, this doesn't affect keyframe visibility in the time-
	line. In PPro it does remove the entire row, so you won't
	see keyframes.
DE DIIT ECM CEDADATOD	Not used in After Effects, but used in Premiere. Set this
PF_PUI_ECW_SEPARATOR	
	flag if you'd like a thick line above this parameter in the
4.4. Danamata III El	effect control window.
4.4. Parameter UI Flags	This is provided so that parameters can be groupe 7
	visually, if needed (without adding groups).
	This flag can be changed at runtime through the

In addition to these flags, an effect parameter may be hidden or shown by using AEGP_GetDynamicStreamFlags.

24.5 Parameter Flags

Behavior flags and UI flags describe different qualities of a parameter. Set them *before* adding the parameter during *PF_Cmd_PARAM_SETUP*. Flags which may be set during events are noted.

Flag	Meaning
PF_ParamF	a <u>Par@Andrecotoes Inderaty</u> Redith time; no keyframe control will be provided in the Timeline panel.
PF_ParamF	a <u>Maluer Mare no</u> t a ligatraically interpolated.
	You can still use discontinuous (hold) interpolation. Useful for parameters which are either on or
	off. Accelerates rendering.
PF_ParamF	aSetChis flag during PRLAmd_USER_CHANGED_PARAM.
	This bit can now be set & cleared when handling PF_Cmd_UPDATE_PARAMS_UI and
	PF_Cmd_USER_CHANGED_PARAM messages, so as to twirl your parameters and groups up
	and down at will.
PF_ParamF	aSetSUPERIVE SE_Cmd_USER_CHANGED_PARAM messages for this parameter.
	See Parameter Supervision for more information.
PF_ParamF	aGontToARthetwirl-Amerit a topic spinner.
	Can be changed during parameter supervision, not just during <i>PF_Cmd_PARAM_SETUP</i> .
	This flag will not be honored unless <i>PF_OutFlag2_PARAM_GROUP_START_COLLAPSED</i> is set.
PF_ParamF	a Finis Smly Affects the Roading DR outjects saved with an older version of the effect which lacks
	parameters added later.
	When set, the PF_ParamDef.value field set in PF_ADD_PARAM() will be used to initialize
	the missing parameter, but the dephault field will still be used for initial value of the parameter
	when the effect is newly applied or reset.
	This is useful for when you want a parameter to default to one value but need it set to something
	else to preserve rendering behavior for older projects.
PF_ParamF	aBremaere Pro Amam_Only Tradicktor tayer parameters. Indicates that a layer param is used as a
	track-matte with applied filters.
	Ignored in After Effects.
PF_ParamF	a <u>Onlyxic leviant_if Richeffer v rets</u> mpudr <u>il the Norlit omatic_wide_time_input</u> and will call
	PF_AreStatesIdentical or PF_HaveInputsChangedOverTimeSpan
PF_ParamF	aNew kin CSKE Wethis parameternis unbidden, then this flag tells After Effects to not twirl open any
	parents and to not scroll the parameter into view in the Effect Controls panel and the Timeline
	panel.
	After Effects uses this behavior internally when paint strokes are made, so as not to distract the
	user by revealing the parameter. However, in another case, when turning on Time Remapping, that
	parameter is revealed.
	So we provide you the same control over parameters in your own effects.

24.6 PF_ValueDisplayFlags

Within PF_ParamDefUnion, PF_FloatSliderDef and PF_FixedSliderDef both have a member variable, PF_ValueDisplayFlags, which allows them to respond to the user's pixel value display preference (which they set

in the info palette). If this is set, the parameter's value will be displayed as 0-1, 0-255, 0-32768, or 0.0 to 1.0, depending on the preference. You can also set the first bit (PF_ValueDisplayFlag_PERCENT) to append a percent sign to the parameter's displayed value.

We know you'd never do anything like this, but if you create a parameter which displays as a percentage, don't confuse the user by allowing any range other than 0 to 100. Please. Percent means 'out of one hundred'.

			\cap	与
CHA	PI	FF	\mathbf{R}	\Box

PF_EffectWorld / PF_LayerDef

After Effects represents images using PF_EffectWorlds, also called PF_LayerDefs.

25.1 PF_EffectWorld Structure

Item	Description
world_flags	Currently, the only flags are:
	• PF_WorldFlag_DEEP - set if the world is 16-
	bpc
	PF_WorldFlag_WRITEABLE - indicates that
	you are allowed to alter the image data of the
	world.
	Normally effects cannot alter input image data; only
	output.
data	Pointer to image data, stored as a PF_PixelPtr.
	Do not access directly; use the <i>PF_PixelPtr Accessor</i>
	Macros.
	Image data in After Effects is always organized in se-
	quential words each containing Alpha, Red, Green, Blue
	from the low byte to the high byte.
rowbytes	The length, in bytes, of each row in the image's block
	of pixels. The block of pixels contains height lines each
	with width pixels followed by some bytes of padding.
	The width pixels (times four, because each pixel is four
	bytes long) plus optional extra padding adds up to row-
	bytes bytes. Use this value to traverse the image data.
	Platform-specific padding at the end of rows makes it
	unwise to traverse the entire buffer. Instead, find the
	beginning of each row using height and rowbytes.
	NOTE: This value does not vary based on whether field
	rendering is active.
	NOTE: Input and output worlds with the same dimen-
	sions can use different rowbytes values.
width	Width and height of the pixel buffer.
height	
extent_hint	The smallest rectangle encompassing all opaque (non-
	zero alpha) pixels in the layer. This defines the area
	which needs to be output.
	If your plug-in varies with extent (like a diffusion
	dither), ignore this and render the full frame each time.
pix_aspect_ratio	The pixel aspect ratio expressed as a PF_Rational.
	NOTE: Effects can use this value for checked out layers,
	but must use PF_InData.pixel_aspect_ratio
1	for the layer to which they're applied. Sorry.
platform_ref	No longer used in CS5.
	Platform-specific reference information. On Windows, this contains an energy value. On magOS
	dows, this contains an opaque value. On macOS,
	PF_GET_PLATFORM_REFS provides a CGrafPtr
	and a GDeviceHandle from a PF_EffectWorld.
	NOTE: You cannot acquire a platform_ref during
	PF_Cmd_GLOBAL_SETUP, as there isn't any output
alamba wil b	context yet. Patience, my pet.
dephault	For layer parameters only.
	Either PF_LayerDefault_MYSELF or
	PF_LayerDefault_NONE.

25.2 New In 16.0

During PF_Cmd_SMART_RENDER_GPU, PF_LayerDef will be filled out the same as it is for regular CPU renders, but PF_LayerDef.data will be null; all other fields will be valid.

25.3 Rowbytes In PF_EffectWorlds

Don't assume that you can get to the next scanline of a PF_EffectWorld using (width * sizeof(current pixel type)) + 4, or whatever; use the PF EffectWorld's rowbytes instead.

Never write outside the indicated region of a PF_EffectWorld; this can corrupt cached image buffers that don't belong to you.

To test whether your effects are honoring the PF_EffectWorld>rowbytes, apply the Grow Bounds effect after your effect.

The output buffer will have larger rowbytes than the input (though it will still have the same logical size).

25.4 Byte Alignment

The pixels in a PF_EffectWorld are not guaranteed to be 16-byte-aligned. An effect may get a subregion of a larger PF_EffectWorld. Users of Apple's sample code for pixel processing optimization, you have been warned.

Beyond 8-bit per channel color, After Effects supports 16 bit and 32-bit float per-channel color.

Effects will never receive input and output worlds with differing bit depths, nor will they receive worlds with higher bit depth than they have claimed to be able to handle.

25.5 Accessor Macros For Opaque (Data Type) Pixels

Use the following macros to access the data within (opaque) PF_PixelPtrs.

It is, emphatically, *not* safe to simply cast pointers of one type into another! To make it work at all requires a cast, and there's nothing that prevents you from casting it incorrectly. We may change its implementation at a later date (at which time you'll thank us for forcing this level of abstraction).

25.2. New In 16.0 85

25.6 PF_PixelPtr Accessor Macros

Macro	Purpose
PF_GET_PIXEL_DATA16	Obtain a pointer to a 16-bpc pixel within the specified world. The returned pixel pointer will be NULL if the world is not 16-bpc. The second parameter is optional; if it is not NULL, the returned pixel will be an interpretation of the values in the passed-in pixel, as if it were in the specified PF_EffectWorld.
	<pre>PF_GET_PIXEL_DATA16 (PF_EffectWorld wP, PF_PixelPtr</pre>
PF_GET_PIXEL_DATA8	Obtain a pointer to a 8-bpc pixel within the specified world. The returned pixel pointer will be NULL if the world is not 8- bpc. The second parameter is optional; if it is not NULL, the returned pixel will be an interpretation of the values in the passed-in pixel, as if it were in the specified PF_EffectWorld.
	<pre>PF_GET_PIXEL_DATA8 (PF_EffectWorld wP, PF_PixelPtr</pre>

Think of PF_GET_PIXEL_DATA16 and PF_GET_PIXEL_DATA8 as safe (ahem) casting routines.

The code required is actually very simple to get a PF_Pixel16* out of the PF_EffectWorld output:

This returns deep_pixelP as NULL if the world does not have deep pixels.

The second parameter is not used very often and should be passed as NULL; pass a PF_PixelPtr that is *not* contained in a PF_EffectWorld to coerce it to the depth of that PF_EffectWorld).

Errors

Always, always (always!) return a PF_Err from main (). Plug-ins must pass all errors back to After Effects.

It is vitally important that you pass any errors (returned to you by callbacks and PICA suites) to After Effects, unless you've handled them.

Be vigilant about returning the right error code, and disposing of any memory you've allocated.

Really. We're serious.

26.1 Error Codes

Error	Meaning
PF_Err_NONE	Success.
PF_Err_OUT_O	METMOTY allocation failed.
	Note that RAM preview will cause this condition, so After Effects will be expecting to receive
	this error from your plug-in.
PF_Err_INTER	NA Tobsensussing a Maia structure.
PF_Err_INVAL	I Prathensk finding/using array member.
	OPNOINIEM <u>v</u> eikhpan <u>arnièter</u> data.
PF_Err_INVAL	IProblemBaccessing function through pointer.
PF_Err_BAD_C	A Problems Bring M parameter passed to a callback.
PF_Interrupt	RoutCeffect and AEGP callbacks can return this to effects, if a user action aborts a render.
	If the effect gets this error from a callback, it should stop processing the frame and return the
	error to the host.
	Failure to pass the error back may result in misrendered frames being cached.
PF_Err_CANNO	T RearG Thik from RAPIEA TEXT rary_SCAN_FUNC when problems occur parsing the clipboard
	into keyframe data.

26.2 Error Reporting Policy

After Effects has a consistent policy for error handling; follow it.

If you encounter an error in your plug-in's code, report it to the user immediately, before returning from your plug-in to After Effects.

After Effects considers errors from the operating system, encountered during your plug-in's execution, to be yours.

If you get an error code back from one of our callback functions, pass it back to After Effects; we've already reported it.

Out-of-memory errors are never reported by After Effects. Error reporting is always suppressed during RAM preview, and when After Effects is running in - noui mode.

To report an error from within a plug-in, set PF_OutFlag_DISPLAY_ERROR_MESSAGE, and describe the error in *PF_OutData>return_msg*.

Doing so will enter your error into the render log, and prevent system hangs in renders driven by a render engine or scripting.

26.3 Dig In!

Now you have a basic understanding of effect plug-ins, and are ready to start experimenting with some real code. Go ahead and get started!

After getting the basics of your plug-in setup, you may have some questions about reuseable code, advanced functionality, and how to optimize your code to make it faster.

To this end, After Effects exposes a tremendous amount of its internal functionality via function suites.

By relying on After Effects code for utility functions, you should be able to get your image processing algorithms implemented quickly.

This will discussed in Effect Details.

88 Chapter 26. Errors

Effect Details

Now that we've covered the basics of effect plug-ins, we'll cover some of the finer points to polish off your effect. Not every section will be relevant to every plug-in, so feel free to use the PDF document bookmarks to skip to the sections pertinent to your current project.

27.1 Free Code == Good

After Effects provides effect plug-ins with as much information and supporting code as possible. Use our function suites and callbacks to obtain the value of parameters (including source footage) at different times. Use our memory allocation suite to avoid competing with the host for resources. Use our image processing suites to copy, fill, blend and convolve images, and convert between color spaces. Obtain information about the masks applied to a layer. ANSI emulation and math utility suites are also provided, as well as information about the application, user, serial number, and current drawing context.

Previous versions of After Effects have provided functions for many common tasks. As we moved to support deeper color, these were moved to function suites. Use the newer function suites whenever possible; things will just be better.

Using our function suites keeps your plug-in compact; you write and test less code. The functions are tested, optimized, and used by our own plug-ins. The functions are distributed to multiple processors and take advantage of available hardware acceleration.

No, really, use the provided functions. Seriously.

Accessing the After Effects Function Suites

If you are writing C++ code, accessing functions in our PICA function suites is a breeze, using the AEGP_SuiteHandler, which automatically acquires the suite when needed, and disposes of it when done. Just instantiate the handler like so:

```
AEGP_SuiteHandler suites(in_data->pica_basicP);
```

After that, you may make calls to any function in any suite, like so:

```
PF_Handle infoH = suites.HandleSuite1()->host_new_handle(sizeof(MyStruct));
```

If you must use C code, then acquire and release the suites manually using the PF_Suite_Helper utility files, as demonstrated in the Checkout sample project.

Behind the scenes, these both of these methods acquire PICA function suites using AcquireSuite, a member function of the SPBasicSuite pointed to in PF_InData .

28.1 Suite Versions

WhizBangSuite1 may provide a Foobar() function which takes two arguments, and WhizBangSuite2>Foobar() may take three. Though each new version of a suite supercedes the old one, feel free to acquire multiple versions of the same suite; we never remove or alter previously shipped suites.

When unsure of the capabilities of the plug-in host (no third party host besides Premiere supports PICA), attempt to acquire the latest version, and "fall back" to previous versions. If functionality you require isn't available, warn the user, and return an error (or fall back on other behavior when running in more "primitive" plug-in hosts). Note that support for these suites in other hosts of After Effects plug-ins is a maze of twisty caves and passages, all alike.

28.2 Threading

Unless documented otherwise, assume that any function provided by our suites is not thread-safe. For example, only your plug-in's main thread should do anything that modifies the user interface.

Memory Allocation

Use After Effects for any memory allocations of significant size. For small allocations, you can use new and delete, but this is the exception, not the rule. In low-memory conditions (such as during RAM preview), it's very important that plug-ins deal gracefully with out-of-memory conditions, and not compete with After Effects for OS memory. By using our memory allocation functions, After Effects can know when to free cached images, to avoid memory swapping. Failing to use our functions for sizable allocations can cause lock-ups, crashes, and tech support calls. Don't do that.

If you're wrapping existing C++ classes, create a base class that implements new and delete for that class and derive from it. To overload the STL, we don't recommend you overload global new and delete. Instead provide an allocator as part of the template definition.

Handles passed to you by After Effects are locked for you before you're called, and unlocked once you return.

29.1 PF_HandleSuite1

Function	Purpose	Replaces
host_new_handle	Allocates a new handle.	PF_NEW_HANDLE
	PF_Handle (*host_new_	
	<pre>→handle) (A_HandleSize size);</pre>	
host_lock_handle	Locks a handle.	PF_LOCK_HANDLE
	<pre>void (*host_lock_handle)(PF_Handle pf_handle);</pre>	
host_unlock_handle	Unlocks a handle.	PF_UNLOCK_HANDLE
	<pre>void (*host_unlock_</pre>	
	→handle)(
	<pre>PF_Handle pf_handle);</pre>	
host_dispose_handle	Frees a handle.	PF_DISPOSE_HANDLE
	<pre>void (*host_dispose_</pre>	
	→handle) (
	<pre>PF_Handle pf_handle);</pre>	
host_get_handle_size	Returns the size, in bytes, of the re-	PF_GET_HANDLE_SIZE
	allocatable block whose handle is passed in.	
	A_HandleSize (*host_get_	
	<pre></pre>	
	_	
host_resize_handle	Resizes a handle.	PF_RESIZE_HANDLE
	PF_Err (*host_resize_	
	<pre></pre>	
	→PF_Handle *handlePH);	

Image Buffer Management Functions

Use these functions to create and destroy PF_EffectWorld / PF_LayerDef, and to find out their bit-depth.

30.1 PF_WorldSuite2

Function	Description	
PF_NewWorld	Creates a new PF_EffectWorld.	
	PF_Err PF_NewWorld(PF_ProgPtr effect_ref, A_long widthL, A_long heightL, PF_Boolean clear_pixB, PF_PixelFormat pixel_format,	
PF_DisposeWorld	<pre>PF_EffectWorld *worldP); Disposes of a PF_EffectWorld.</pre>	
	<pre>PF_Err PF_DisposeWorld(PF_ProgPtr effect_ref, PF_EffectWorld *worldP);</pre>	
PF_GetPixelFormat	Get the pixel format for a given PF_EffectWorld. PF_Err PF_GetPixelFormat(const PF_EffectWorld *worldP, PF_PixelFormat *pixel_formatP); pixel_formatP can be: • PF_PixelFormat_ARGB32 - standard 8-bit RGB • PF_PixelFormat_ARGB64 - 16-bit RGB • PF_PixelFormat_ARGB128 - 32-bit floating point RGB	

Iteration Suites

Effects often iterate over all pixels in an image, filtering each one. By taking advantage of After Effects' iteration suites, you make it possible for After Effects to sub-allocate your task to as many processors are present, taking advantage of hardware-specific acceleration.

After Effects will also manage progress reporting and user cancellation automatically.

Use these suites! Make sure the pixel processing functions you pass to these iterator callbacks are re-entrant.

31.1 PF_Iterate8Suite1, PF_Iterate16Suite1, PF_IterateFloatSuite1

Function	Purpose
iterate	Iterates across pixels from a source image, alters them,
	and populates a destination image.
	You may specify a rectangular region of pixels across
	which to iterate; if you don't, After Effects will iterate
	over every overlapping pixel. You give a refcon, and
	the function is invoked with that refcon, plus the x and
	y coordinates of the current pixel, plus pointers to that
	pixel in the source and destination images. If you pass a
	NULL source, it will iterate over the dst. This function
	is quality independent.
	Don't depend upon the pixels being traversed in any
	particular order. The image may be subset to different
	CPUs, so consider all the parameters (except dst) to be
	read-only while After Effects is processing. This call-
	back automatically includes progress and abort check-
	ing, so don't do so in your pixel function.
	iterate(
	PF_InData *in_data,
	A_long progress_base, A_long progress_final,
	PF_EffectWorld *src,
	<pre>const PF_Rect *area, void *refcon,</pre>
	PF_Err (*pix_fn)(
	<pre>void *refcon,</pre>
	A_long x,
	A_long y,
	PF_Pixel *in,
	PF_Pixel *out),
	<pre>PF_EffectWorld *dst);</pre>
iterate_origin	Lets you specify an offset from the input
	into the output. For example, if your out-
	put buffer is smaller than your input buffer,
	<pre>pass (in data>output_origin_x,</pre>
	in_data>output_origin_y) as the origin,
	and NULL for area, and this function will offset the src
	pixel pointer appropriately for your pixel function.
	iterate_origin(
	PF_InData *in_data,
	A_long progress_base,
	A_long progress_final,
	<pre>PF_EffectWorld *src, const PF_Rect *area,</pre>
	const PF_Point *origin,
	void *refcon,
	PF_Err (*pix_fn)(
	<pre>void *refcon,</pre>
	A_long x,
	A_long y,
	PF_Pixel *in,
	<pre>PF_Pixel *out), PF_EffectWorld *dst);</pre>

31-1-PE_iterate8Suite1, PF_iterate16Suite1, PF_iterateFige1Suite9uite only. Allows a Look-Up Table9

(LUT) to be passed for iteration; you can pass the same or different LUTs for each color channel. If no LUT is passed, an identity LUT is used.

Graphics Utility Suites

After Effects exposes its internal transform and graphic utility routines through the following function suites.

32.1 Transform Worlds

These functions combine $PF_EffectWorlds$ in interesting ways. When you use these, you're using the same code After Effects does internally.

32.1.1 PF_WorldTransformSuite1

Function	Purpose
composite_rect	Composite a rectangle from one PF_EffectWorld
	into another, using one of After Effects' transfer modes.
	PF_Err composite_rect (PF_ProgPtr effect_ref, PF_Rect *src_rect, A_long src_opacity, PF_EffectWorld *src_world, A_long dst_x, A_long dst_y, PF_Field field_rdr, PF_XferMode xfer_mode, PF_EffectWorld *dst); field_rdr can be upper, lower or both. xfer_mode is one of the following:
	• PF_Xfer_COPY • PF_Xfer_BEHIND • PF_Xfer_IN_FRONT
blend	Blends two images, alpha-weighted. Does not deal with different-sized sources, though the destination may be either PF_EffectWorld.
	<pre>PF_Err blend (PF_ProgPtr</pre>
convolve	Convolve an image with an arbitrary size kernel on each of the a, r, g, and b channels separately. You can specify a rectangle to convolve (for instance, the extent_hint from <i>PF_EffectWorld Structure</i>), or pass 0 to convolve the entire image. Do not use if the source <i>is</i> the destination. Describe the convolution using <i>Kernel Flags</i> .
	<pre>PF_Err convolve(PF_EffectWorld *src, const PF_Rect *area, PF_KernelFlags flags, A_long kernel_size, void *a_kernel, void *r_kernel, void *g_kernel, void *b_kernel, PF_EffectWorld *dst);</pre>
сору	Copies a region from one PF_EffectWorld to another, preserving alpha (unlike the macOS CopyBits). PF_Err copy (PF_EffectWorld *src, PF_EffectWorld *dst, PF_Rect *src_r, PF_Rect *src_r, PF_Rect *dst_r);
32.1 _{py} Transform Worlds	A higher fidelity version of the above (using the same parameters).
transfer_rect	Blends using a transfer mode, with an optional mask.

32.2 Kernel Flags

Functions such as convolve or gaussian kernel work with kernels, or matrices of filter weight values. These matrices can be in any format. The kernel flags describe how the matrices should be created and used. OR together any flags you need.

The flags relevant to given routines are documented along with the routine prototype. The first entry in the left column is always the default and has value 0.

Kernel Flags	Indicates
PF_KernelFlag_2D	Specifies a one or two dimensional kernel.
PF_KernelFlag_1D	
PF_KernelFlag_UNNORMALIZED	NORMALIZED equalizes the kernel; the volume under the kernel surface
PF_KernelFlag_NORMALIZED	is the same as the volume under the covered area of pixels.
PF_KernelFlag_CLAMP	CLAMP restricts values to the valid range for their data type.
PF_KernelFlag_NO_CLAMP	
PF_KernelFlag_USE_LONG	USE_LONG defines the kernel as an array of longs valued from 0 to 255.
PF_KernelFlag_USE_CHAR	USE_CHAR defines the kernel as an array of unsigned chars from 0 to
PF_KernelFlag_USE_FIXED	255.
PF_KernelFlag_USE_UNDEFINE	USE_FIXED defines the kernel as an array of fixeds from 0 to 1.
	USE_LONG is the only implemented flag.
PF_KernelFlag_HORIZONTAL	Specifies the direction of the convolution.
PF_KernelFlag_VERTICAL	
_	BOKKETESPLICATE_BORDERS to replicate border pixels when sampling
PF_KernelFlag_REPLICATE_BO	RIDITATION THE END TO THE REAL PROPERTY AND THE END TH
	as alpha zero (black).
	REPLICATE_BORDERS is not implemented and will be ignored.
PF_KernelFlag_STRAIGHT_CON	VOLSEESTRAIGHT_CONVOLVE to indicate straight convolution, use
PF_KernelFlag_ALPHA_WEIGHT	CAMPAGALWEIGHT_CONVOLVE to tell the convolution code to alpha-
	weight the contributions of pixels to the resulting convolved output.
	ALPHA_WEIGHT_CONVOLVE is not implemented and will be ignored.

32.3 Fill 'Em Up!

The FillMatteSuite can be used to fill a PF_EffectWorld, either with a specific color or premultiplied with an alpha value.

32.3.1 PF_FillMatteSuite2

Function	Purpose
fill	Fills a rect with a color (or, if the color pointer is null, fills with black and alpha zero). If the rect is null, it fills the entire image.
	<pre>PF_Err fill (PF_ProgPtr</pre>
fill16	Same as fill, but takes a pointer to a PF_Pixel16 color.
fill_float premultiply	Takes a pointer to a PF_PixelFloat color. Converts to (and from) r, g, and b color values premultiplied with black to represent the alpha channel. Quality independent. • forward is used as a boolean; • true means convert non-premultiplied to premultiplied, • false mean un-pre-multiply. PF_Err premultiply (A_long forward, PF_EffectWorld *dst);
premultiply_color	Converts to (and from) having r, g, and b color values premultiplied with any color to represent the alpha channel.
	<pre>PF_Err premultiply_color (PF_ProgPtr</pre>
premultiply_color16	Same as above, but takes a pointer to a PF_Pixel16 color.
premultiply_color_float	Takes a pointer to a PF_PixelFloat color.

32.4 Sampling Images

Note: areas outside the bounds of the image being sampled are treated as zero alpha. For convenience, the functions from PF_Sampling8Suite1, PF_Sampling16Suite1, and PF_SamplingFloatSuite1 are all listed in this table.

32.4.1 PF_SamplingSuite Functions (Multiple Suites)

Function	Purpose
nn_sample	Performs nearest neighbor sampling.
	<pre>PF_Err nn_sample (PF_ProgPtr</pre>
nn_sample16	Same as above, but takes a pointer to a PF_Pixel16
	dst_pixel.
nn_sample_float	Takes a pointer to a PF_PixelFloat dst_pixel. Queries the appropriate alpha-weighted interpolation of
subpixel_sample	colors at a non-integral point in a source image, in high quality. Nearest neighbor sampling is used in low quality. Because the sampling routine, if used, will typically be called many times, it is convenient to copy the function pointer out to the callbacks structure and into a register or onto the stack to speed up your inner loop. See the sample code for an example. NOTE: The sampling assumes that 0,0 is the center of the top left pixel.
	<pre>PF_Err subpixel_sample (PF_ProgPtr</pre>
subpixel_sample16	Same as above, but takes a pointer to a PF_Pixel16* dst_pixel.
subpixel_sample_float	Takes a pointer to a PF_PixelFloat * dst_pixel.
area_sample	Use this to calculate the appropriate alpha weighted average of an axis-aligned non-integral rectangle of color in a source image, in high quality. Nearest neighbor sampling is used in low quality. Because of overflow issues, this can only average a maximum of a 256 x 256 pixel area (i.e. x and y radius < 128 pixels). NOTE: the sampling radius must be at least one in both x and y. PF_Err area_sample (PF_ProgPtr effect_ref, PF_Fixed x, PF_Fixed y, const PF_SampPB *params, PF_Pixel *dst_pixel); NOTE: Areas outside the boundaries of the layer are considered the same as zero alpha, for sampling purposes.
area_sample16	Same as above, but takes a PF_Pixel16* dst_pixel.

32.4.2 PF_BatchSamplingSuite1 Functions

Function	Purpose
begin_sampling	Your effect is going to perform some batch sampling; After Effects will perform setup tasks to optimize your sampling.
	<pre>PF_Err (*begin_sampling)(PF_ProgPtr</pre>
end_sampling	Tells After Effects you're done sampling.
	<pre>PF_Err (*end_sampling)(PF_ProgPtr effect_ref, PF_Quality qual, PF_ModeFlags mf, PF_SampPB *params);</pre>
get_batch_func	Obtains a pointer to After Effects' batch sampling function (highly optimized).
	<pre>PF_Err (*get_batch_func)(PF_ProgPtr</pre>
get_batch_func16	Obtains a pointer to After Effects' 16-bpc batch sampling function (also highly optimized).
	<pre>PF_Err (*get_batch_func16)(PF_ProgPtr</pre>

32.5 Do The Math For Me

Along with the variety of graphics utilities, we also provide a block of ANSI standard routines so that plug-ins will not need to include other libraries to use standard functions.

We give function pointers to a large number of math functions (trig functions, square root, logs, etc.).

Using our suite functions provides for some (application level) error handling, and prevents problems with including different versions of multiple "standard" libraries.

All functions return a double. All angles are expressed in radians, use PF_RAD_PER_DEGREE (a constant from AE_EffectCB.h) to convert from degrees to radians if necessary.

32.5.1 PF_ANSICallbackSuite1

Function	Purpose	Replaces
acos	Returns the arc cosine of x.	PF_ACOS
asin	Returns the arc sine of x.	PF_ASIN
atan	Returns the arc tangent of x.	PF_ATAN
atan2	Returns atan(y/x).	PF_ATAN2
ceil	Returns the next integer above x.	PF_CEIL
cos	Returns the cosine of x.	PF_COS
ехр	Returns e to the power of x.	PF_EXP
fabs	Returns the absolute value of x.	PF_FABS
floor	Returns the closest integer below x.	PF_FLOOR
fmod	Returns x modulus y.	PF_FMOD
hypot	Returns the hypotenuse of x and y, which is $sqrt(x*x + y*y)$.	PF_HYPOT
log	Returns the natural log (ln) of x.	PF_LOG
log10	Returns the log (base 10) of x.	PF_LOG10
pow	Returns x to the power of y.	PF_POW
sin	Returns the sine of x.	PF_SIN
sqrt	Returns the square root of x.	PF_SQRT
tan	Returns the tangent of x.	PF_TAN
(while not strictly math functions, these emulate ANSI functionality)		
sprintf	Emulates the C sprintf function.	PF_SPRINTF
strcpy	Emulates the C strcpy function.	PF_STRCPY

CHAPTER 33

Interaction Callback Functions

While the un-macro'd function pointers are provided in *PF_InData*, use the provided macros to access them. See how stringent we are about deprecating macro usage? Let's let this be our little secret.

33.1 Interaction Callbacks

Function	Purpose
PF_ADD_PARAM	Enumerate your plug-in's parameters to After Effects during <i>PF_Cmd_PARAM_SETUP</i> , using multiple calls to this function. Note: Failing to completely clear out a PF_ParamDef prior to PF_ADD_PARAM() can cause many problems. Always use AEFX_CLR_STRUCT before adding parameters.
	<pre>PF_Err PF_ADD_PARAM (PF_InData *in_data, PF_ParamIndex index, PF_ParamDefPtr def);</pre>
	We provide convenience macros for specific parameter types, in Utils/ Param_Utils.h: • PF_ADD_COLOR, • PF_ADD_ARBITRARY, • PF_ADD_SLIDER, • PF_ADD_FIXED, • PF_ADD_FLOAT_SLIDERX, • PF_ADD_CHECKBOXX, • PF_ADD_BUTTON, • PF_ADD_ANGLE, • PF_ADD_NULL, • PF_ADD_LAYER, • PF_ADD_LAYER, • PF_ADD_PERCENT, • PF_ADD_POINT, • PF_ADD_POINT_3D, • PF_ADD_TOPICX, • PF_ADD_POPUPX, • PF_ADD_POPUPX, • PF_ADD_FLOAT_SLIDERX_DISABLED
PF_ABORT	Returns non-zero if the user has cancelled; return that value to After Effects. Wrap your render routine in a "while abort has not been requested" while loop. PF_Err PF_ABORT (PF_InData *in_data);
PF_PROGRESS	Displays a progress bar during processing; current and total describe the percentage complete. Returns non-zero if you should suspend or abort your current processing; return that value to After Effects. Call once per scanline, unless your effect is very slow. If total is 0, PF_ABORT is used instead (presenting the user with different choices).
	<pre>PF_Err PF_PROGRESS (PF_InData *in_data, A_long current, A_long total);</pre>
PF_CHECKOUT_PARAM 33.1. Interaction Callbacks	Obtains parameter values, or the source video layer, at a specified time. After Effects makes caching decisions based on the checkout state of parameters.
	Allocate a new <i>PF_ParamDef</i> to hold the result; those passed to the plug-in are read-only. If you check out a layer parameter that's set to <none>, the layer returned will be filled with good. Macket are not included with</none>

33.2 Parameter Checkout vs. Param Zero

Effects are applied to an image in order from 0 to n within the Effect Control (and Composition) panel.

The output from effect [n-1] is the input (param[0]) of effect [n].

On the other hand, when a normal effect checks out a layer using PF_CHECKOUT_PARAM, it receives the raw (uneffected) source layer, regardless of its order.

However, when a SmartFX effect checks out its input parameter (params[0]), previous effects are applied.

33.3 Parameter Checkout Behavior

Regardless of whether the layer in and out point have been trimmed, you will get valid frames from the start of the source footage to the end, and then transparent before and after that.

Layer params with a lower frame rate than the composition in which they're checked out are only refreshed as often as necessitated by the lower frame rate.

A 10fps layer checked out in a 30fps composition will only need to be refreshed every third frame. if your effect wants to change it's output every frame despite the static input layer, you'd need to set *PF_Outflag_NON_PARAM_VARY*.

When an effect checks out a continuously-rasterized Adobe Illustrator layer, After Effects renders the Illustrator layer with geometrics applied, in a composition-sized buffer.

33.4 Parameter Checkout And Re-Entrancy

Plug-ins that check out layers at different times can generate re-entrant behavior. Consider an instance where the Checkout sample plug-in is applied to a layer in composition B, and B is pre-composed into composition A where Checkout is applied to it as well.

When composition A is rendered, Checkout[A] will be sent *PF_Cmd_RENDER*, during which it checks out a layer (composition B) from a time other than the current time.

In order to provide that checked-out layer, After Effects sends PF_Cmd_RENDER to Checkout [B].

Presto, recursion!

If you're going to check out parameters, your effects must handle re-entrant render requests appropriately.

Don't use globals, or read or write static variables...but you weren't going to anyway, right?

33.5 Progress During Iteration

After Effects strives to be as responsive as possible to user interaction, even while rendering. Do the same through appropriate use of PF_ITERATE(). For example, perhaps you're using a PF_ITERATE'd function three times during your response to PF_Cmd_RENDER.

In this case, you'd start off with:

```
lines_per_iterateL = in_data>extent_hint.top - in_data>extent_hint.bottom;
total_linesL = 3 * lines_per_iterateL;
lines_so_farL = 0;
```

After each iteration, you'd add the already-completed lines to the current position:

```
suites.iterate8suite()>iterate( lines_so_farL,
                                 total_linesL,
                                 input_worldP,
                                 &output>extent_hint,
                                 refcon.
                                 WhizBangPreProcessFun,
                                 output_worldP);
lines_so_farL += lines_per_iterateL;
ERR(PF_PROGRESS(lines_so_farL, total_linesL));
suites.iterate8suite()>iterate( lines_so_farL,
                                total_linesL,
                                 input_worldP,
                                 &output>extent_hint,
                                 refcon,
                                 WhizBangRenderFunc,
                                 output_worldP);
lines_so_far += lines_per_iterateL;
ERR(PF_PROGRESS(lines_so_farL, total_linesL));
suites.iterate8suite()>iterate( lines_so_farL,
                                 total_linesL,
                                 input_worldP,
                                 &output>extent_hint,
                                 WhizBangPostProcessFunc,
                                 output_worldP);
ERR(PF_PROGRESS(lines_so_farL, total_linesL));
```

Pixel Aspect Ratio

Effects must respond correctly to footage with non-square pixels, and non-uniform downsampling factors. Even different layer parameters can have different pixel aspect ratios! Doing so isn't difficult once you understand the concepts involved.

Simple effects needn't do any work to match up *point parameters* to the actual pixels in the output. Point parameters are given to the effect scaled for downsample factor and pixel aspect ratio; they are in the coordinate system of the input buffer. This provides an implicit "pixel coordinate system." This coordinate system is handy and easy to understand. But effects that use absolute pixel measurements or geometry must take a deeper look at the relationship between the input buffer and the final rendered image.

34.1 Don't Assume Pixels Are Square, Or 1-To-1

First, it is not necessarily a square coordinate system, due to both pixel aspect ratio and non-uniform downsample factor. The final rendered image can be stretched or squashed horizontally, relative to the pixels your effect processes. Circles will appear as ellipses, squares as rectangles. The distance between two points varies based on their angle in this coordinate system; anything rotated in this system is skewed, in the final output.

Second, even if it *is* a square coordinate system, it's not necessarily the same size as the final output. This means that any slider which defines a size in pixels will be a problem when the image is rendered downsampled; the width of anti-aliasing filters changes based on downsample factor.

Sometimes these issues aren't a problem. Any effect that colors pixels based solely on a linear function of the x and y coordinates need not bother with pixel aspect ratio and downsample factor at all. Staying in the input coordinate space is an option, though you must account for pixel aspect ratio and downsample factor elsewhere.

Suppose you're writing a particle system effect that sprays textured sprites from a source position defined by an effect control point. Using pixel coordinates to represent the particle positions seems fine (as long as the particles don't have to rotate around a point), but when you go to actually *render* the particle textures, you'll have to scale them by pixel aspect ratio and downsample factor.

If an effect already has coordinate transformation machinery in its pipeline, there's an alternative that's often simpler. Many algorithms require some sort of coordinate transformation; using matrices to set up a transformation, for example. But there are other easily adaptable algorithms, for example a texture generation effect that computes the value of each pixel based solely on its position. In this case, the code must take the raw pixel position and account for pixel aspect ratio and downsample factor.

34.2 Suggested Approach

The simplest way to get all of this right is to work entirely in full resolution square coordinates, then scale by down-sample factor and pixel aspect ratio as a final output transformation. Since point parameters are always reported in input buffer coordinates, convert them to full-resolution square coordinates before use. With this approach you don't need to worry about sliders which define a size in pixels; just interpret them as defining size in full-resolution vertical pixels.

1) When getting your point parameters, go immediately to floating point and a full resolution square pixel system, like this.

```
x *= in_data>pixel_aspect_ratio.num / (float)in_data>pixel_aspect_ratio.den;
x *= in_data>downsample_x.den / (float)in_data>downsample_x.num;
y *= in_data>downsample_y.den / (float)in_data>downsample_y.num;
```

- 2) Perform all setup (define transformation matrices, generate coordinates for later scan conversion, compute values based on the distance between points, rotating things, et cetera) in this coordinate space. Note that you're not actually dealing with pixels in this stage; you're just manipulating coordinates or coordinate transformations.
- 3) To go back to a coordinate system that corresponds directly to the pixels of the output buffer, undo the transformations from step one. Do this as late as possible, so as little code as possible needs to deal with this non-square space. If you're using matrices, this would be a final output transformation. For an effect which renders something based on the coordinate of each pixel, iterate over the output pixels and convert pixel coordinates to square coordinates before doing any processing for that pixel.

This may seem like extra work, but most reasonably complex effects like this have a coordinate transformation step anyway; and if they don't, they still need one to handle pixel aspect ratio and downsample factor correctly.

34.3 Applying User Input In Pixels

After Effects does all of its stretching horizontally so as to not to introduce unnecessary field interpolations; when pixels are used as a unit, we think of them as vertical pixels.

34.4 Test Test Test!

Test at 1/2, 1/4, and custom resolutions and compare the output. Use an anamorphic (2:1) pixel aspect ratio composition to track down bugs in pixel aspect ratio handling (it really makes them obvious), and be sure to test with different horizontal and vertical downsample factors.

Some developers have reported problems with the downsample factors provided by some "After Effects compatible" plug-in hosts being zero. Check for zero before dividing.

Parameters & Floating Point Values

We have something to admit to you; for years, even though we've given you 8 bit color values, we've internally used floating point representations behind your back.

That's right, even with over-bright colors, we'd only ever tell you '255, 255, 255'. Yeah, right.

Well, we can't live the lie any longer! Given a color parameter (passed to you by After Effects in your effect's parameter array), this function returns a floating point representation, including any high dynamic range component.

35.1 PF_ColorParamSuite1

Function	Purpose
PF_GetFloatingPoint ColorFromColorDef	
	PF_Err PF_ GetFloatingPointColorFromColorDef(PF_ProgPtr effect_ref, const PF_ParamDef *color_defP, PF_PixelFloat *fp_colorP);
	rr_rixerrioat

35.2 PF_PointParamSuite1

We also provide a way to get floating point values for point parameters.

Function	Purpose
PF_GetFloatingPoint ValueFromPointDef	
	PF_Err PF_
	→GetFloatingPointValueFromPointDef(
	PF_ProgPtr effect_ref,
	<pre>const PF_ParamDef *point_defP,</pre>
	A_FloatPoint *fp_pointP);

35.3 PF_AngleParamSuite1

New in CS6.0.2, we now provide a way to get floating point values for angle parameters.

Function	Purpose
PF_GetFloatingPoint ValueFromAngleDef	
	PF_Err PF_ →GetFloatingPointValueFromAngleDef(PF_ProgPtr effect_ref, const PF_ParamDef *angle_defP, A_FloatLong *fp_valueP);

Parameter Supervision

Supervision means dynamically changing the values of some parameters based on the values of others. To supervise a parameter, set $PF_ParamFlag_SUPERVISE$ before adding it during $PF_Cmd_PARAM_SETUP$. Whenever it is changed, you will receive $PF_Cmd_USER_CHANGED_PARAM$. The index (into the plug-in's parameter array) of the changed parameter is sent in the $PF_UserChangedParamExtra$ (extra) param. During $PF_Cmd_USER_CHANGED_PARAM$, you may change the values and appearance of any of your parameters.

36.1 Updating Parameter UI

If you set PF_ParamFlag_SUPERVISE on any parameter, After Effects will send you PF_Cmd_UPDATE_PARAMS_UI, just as if you had set PF_OutFlag_SEND_UPDATE_PARAMS_UI.

During $PF_Cmd_UPDATE_PARAMS_UI$, you may only change the appearance and enable state of parameters. Use PF_UpdateParamUI() from $PF_ParamUtilSuite3$ to update the UI, passing it a copy of the parameter you wish to modify. Do not attempt to modify the original. It is not necessary to set PF_OutFlag_REFRESH_UI; PF_UpdateParamUI() handles that for you.

Note: This is the only way to update the UI of PF_PUI_STD_CONTROL_ONLY parameters.

36.2 Updating Parameter Values

A parameter's value (not just UI) can be modified during *PF_Cmd_USER_CHANGED_PARAM* and during *PF_Cmd_EVENT* (*PF_Event_DO_CLICK*, *PF_Event_DRAG*, & *PF_Event_KEYDOWN*). After Effects will not honor changes made at other times.

When changing parameter *values* (and not just the UI), modify the original parameter, and set PF_Paramdef.uu.change_flags to PF_ChangeFlag_CHANGED_VALUE.

This change will be also update the UI, and will be undoable by the user. Note that $PF_ChangeFlag_CHANGED_VALUE$ isn't supported for layer parameters.

This suite is provided to give effect plug-ins some access to their parameter streams, without requiring AEGP suite usage. At least some of these functions are provided by several third-party hosts. These functions are especially handy for effects with supervised parameters.

36.3 PF_ParamUtilSuite3

Function	Purpose	
PF_UpdateParamUI		
	PF_UpdateParamUI(
	PF_ProgPtr effect_ref,	
	PF_ParamIndex param_index,	
	<pre>const PF_ParamDef *defP);</pre>	
	Force After Effects to refresh the parameter's UI, in the	
	effect controls palette.	
	Starting in CC 2014, After Effects will now honor a	
	change to a custom UI height. Simply change the ui_height of your custom UI PF_ParamDef and then call	
	PF_UpdateParamUI. The effect's custom UI height will	
	be updated in the Effect Control Window.	
	Starting in CS6, when a plug-in disables a parameter,	
	we now save that state in the UI flags so that the plug-in	
	can check that flag in the future to see if it is disabled.	
	NOTE: Never pass param[0] to this function.	
PF_GetCurrentState		
	PF_GetCurrentState(
	PF_ProgPtr effect_ref,	
	PF_ParamIndex param_index,	
	<pre>const A_Time *startPTO,</pre>	
	<pre>const A_Time *durationPTO, PF_State *stateP);</pre>	
	This API, combined with PF_AreStatesIdentical below,	
	lets you determine if a set of inputs (either layers, other	
	properties, or both) are different between when you first	
	called PF_GetCurrentState and a current call, so it can	
	be used for caching. You can specify a range of time to	
	consider or all of time.	
	Updated in CS6 to add param_index, startPT0, and du-	
	rationPT0. Pre-defined constants for param_index are	
	as follows:	
	• PF_ParamIndex_CHECK_ALL - check every	
	parameter, including every layer referred to by a	
	layer parameter.	
	• PF_ParamIndex_CHECK_ALL_EXCEPT_LAYER_	_PARAMS
	- omit all layers. Pass a specific layer parameter	
	index to include that as the only layer parameter tested.	
	• PF_ParamIndex_CHECK_ALL_HONOR_EXCLUDE	7
	- Similar to CHECK_ALL, but honor	<u>.</u>
	PF_ParamFlag_EXCLUDE_FROM_HAVE_INPUTS_	CHANGED
	Passing in NULL for both start and du-	.0111111022
	ration indicates all time. For effects that	
	do simulation across time and therefore set	
	PF_OutFlag2_AUTOMATIC_WIDE_TIME_INPUT,	
	when you ask about a time range, it will be expanded to	
	include any times needed to produce that range.	
	Populates a PF_State, an opaque data type used as a	
	receipt for the current state of the effect's parameters	
	(the PF_State is used in our internal frame caching	
24	database). Chapter 36. Parameter Supervision	
24 PF_AreStatesIdentical		
	PF_AreStatesIdentical(

PF_ProgPtr

effect_ref,

const PF_State *state1P,

Global, Sequence, & Frame Data

After Effects allows plug-ins to store data at three scopes; global, sequence, and frame. Consider carefully where you store information; choosing poorly can impact performance, or make your plug-in confusing to the user.

Use global data for information common to all instances of the effect: static variables and data, bitmaps, pointers to other DLLs or external applications.

Store anything specific to this instance of your plug-in (UI settings, text strings, and any custom data not stored in parameters) in sequence data, Use After Effects' memory allocation functions.

Frame data is used for information specific to rendering a given frame. This has fallen into disuse, as most machines are capable of loading an entire frame into memory at a time. Of course, your IMAX-generating users will still appreciate any optimizations you can make.

37.1 Persistence

After Effects saves sequence data in the project file, but not global or frame data. Pointers within sequence data which point to external data are, in all likelihood, invalid upon reopening the project, and must be re-connected. We call this process "flattening" and "unflattening" the sequence data.

37.2 Validating Sequence Data

Careful sequence data validation is important for effects that do simulation across time, where frame N is dependent on frame N-1, and you use a cache of calculated data in your sequence data. If a parameter is changed, certain calculated data may no longer be valid, but it would also be wasteful to blindly recalculate everything after every change.

When asked to render frame N, assuming you have your cached data calculated up to frame N-1, call PF_GetCurrentState() / PF_AreStatesIdentical() from *PF_ParamUtilSuite3* to see if the cache of calculated data is still valid given the current parameter settings.

The state of all parameters (except those with *PF_ParamFlag_EXCLUDE_FROM_HAVE_INPUTS_CHANGED* set), including layer parameters (including *param[0]*) are checked over the passed time span.

This is done efficiently, as the change tracking is done with timestamps.

If the inputs have not changed, you can safely use your cache, AND the internal caching system will assume that you have a temporal dependency on the passed range. So if something changes upstream, the host's caches will be properly invalidated automatically.

To test that it is working, apply your effect with one parameter keyframed on every frame. RAM Preview to fill the cache, then change one of the keyframes. The related frame and all dependent frames (e.g. later frames, in the case of a simulation) should lose their cache marks and require re-rendering. Similarly, upstream changes to sources of layer parameters should cause time-selective invalidation of the cache.

37.3 Flattened And Unflattened Sequence Data

If your sequence data references external memory (in pointers or handles), you must flatten and unflatten your data for disk-safe storage. This is analogous to creating your own miniature file format.

Upon receiving *PF_Cmd_SEQUENCE_FLATTEN*, put data referenced by pointers into one contiguous block from which you can later recover the old structure.

If your sequence data contains a pointer to a long, allocate 4 bytes in which to store the flattened data. You must handle platform-specific byte ordering.

Remember, your users (the ones who bought two copies of your plug-in, anyway) may want the same project to work on macOS and Windows.

After Effects sends PF_Cmd_SEQUENCE_RESETUP when the data is reloaded, for either flat or unflat data.

Use a flag at a common offset within both structures to indicate the data's state.

```
typedef struct {
   A_char* messageZ;
   PF_FpLong big_numF;
   void* temp_storage;
} non_flat_data;

typedef struct {
   char message[256];
   PF_FpLong big_numF;
   A_Boolean big_endianB;
} flat_data;
```

37.4 Resizing Sequence Data

During PF_Cmd_SEQUENCE_SETUP, allocate a handle for data specific to this instance of your effect.

You may modify the contents, but not the size, of the sequence data during any selector.

You may resize the sequence data handle only during the following selectors:

```
• PF_Cmd_AUDIO_SETUP
```

- PF_Cmd_AUDIO_SETDOWN
- PF_Cmd_FRAME_SETUP
- PF_Cmd_FRAME_SETDOWN
- PF_Cmd_AUDIO_RENDER
- PF_Cmd_RENDER
- PF_Cmd_SEQUENCE_SETUP (duh)
- PF_Cmd_SEQUENCE_SETDOWN
- PF_Cmd_SEQUENCE_FLATTEN
- PF_Cmd_SEQUENCE_RESETUP
- PF_Cmd_DO_DIALOG

CHAPTER 38

Arbitrary Data Parameters

Some values are not adequately represented by After Effects existing parameter types. You can create and register any data for interpolation by After Effects, by creating parameters of arbitrary data type, or "arb data". You can rely on our interpolation engine and parameter management, without having to force your data into a pre-defined parameter type.

We've created a new messaging structure for custom data types, which are easily conceptualized as member (and friend) functions of a C++ class. You must respond to all selectors detailed here if you use arb data.

These functions deal with custom data structure management. Your arb data will be unloaded and reloaded at the user's whim; provide disk-safe flatten and unflatten functions.

38.1 Arbitrary Data Selectors

Se- lector	Response
	i.A.Hocate, propulate Nand return a handle to a new instance of your arb data.
PF_Arb	i Free and dessing an instance of your arbitrary data type.
PF_Arb	i Make: ar comprof an existing instance. You will be passed two handles, but only the source handle contains
	a valid instance. You must create a new instance, copy the values from the source, and put it in the destination handle. If you are passed a NULL handle, create a default instance of your arb data.
PF_Arb	i You'll be passed a handle wan instance of your data type, and a variable in which you return the size of a flattened version of that instance.
DE 7 l-	
PF_ACC	i Elatteny the liastance you're passed, and place it in the supplied buffer. The buffer will be the size you reported in response to PF_Arbitrary_FLAT_SIZE_FUNC.
PF_Arb	i Unpack the buffer into an instance of your arbitrary data type, and put in the handle which you've been
	passed.
PF_Arb	i Your interpolation function is passed three handles to instances of your arbitrary data type; one containing
	initial values (0), one final values (1), and a third to hold your interpolated data (somewhere between 0
	and 1). You are also passed a float indicating where, between 0 and 1, your interpreted value should be.
	Allocate an instance and fill it with interpolated data. Then put the interpolated instance into the handle
	you've been passed. The velocity curves have already been accounted for when the normalized time
	value was calculated.
	NOTE: Never check out parameters if the <i>in_data>effect_ref</i> is NULL.
PF_Arb	i You are passed And instances of your arbitrary data, and a pointer to a comparison result. Populate the
	result with one of the values for PF_ArbCompareResult (see AE_Effect.h) to indicate whether the first
	was equal to, less than, more than, or simply not equal to the second.
PF_Arb	iIndicate the buffer size you were for printing your parameter's current values by setting print_sizePLu
	(member of print_size_func_params, part of the PF_ArbParamsExtra structure).
PF_Arb	i Formaty our and it and it and it and it are the sed of the control of the result to the buffer. This can be as elaborate
	as you would like. Your plug-in should emulate the cut-and-paste behavior for pasting text representa-
	tions of parameter settings (into a Microsoft Excel spreadsheet, for example) displayed by the plug-ins
	shipped with After Effects. You have a great deal of flexibility in how you format your output.
PF_Arb	i Given a buffer of text clata (often from the system clipboard), parse it into your arbitrary data format.

38.2 Implementing Arbitrary Data

In addition to the normal command and event selector, arb data requires another set of host interaction. This is transparent for other parameter types, as After Effects manages their representing data. Writing an arb data plug-in will give you insight into the vast amount of parameter management After Effects performs, and the sequence in which those managing actions occur. It may even cause you to rethink your implementation, and use the parameter types After Effects manages *for* you.

Instantiate your arb data (using After Effects' memory allocation functions, of course) and point ParamDef.u.arb_d.dephault at it. Populate it with appropriate default values. No value variable is required to set up the parameter; zero it out for safety's sake.

In your plug-in's entry function, include a case for handling PF_Cmd_ARBITRARY_CALLBACK.

Invoke a secondary event handler, <code>HandleArbitrary</code>. It receives a <code>PF_ArbParamsExtra</code> in extra, which in turn contains a <code>PF_FunctionSelector</code> identifying the command sent.

Perhaps After Effects has sent PF_Cmd_ARBITRARY_CALLBACK and the PF_FunctionSelector is PF_Arbitrary_COPY_FUNC. Pointers to a source and destination Arb are provided in PF_ArbParamsExtra. copy_func_params. Allocate a new Arb, and point dest_arbPH at it. If src_arbH is NULL, create a default Arb for dest_arbPH.

The user may select the arb's keyframe data in the Timeline panel, copy it, then switch to another application. You will be sent a PF_Arbitrary_PRINT_SIZE_FUNC; set the size of your output buffer by setting print_sizePLu in the PF_ArbParamsExtra. You'll then receive PF_Arbitrary_PRINT_FUNC; populate the print bufferPC output buffer with a textual representation of the Arb(s) in question.

Users may paste keyframe data into your Arb's timeline. You will receive PF_Arbitrary_SCAN_FUNC. Create an Arb based on the contents of the character buffer handed to you (its size is indicated in print_sizeLu).

38.3 Arbitrary Data? Re-Entrancy!

Your plug-in code *must* be recursively re-entrant to support custom data types, since it could be called by After Effects for numerous reasons. Your plug-in could check out a layer that, in turn, depends on another instance of your effect. Your plug-in's arbitrary data handling code will be triggered by your attempt to check out a (seemingly) unrelated layer. Watch out for calls to C run-time libraries that rely on static values accessed through global variables. If you're not prepared for this eventuality, you'll hang After Effects, and users will curse and punch their monitors.

38.4 When Not To Access Arbitrary Parameters

If in_data>effect_ref is NULL, do not check out arbitrary parameters.

38.5 Changes During Dialogs

After Effects ignores any changes made to arbitrary data parameters during PF_Cmd_DO_DIALOG.

This is by design; changes made during the display of the options dialog affect the entire effect stream, not just the arbitrary parameter at a given time.

If you must alter your arb's behavior based on these changes, save that information in sequence data and apply it later, often during PF Cmd USER CHANGED PARAM.

Useful Utility Functions

39.1 PF_EffectUISuite

Although not strictly concerned with parameters, this suite can change the name of the options button.

Function	Purpose
PF_SetOptionsButtonName	Changes the text on the options button in the effect con-
	trols palette.
	NOTE: This must be called during
	PF_Cmd_PARAM_SETUP.
	PF_SetOptionsButtonName(
	PF_ProgPtr effect_ref,
	<pre>const A_char *nameZ);</pre>
	nameZ may be up to A_char[31] in length.

39.2 PF_AppSuite

Roughly 437 years ago, when we released After Effects 5.0, we published some useful utility callbacks in PF_AppSuite. They're as useful today as they were then. After Effects has user-controllable UI brightness.

In addition to the *PF_EffectCustomUIOverlayThemeSuite* for custom UI in effects, use these calls to integrate seam-lessly into the After Effects UI.

What better way to shame someone into purchasing a copy of your plug-in than by putting their personal information into a watermark, eh? Or set the cursor to add mask vertices, just to confuse people? Heh heh heh. But that would be wrong.

Function	Purpose
PF_AppGetBgColor	Retrieves the current background color.
	<pre>PF_AppGetBgColor(PF_App_Color bg_colorP);</pre>
PF_AppGetColor	Retrieves the color for the specified UI element. See AE_EffectSuites.h for a complete enumeration of available PF_App_Color values; basically any color in After Effects' UI can be retrieved. CC adds several new PF_App_ColorType enum values for new elements that can be queried. Note that in CS6, the color definitions are off from FILL_LIGHT downward. Use following psuedocode for CS6 only: GetColor(enum e) { if host_is_CS6 and e >= FILL_LIGHT e += 3 call real GetColor }
	<pre>PF_AppGetColor(PF_App_ColorType color_type, PF_App_Color *app_colorP);</pre>
PF_AppGetLanguage	New in CC. Retrieves the active displayed language of AE UI so plug-in can match. Here are the possible language codes as of CC: • Chinese - zh_CN • English - en_US • French - fr_FR • German - de_DE • Italian - it_IT • Japanese - ja_JP • Korean - ko_KR • Spanish - es_ES PF_AppGetLanguage(
PF_GetPersonalInfo	A_char lang_tagZ); Retrieves the user's registration information. PF_GetPersonalInfo(PF_AppPersonalTextInfo *ptiP);
	<pre>typedef struct PF_AppPersonalTextInfo { A_char name[PF_APP_MAX_PERS_LEN + 1]; A_char org[PF_APP_MAX_PERS_LEN + 1]; A_char serial_str[PF_APP_MAX_PERS_</pre>
PF_GetFontStyleSheet	Retrieves font style sheet information for the fonts used in After Effects' UI. Trivia: The font used in After Effects' UI starting in 15.0 is Adobe Clean. Before that, it was Tahoma on Windows and Lucida Grande on macOS X. PF_GetFontStyleSheet (
134	PF_FontStyleSheet 39. Sheet Utility Functions PF_FontName *font_nameP0, A_short *font_numPS0, A_short *sizePS0, A_short *stylePS0);

39.3 Advanced Appsuite: You Can Do That?!

PF_AdvAppSuite was originally designed for some pretty nefarious purposes; an external application was pretending to be an After Effects plug-in, and required ways to notify After Effects of the changes it had made to the project. Our API impurity is your gain.

39.4 PF_AdvAppSuite2

Function	Purpose
PF_SetProjectDirty	Tells After Effects that the project has been change
	since it was last saved.
	<pre>PF_SetProjectDirty(void);</pre>
PF_SaveProject	Saves the project to the current path. To save the project
	elsewhere, use AEGP_SaveProjectToPath().
	<pre>PF_SaveProject(void);</pre>
PF_SaveBackgroundState	Stores the background state (After Effects' position i
	the stacking order of open applications and windows).
	PF_SaveBackgroundState(void);
PF_ForceForeground	Brings After Effects to the front of all currently ope
	applications and windows.
	PF_ForceForeground(void);
PF_RestoreBackgroundState	Puts After Effects back where it was, in relation to other
	applications and windows.
	<pre>PF_RestoreBackgroundState(void);</pre>
PF_RefreshAllWindows	Forces all After Effects windows to update. Note that
	although the Composition panel will be refreshed, th
	does not guarantee a new frame will be sent to Externational Monitor Preview plug-ins.
	<pre>PF_RefreshAllWindows(void);</pre>
PF_InfoDrawText	Writes text into the After Effects info palette.
	PF_InfoDrawText(
	<pre>const A_char *line1Z0, const A_char *line2Z0);</pre>
DE InfoDrayColor	Draws the specified color in the After Effects inf
PF_InfoDrawColor	palette (alpha is ignored).
	PF_InfoDrawColor(
	PF_Pixel color);
PF_InfoDrawText3	Writes three lines of text into the After Effects inf
	palette.
	<pre>PF_InfoDrawText3(const A_char *line1Z0,</pre>
	<pre>const A_char *line2Z0,</pre>
	<pre>const A_char *line3Z0);</pre>
PF_InfoDrawText3Plus	Writes three lines of text into the After Effects inf
39.4. PF_AdvAppSuite2	palette, with portions of the second and third lines le and right justified.
	PF_InfoDrawText3Plus(
	const A_char *line1Z0,
	const A_char *line2_jrZ0,
	<pre>const A_char *line2_jlZ0, const A_char *line3_jrZ0,</pre>
	<pre>const A_char *line3_j120;</pre>
PF_AppendInfoText	Appends characters to the currently-displayed info tex

39.5 Formatting Time

 ${\tt PF_AdvTimeSuite} \ provides \ several \ functions \ to \ match \ how \ After \ Effects \ displays \ time. \ In \ fact, these \ are \ the \ same \ functions \ we \ use \ internally.$

39.5.1 PF_AdvTimeSuite4

Function	Purpose
PF_FormatTimeActiveItem	Given a time value and scale, returns a formatted string representing that time. If durationB is TRUE, appropriate units will be appended.
	PF_FormatTimeActiveItem(A_long
PF_FormatTime	Contextualizes the formatted time string for the given PF_InData and PF_EffectWorld (i.e., layer time).
	PF_FormatTime(PF_InData *in_data, PF_EffectWorld *world, A_long time_valueUL, A_u_long time_scaleL, PF_Boolean durationB, A_char *time_buf);
PF_FormatTimePlus	Allows you to select composition or layer time.
	PF_FormatTimePlus(PF_InData *in_data, PF_EffectWorld *world, A_long time_valueUL, A_u_long time_scaleL, PF_Boolean comp_timeB, PF_Boolean durationB, A_char *time_buf);
PF_GetTimeDisplayPref	Returns the starting frame number (specified by the user in composition settings), and the composition's time display preferences. Updated in 14.2 to support higher frame rates.
	PF_GetTimeDisplayPref(PF_TimeDisplayPref2 *tdp, A_long *starting_num); typedef struct { A_char display_mode; A_long framemax; A_long frames_per_foot; A_char frames_start; A_Boolean nondrop30B; A_Boolean honor_source_ →timecodeB; A_Boolean use_feet_framesB; } PF_TimeDisplayPrefVersion3;
PF_TimeCountFrames	New in 15.0. Returns the index of the frame in the current comp.
	PF_TimeCountFrames(const A_Time *start_timeTP, const A_Time *time_stepTP, A_Boolean include_partial_frameB, A_long *frame_countL);
	Chamber 20 Hasful Hillity Functions

39.6 Affecting The Timeline

Long ago, we helped a developer integrate their stand-alone tracker with After Effects by exposing a set of functions to give them some way to notify us of, and be notified of, changes to the timeline.

With the numerous AEGP API calls available, these aren't used much, but they're still available.

Don't confuse this suite with AEGP_ItemSuite.

39.6.1 PF_AdvItemSuite1

Function	Purpose
PF_MoveTimeStep	Moves current time num_stepsL in the specified direction.
	<pre>PF_MoveTimeStep(PF_InData</pre>
PF_MoveTimeStepActiveItem	Moves num_stepsL in the specified direction, for the active item.
	<pre>PF_MoveTimeStepActiveItem(PF_Step time_dir, A_long num_stepsL);</pre>
PF_TouchActiveItem	Tells After Effects that the active item must be updated. PF_TouchActiveItem (void);
PF_ForceRerender	Forces After Effects to rerender the current frame. PF_ForceRerender(PF_InData *in_data, PF_EffectWorld *world);
PF_EffectIsActiveOrEnabled	Returns whether the effect which owns the PF_ContextH is currently active or enabled (if it isn't, After Effects won't be listening for function calls from it).
	<pre>PF_EffectIsActiveOrEnabled(PF_ContextH contextH, PF_Boolean *enabledPB);</pre>

39.7 Accessing Auxiliary Channel Data

Some file types contain more than just pixel data; use PF_ChannelSuite to determine whether such information is present, and the macros in AE_ChannelSuites.h to retrieve it in the format you need.

39.7.1 PF_ChannelSuite1

Function	Purpose
PF_GetLayerChannelCount	Retrieves the number of auxiliary channels associated
	with the indexed layer.
	PF_GetLayerChannelCount(
	PF_ProgPtr effect_ref,
	PF_ParamIndex param_index,
	A_long *num_channelsPL);
PF_GetLayerChannelIndexedRefAndDesc	Retrieves (by index) a reference to, and description of the specified channel.
	<pre>PF_GetLayerChannelIndexedRefAndDesc(PF_ProgPtr effect_ref,</pre>
	PF_ParamIndex param_index,
	PF_ChannelIndex channel_index,
	PF_Boolean *foundPB,
	<pre>PF_ChannelRef *channel_refP, PF_ChannelDesc *channel_descP);</pre>
PF_GetLayerChannelTypedRefAndDesc	Retrieves an auxiliary channel by type. Returned information is valid only if foundPB returns TRUE.
	PF_GetLayerChannelTypedRefAndDesc(
	PF_ProgPtr effect_ref,
	PF_ParamIndex param_index,
	PF_ChannelType channel_type,
	PF_Boolean *foundPB,
	<pre>PF_ChannelRef *channel_refP, PF_ChannelDesc *channel_descP);</pre>
	PF_DataType will be one of the following:
	PF_DataType_FLOAT - 34 bytesPF_DataType_DOUBLE - 38 bytes
	• PF_DataType_LONG - 34 bytes
	• PF_DataType_SHORT - 32 bytes
	• PF_DataType_FIXED_16_16 - 34 bytes
	• PF_DataType_CHAR - 31 byte
	• PF_DataType_U_BYTE - 31 byte
	• PF_DataType_U_SHORT - 32 bytes
	• PF_DataType_U_FIXED_16_16 - 34 bytes
	• PF_DataType_RGB - 3 bytes
	PF_ChannelType will be one of the following:
	• PF_ChannelType_DEPTH
	• PF_ChannelType_NORMALS
	• PF_ChannelType_OBJECTID
	• PF_ChannelType_MOTIONVECTOR
	• PF_ChannelType_BK_COLOR
	• PF_ChannelType_TEXTURE
	• PF_ChannelType_COVERAGE
	• PF_ChannelType_NODE
	• PF_ChannelType_MATERIAL
	• PF_ChannelType_UNCLAMPED
	PF_ChannelType_UNKNOWN
PF_CheckoutLayerChannel	Retrieves the PF_ChannelChunk containing the data
	associated with the given PF_ChannelRefPtr.
44	PF_Checkout Chapter 39. eUseful Utility Function PF_ProgPtr effect_ref,
	PF_ChannelRefPtr channel_refP,

long

long

what_time, duration,

Motion Blur

Effects handle their own motion blur, using *PF_InData>shutter_angle* along with *PF_InData>shutter_phase*.

The plug-in must set *PF_OutFlag_I_USE_SHUTTER_ANGLE* so After Effects knows it needs this information.

They must *check out* their own parameters at other times to examine their change over the shutter interval.

If the plug-in checks out parameters outside this interval, set PF_OutFlag_WIDE_TIME_INPUT.

Doing so allows After Effects to compare the parameters within the sampling interval, and determine if they've changed.

Working With Paths

41.1 Accessing Path Data

Paths differ from other parameter types, in that their values are not directly accessible. In addition to checking them out and in (like layer parameters), you must use our path data function suites to obtain the details of the path at a given time. See *PF_PathQuerySuite1* and *PF_PathDataSuite*. Never use the values present in a path parameter when it's passed to you, without first checking it out; while deleted paths will not be available, further updating is done "lazily" (later); your effect won't see these changes unless it checks out the path.

41.2 Manipulating Path Data

You can also use the AEGP_MaskOutlineSuite3 to manipulate paths. See Cheating Effect Usage of AEGP Suites. Path parameters are treated as opaque blobs of data; get and set functions must be used to access and manipulate them. Like layer parameters, they must be checked out (and in!) by effects which access them.

41.3 Vertices

Path vertices are more complex than simple points. All member variables are PF_FpLongs (doubles), and are in the layer's coordinate space.

41.4 PF_PathVertex

Member	Description
Х	The location of the vertex.
У	
tan_in_x	The incoming tangent point.
tan_in_y	
tan_out_x	The outgoing tangent point.
tan_out_y	

41.5 PF_PathDataSuite

This suite provides information about paths (sequences of vertices).

sure why you'd ever need this, don't use it. Math is hard.

Function	Description
PF_PathIsOpen	Returns TRUE if the path is not closed (if the beginning
	and end vertex are not identical).
	<pre>PF_PathIsOpen(PF_ProgPtr</pre>
	PF_PathOutlinePtr pathP,
	<pre>PF_Boolean *openPB);</pre>
PF_PathNumSegments	Retrieves the number of segments in the path. N seg-
	ments means there are segments [0.N-1]; segment J is defined by vertex J and $J+1$.
	PF_PathNumSegments(
	PF_ProgPtr effect_ref0, PF_PathOutlinePtr pathP,
	A_long *num_segmentsPL);
PF_PathVertexInfo	Retrieves the PF_PathVertex for the spec-
	ified path. The range of points is [0.
	<pre>num_segments]; for closed paths, vertex[0] == vertex[num_segments].</pre>
	PF_PathVertexInfo(
	PF_ProgPtr effect_ref0, PF_PathOutlinePtr pathP,
	A_long which_pointL,
	<pre>PF_PathVertex *vertexP);</pre>
PF_PathPrepareSegLength	This fairly counter-intuitive function informs After Ef-
	fects that you're going to ask for the length of a segment
	(using PF_PathGetSegLength below), and it'd better get ready. frequencyL indicates how many times
	you'd like us to sample the length; our internal effects
	use 100.
	PF_PathPrepareSegLength(
	<pre>PF_ProgPtr effect_ref0, PF_PathOutlinePtr pathP,</pre>
	A_long which_segL,
	A_long frequencyL, PF_PathSegPrepPtr *lengthPrepPP);
PF_PathGetSegLength	Retrieves the length of the given segment.
	<pre>PF_PathGetSegLength(PF_ProgPtr</pre>
	PF_PathOutlinePtr pathP,
	A_long which_segL,
	<pre>PF_PathSegPrepPtr *lengthPrepP0, PF_FpLong *lengthPF);</pre>
PF_PathEvalSegLength	Retrieves the location of a point lengthF along the given
rr_racmevaroegnemgem	path segment.
	PF_PathEvalSegLength(
	<pre>PF_ProgPtr effect_ref0, PF_PathOutlinePtr pathP,</pre>
	PF_PathSegPrepPtr *lengthPrepPP0,
	A_long which_segL, PF_FpLong lengthF,
	PF_FpLong *x,
M. F. DE Dalla Dalla Oc. "	PF_FpLong *y);
l1.5. PF_PathDataSuite PF_PathEvalSegLengthDeriv1	Retrieves the location, and the first derivative, of a point
	lengthF along the given path segment. If you're not
	sure why you'd ever need this don't use it Math is hard

41.6 PF_PathQuerySuite1

This suite is used to identify and access the paths associated with the effect's source layer.

Function	Purpose
PF_NumPaths	Retrieves the number of paths associated with the effect's source layer.
	<pre>PF_NumPaths(PF_ProgPtr effect_ref, A_long *num_pathsPL);</pre>
PF_PathInfo	Retrieves the PF_PathID for the specified path.
	<pre>PF_PathInfo(PF_ProgPtr effect_ref, A_long indexL, PF_PathID *unique_idP);</pre>
PF_CheckoutPath	Acquires the PF_PathOutlinePtr for the path at the specified time.
	<pre>PF_CheckoutPath(PF_ProgPtr</pre>
PF_CheckinPath	Releases the path back to After Effects. Always do this, regardless of any error conditions encountered. Every checkout must be balanced by a checkin, or pain will ensue.
	PF_CheckinPath(PF_ProgPtr effect_ref, PF_PathID unique_id, PF_Boolean changedB, PF_PathOutlinePtr pathP);

Accessing Camera & Light Information

Using functions provided in the *AEGP_PFInterfaceSuite*, effects can access camera and lighting information for the layer to which they're applied; see the Resizer sample.

You can also use many of the other functions from AE_GeneralPlug.h; the possibilities are vast.

Color Space Conversion

Different pixel formats are useful for different operations. After Effects exposes its internal functions through PF_ColorCallbacksSuite. Here are the supported formats.

43.1 Pixel Types For Different Color Spaces

Pixel Type	Data Structure
8 bpc ARGB	
	typedef struct {
	A_u_char alpha, red, green, blue;
	} PF_Pixel8;
16 bpc ARGB	
	typedef struct {
	A_u_short alpha, red, green, blue;
	} PF_Pixel16;
32 bpc ARGB	
	typedef struct {
	PF_FpShort alpha, red, green, blue;
	} PF_PixelFloat, PF_Pixel32;
HLS (Hue, Lightness, Saturation)	
1125 (1146) 2.8.10.1055, 2.10.141.011)	typedef PF_Fixed PF_HLS_PIXEL[3]
	olbono 11 Transa 11 Tuno Transa Transa (a)
YIQ (luminance, in-phase chrominance, quadrature	
chrominance)	typedef PF_Fixed PF_YIQ_PIXEL[3]

Plug-ins can draw on image processing algorithms written for nearly any color space by using the following callback functions.

43.2 Color Space Conversion Callbacks

Func-	Purpose	Re-
tion		places
RG-	Given an RGB pixel, returns an HLS (hue, lightness, saturation) pixel. HLS values are scaled	PF_RGB_TO_HLS
BtoHL	S from 0 to 1 in fixed point.	
HLSto	R GB ven an HLS pixel, returns an RGB pixel.	PF_HLS_TO_RGB
RG-	Given an RGB pixel, returns a YIQ (luminance, inphase chrominance, quadrature chromi-	PF_RGB_TO_YIQ
BtoYIC	Q nance) pixel. Y is 0 to 1 in fixed point, I is -0.5959 to 0.5959 in fixed point, and Q is -0.5227	
	to 0.5227 in fixed point.	
YIQ-	Given a YIQ pixel, returns an RGB pixel.	PF_YIQ_TO_RGB
toRGB		
Lu-	Given an RGB pixel, returns 100 times its luminance value (0 to 25500).	PF_LUMINANCE
mi-		
nance		
Hue	Given an RGB pixel, eturns its hue angle mapped from 0 to 255, where 0 is 0 degrees and 255	PF_HUE
	is 360 degrees.	
Light-	Given an RGB pixel, returns its lightness value (0 to 255).	PF_LIGHTNESS
ness		
Sat-	Given an RGB pixel, returns its saturation value (0 to 255).	PF_SATURATION
ura-		
tion		

Changing Parameter Orders, the Nice Way

It is possible to add or remove parameters from a plug-in, without forcing users to re-apply all instances of that plug-in to use the updated version. However, some advance planning on your part is necessary to allow for such changes. Your users (and technical support staff) will appreciate the effort.

You must first create a parameter array index. During *PF_Cmd_PARAM_SETUP*, assign index values to each parameter as you add them, using a simple enumeration. The order of enumeration corresponds to the order in which the parameters are registered during *PF_Cmd_PARAM_SETUP*, which in turn determines the order in which they appear in the Effect Control and Timeline panels.

Create another enumeration for disk IDs. The order of this enumeration must *not* be changed, though you may add to the end of this list. Note that the order of this list need not correspond with that of the parameter array index. Parameter disk IDs should range from 1 to 9999. Why not zero? Long story...

In the early "wild west" days of After Effects plug-in programming, it was fairly common for developers not to bother with setting IDs. After Effects, realizing this, checked the ID of the first parameter added by that effect; if it was zero, it was assumed that the programmer hadn't bothered to ID params; After Effects then assigned each its own ID. This assumption works fine if you never set param IDs, but not so well if you start numbering your IDs from NULL. That's why.

Before calling PF_ADD_PARAM(), specify the disk ID in the PF_ParamDef.uu.id field. If no value is specified, After Effects makes parameters sequential starting with 1. The parameter's information is tagged with this ID when saved. In this way, After Effects can still understand that, although your "Foobarocity" slider is now the fourth parameter passed, it's the same parameter as when it was second.

To delete a parameter without forcing re-application, remove the code which creates it and its entry in the parameter array index list. However, *do not* remove its entry in the disk ID list. To add a new parameter, add an entry in the appropriate location in the parameter array indices list, add the parameter creation code, and append the disk ID to the end of the disk ID enumeration. To re-order, change the parameter array index list and reorder the parameter creation code appropriately.

44.1 Change defaults? Change IDs

If you don't, if someone saves a project with the old default and then reads it in with the new effect installed, that parameter will change to the new default value.

Presto! Instant support call.

This is another prime use case for PF_ParamFlag_USE_VALUE_FOR_OLD_PROJECTS from Parameter Flags.

Tips & Tricks

45.1 Best Practices

If your prototypes are anything like ours, the first version of your plug-in that runs without crashing differs radically from the version that actually ships.

How your plug-in responds to things like downsampling, errors and exceptions, pixel aspect ratio, out-of-memory situations, and being interrupted while processing determines how usable it is (and how many support requests you'll have to handle).

45.2 Responsiveness

Make your plug-ins as responsive as possible using PF_ABORT() and PF_PROGRESS() from *Interaction Callbacks*.

We actually test all our effects for interruptability; you'd be surprised how cranky users can get waiting for your pokey effect to finish processing a film resolution sequence!

After Effects' iteration functions inherently provide this functionality; you don't need to worry about calling the above functions from within your pixel processing functions.

45.3 Make Your Effect Easy To Find

It's possible to have your effect show up in the "Effects & Presets" palette when users search for something other than the plug-in's name.

Apply your effect (leaving the settings at default, unless you're very certain the user will want something different when they search for the given term), and select "Save selection as animation preset" from the effect controls palette.

Save it to the name by which you want users to find the plug-in.

Have your plug-in's installer put the resultant .ffx file into the \Presets directory, next to the After Effects executable.

Your preset will show up when users search for the name to which it was saved.

45.4 Sampling Pixels At (x,y)

Sometimes, instead of just processing every pixel, you'll want to get to a specific offset within the input frame. Below is one way to sample the pixel at a given (x,y) location; similar code could be used to write to the given location.

Special thanks to Paul Miller for answering this question.

45.5 Where's The Center Of A Pixel?

Deeeeeep, man. After Effects rotates around the upper left corner of the upper left pixel when the anchor point (see User Documentation) is (0,0).

However, the subpixel sample and area sample callbacks actually treat (.0, .0) as a direct hit. To compensate for this, subtract 0.5 from x and y values before calling those functions.

The matrix functions (transform_world from PF_WorldTransformSuite1) don't have this problem.

When translating an image by a subpixel amount, make the output layer one pixel wider than its input, and leave the origin at (0,0).

45.6 Text Layer Origin

Almost all layer types have their origin in the upper-left corner. Not so with text layers!

A text layer origin by default is at the bottom-left baseline position of the first character. You can see this if you create a text item and then pick the layer so the anchor point shows up.

Look at where the default anchor point location is. The transform is not at the corner of the layer rectangle.

45.7 Clean Slate

You don't necessarily begin effect processing with a clean output slate. Our Gaussian blur filter, in an effort to do so, performs the following before rendering:

```
src_rect.left = in_data>output_origin_x;
src_rect.right = src_rect.left + input>width;
src_rect.top = in_data>output_origin_y;
src_rect.bottom = src_rect.top + input>height;

err = PF_FILL(NULL, NULL, output);

if (!err) {
   err = PF_COPY(&params[0]>u.ld, output, NULL, &src_rect);
}
```

45.8 Caching Behavior

```
After Effects provides numerous ways to specify caching behavior. PF_OutFlag_NON_PARAM_VARY, PF_OutFlag_WIDE_TIME_INPUT, PF_OutFlag_I_USE_SHUTTER_ANGLE, PF_OutFlag_I_SYNTHESIZE_AUDIO, PF_OutFlag2_I_USE_3D_CAMERA, and PF_OutFlag2_I_USE_3D_LIGHTS (all from PF_OutFlags) all influence caching decisions.
```

Supporting *dynamic outflags* can greatly improve performance, preventing After Effects from invalidating your effect's cache as aggressively as it otherwise would.

Confirm that your plug-in performs well with different After Effects cache settings. Does your plug-in get called to update as often as expected, or does After Effects think it has valid pixels when you think it doesn't?

45.9 Global Performance Cache Consideratons

With the new caching in CS6, you may need to clear cached frames after changing your effect's rendering, so that frames rendered and stored in the cache prior to the change will not be reused. To do so manually during development:

- 1) In Preferences > Media & Disk Cache, disable the Disk Cache
- 2) Click "Empty Disk Cache" just to be sure (disabling the Disk Cache in step 1 only disables the *writing* of disk cache, not necessarily the usage)
- 3) Relaunch

If you ever encounter a glitch, it likely a legitimate bug in your effect, such as improper rectangle handling in SmartFX.

On the other hand, if you fix a rendering bug in your plug-in and ship an update, you can't expect all users will empty their disk caches. A user may have a disk cache of the buggy frame and it needs to be invalidated. What to do? Update your plug-in's effect version. This value (and the AE build number) is part of the cache key, so if you update it any frames cached containing content from your plug-in will no longer match.

45.7. Clean Slate 159

45.10 Some Thoughts On Time From A Long-Time Developer

Stoney Ballard put together the following summary of how time works with effects; you may find it helpful.

There are five in_data parameters that describe time to a filter:

- current_time
- time_step
- local time step
- total time
- time scale

Their values are dependent on:

- The frame being rendered
- The duration of the layer and composition The frame rate of the comp
- Any Time Stretch Any Time Remapping
- The time behavior of an outer composition (one enclosing the composition with the layer being filtered)
- The setting of the "Preserve frame rate when nested or in render queue" (PFR) switch

The frame being rendered affects current_time. It is expressed in the local (layer) time system. If the PFR switch is off, current_time may be any non-negative value. If on, it will be restricted to a multiple of time_step and local_time_step. Layer duration affects only total_time. Comp duration is a factor only when Time Remapping (TR) is on. In that case, total_time is the larger of layer duration and composition duration. Composition frame rate affects only the time_scale. Time Stretch affects only time_step and local_time_step. If the time stretch is negative, these values are negative. Even if the layer's duration (as seen in

the comp) changes, total_time remains unaffected. This works as if Time Stretch was *above* a filter, but *below* an outer comp. PFR does not alter the effect of Time Stretch. Time Stretch is different than an outer comp, since it affects both step params equally, while an outer comp affects only time_step.

Time Remapping happens *below* the filter, so that it does not affect the time params other than the total_time. When TR is on, the layer is lengthened to the same as the comp (but never shortened), regardless of how much time it actually takes, or where in the comp the layer is. This may cause total_time to be larger. It has nothing to do with the actual time map, just whether or not it's enabled.

The biggest variation comes from being nested in an outer comp, unless PFR is on. When PFR is on, a filter is completely isolated from time variations in an outer comp. Of course, current_time will not necessarily move in increments of time_step in that case. It may skip frames or go backwards.

When PFR is off, local_time_step, total_time, and time_scale remain set to what they were for the inner comp, but time_step contains the time to the next frame in the outer comp, expressed in the local time system. This may be any value, including 0. This can be interpreted as an instantaneous time rate, rather than a duration. A 0 value can last for an arbitrary number of rendered frames, but the current_time won't change on the local layer.

Looked at from the other direction:

current_time is quantized to time_step intervals unless rendering an outer comp with PFR off for the inner comp. This is the current time in the layer, not in any comp.

The value of local_time_step is affected only by Time Stretch. It can never be zero, but it can be negative.

time_step and local_time_step are always the same value unless rendering an outer comp with PFR off. time_step is also affected by the time behavior of an outer comp (with PFR off). It can have any value, positive, negative, or zero, and can be different for every frame (of the outer comp). time_step can be used to determine the duration of the current frame (with PFR off).

total_time is the duration of the layer, unless Time Remapping is on, which makes it the larger of the layer duration and the duration of the comp.

time_scale is the scale such that total_time / time_scale is the layer duration in seconds in its comp. It is affected only by the comp frame rate, although presumably all the time values could be scaled proportionately for any reason.

A layer's intrinsic frame rate (if it has one) is not visible anywhere, although it's usually the same as the comp frame rate. If a filter needs to access the actual frames of a clip, it can do so

only by being in a comp of the same frame rate, and with no Time Stretch or Time Remapping applied to its layer. It should use local_time_step to determine where the frames are.

45.11 Rate x Time == Pain!

Be careful if one of your parameters is a speed or velocity parameter. Consider the ripple effect. It assumes a constant and uses the current time to determine how far along the ripple has gone (d = v * t). If the user interpolates the speed over time, you should integrate the velocity function from time zero to the current time. Ripple does *not* do this, but provides a "phase" parameter that the user can interpolate as they wish, providing correct results as long as the speed is set to zero. If you want to provide the correct behavior, you can sample (and integrate) the speed parameter from the beginning of time until the current time using PF_CHECKOUT_PARAM(), or you can provide a "phase" or "distance" parameter and warn the user about interpolating the speed. The cost of checking out many parameter values is negligible compared to rendering, and is the recommended approach.

If you check out parameter values at other times, or use layer parameters at all, you *must* check in those parameters when finished, even if an error has occurred. Remember, checked-out parameters are read-only.

45.12 Testing

Try using your plug-in in RAM previews to ensure you handle out-of-memory conditions gracefully. Does your plug-in handle running out of memory gracefully?

If you receive PF_Err_OUT_OF_MEMORY (from *Error Codes*) when requesting memory, do you pass it back to After Effects?

What happens when your video effect is applied to an audio-only layer? Test with projects created using older versions of your plug-in.

SmartFX

The SmartFX API provides bidirectional communication between effects and After Effects, enabling many performance optimizations and providing previously unavailable dependency information. This extension of the effect API is the way to implement 32-bit per channel support in After Effects.

Normal effect plug-ins are given a full-sized input buffer, and asked to render a full-sized output buffer. While output *extent_hint* specifies the portion of the output buffer that must actually be filled, this scheme is still very inefficient if the effect does not need its entire input. Also, many effects don't use extent hints.

46.1 The Way Things Were

Consider a blur effect applied to a huge layer which is mostly off-screen, or viewed through a small region of interest, or masked down to a small size. Only a small section of the output needs to be rendered, indicated to the effect using the output extent_hint. Only a small section of the input to be blurred is needed as well - the output extent_hint expanded by the blur radius. However, using the legacy effects API, there is no way for After Effects to know this, so the entire layer is passed to the plug-in. These extra pixels can be extremely expensive and wasteful to compute, especially in the case of prior effects or nested comps.

46.2 The Way Things Are Now

SmartFX solves this problem by reversing the calling sequence. The effect is told how much of its output is required, and must explicitly *ask* the host for the inputs it needs. The render process is split into two parts: pre-render and render.

During pre-render, the effect describes the input pixel data it needs; this necessary input can vary based on anything you like (non-input layer parameters, non-layer parameters, information from in_data, settings in sequence data...). The effect must also return the extent of the resulting output, which may be smaller than the requested size if there are empty pixels in the requested portion of the layer.

During the render stage, the effect can *only* retrieve pixels that it has previously requested. This two-pass approach facilitates many important optimizations. For example, an effect which multiplies or mattes one input against another might discover that its first input is not

needed at all, if the mask does not intersect it. There are also important optimizations that are performed internally by After Effects to ensure that image buffers are copied as little as possible, and these optimizations are only possible after the host knows the buffer sizes and for all inputs and outputs.

Like AEGPs, SmartFX plug-ins are never unloaded by After Effects.

46.3 Content Bounds

The content bounds of a node are the largest possible result rectangle that can be returned from a call to PreRender. It absolutely cannot vary depending on current render request or anything else. It should be calculated carefully, not loosely.

This calculation is very important. It is an intrinsic property of the node (and its inputs) and is fixed once the graph is built. Violation of it can and probably will cause all sorts of problems in various pieces of code.

46.4 How To Smartify

Effects which set PF_OutFlag2_SUPPORTS_SMART_RENDER (from *PF_OutFlags*) will receive the SmartFX calls PF_Cmd_SMART_PRE_RENDER and PF_Cmd_SMART_RENDER (from *Frame Selectors*), instead of the older PF_Cmd_FRAME_SETUP / PF_Cmd_RENDER / PF_Cmd_FRAME_SETDOWN sequence. To preserve compatibility with non-smartified hosts, you may want to continue supporting the older commands too.

46.5 PF_Cmd_SMART_PRE_RENDER

After Effects requests output from the effect. The effect tells After Effects what input it needs to generate that output, through the use of callback functions, and by manipulating the structures in the extra parameter. An effect cannot access the pixels of any layer inputs it has not checked out during $PF_Cmd_SMART_PRE_RENDER$. So all layer inputs that an effect might possibly need must be checked out in advance using checkout_layer. If an effect might need certain layer inputs, they must be checked out now, even if later during rendering the effect may decide that the layer isn't needed. Also, since no parameter array is passed to SmartFX during $PF_Cmd_SMART_PRE_RENDER$ or $PF_Cmd_SMART_RENDER$, any non-layer parameters needed must be retrieved using $PF_CHECKOUT_PARAM$ (from $Interaction\ Callbacks$)

46.6 PF_PreRenderExtra

Member	Purpose	
PF_PreRenderInput	Describes what After Effects needs rendered (in	the
	PF_RenderRequest), and the bit depth requested	l (in
	the aptly-named bitdepth member).	
	typedef struct {	
	PF_LRect rect;	
	PF_Field field;	
	<pre>PF_ChannelMask channel_mask;</pre>	
	PF_Boolean preserve_rgb_of_zero_	_
	<pre>→alpha; char unused[3];</pre>	
	long reserved[4];	
	} PF_RenderRequest;	
	rect is in layer coordinates. field is also relative to	the
	layer origin; whether the active field falls on even or	
	scanlines of the output buffer depends on the origin	
	the output buffer.	
	channel_mask specifies for which channels the	ef-
	fect should provide output.	
	Data written to other channels will not be honored.	
	It will be one or more of the following, or'd togethe	r:
	• PF_ChannelMask_ALPHA	
	• PF_ChannelMask_RED	
	PF_ChannelMask_GREEN PF_Gl_N_N_N_N_N_N_N_N_N_N_N_N_N_N_N_N_N_N_	
	PF_ChannelMask_BLUE PF_ChannelMask_ADCR	
	PF_ChannelMask_ARGBIf preserve_rgb_of_zero_alpha pixels	ic
	TRUE, the effect must propagate the color conten	
	transparent pixels through to the output.	t OI
		om,
	· · · · · · · · · · · · · · · · · · ·	nich
	tells After Effects that the effect may set alpha	ı to
	non-zero values for such pixels, restoring them	ı to
	visibility.	
PF_PreRenderOutput	Filled in by the effect to tell After Effects what outp	ut it
	plans to generate, based on the input.	
	typedef struct {	
	PF_LRect result_	
	⇔rect;	
	PF_LRect max_resu:	lt_
	→rect;	
	PF_Boolean solid; PF_Boolean reserved,	
	PF_RenderOutputFlags flags;	•
	void* pre_rende	er_
	-data;	=
	<pre>PF_DeletePreRenderDataFunc func;</pre>	
	} PF_PreRenderOutput;	
	pre_render_data will be passed back to the ef	fect
	during PF_Cmd_SMART_RENDER.	
	Currently, the only PF_RenderOutputFlags	
	PF_RenderOutputFlag_RETURNS_EXTRA_F	
PF_PreRenderCallbacks 66	Currently, there is only one callback checkout_layer. check@hapteri46ch&ma	
	the effect.	ıı u y A
	It must be positive and unique. After Effects popul	ates
	the PF_CheckoutResult.	
	uic fr_onechouthesuit.	

46.7 preserve_rgb_of_zero_alpha

preserve_rgb_of_zero_alpha is used both as input to the effect, to tell it what to render, and as output from the effect, to describe the input it needs (as passed to the checkout call). When preserve_rgb_of_zero_alpha is set in an input request, the effect must pass it recursively when making checkouts, otherwise prior effects and masking will eliminate those pixels that the effect would reveal. Use of this is discouraged, though still supported in CS3 (8.0).

46.8 Rectangles

Effects must set both result rectangles accurately. After Effects' caching system relies upon them, incorrect values can cause many problems. If the plug-in returns a result_rect smaller than the request_rect, that tells After Effects the pixels inside the request_rect but outside the result_rect are empty.

Similarly, max_result_rect must encompass all non-zero pixels; the effect will never be asked to render anything outside this region. If there are pixels outside this rectangle, they will never be displayed.

Mis-sized output rectangles can cause problems as well. If these rectangles are too big, a loss of performance results.

Not only will many empty pixels be cached (robbing the application of valuable memory), the effect may be unnecessarily asked to render large regions of nothing. For this reason, the max_result_rect must be computed correctly, rather than set to some arbitrarily large size.

Both result_rect and max_result_rect may vary depending on the effect's parameters, the current time, et cetera; they are valid only for the given invocation of the effect. However, max_result_rect cannot depend on the specific render request. It must be the same no matter what portion of the output is requested by After Effects.

It is legal to return an empty result_rect if the request_rect doesn't intersect the effect's output pixels; no rendering need be done.

After Effects may also call the effect with an empty request_rect, meaning the effect is only being asked to compute the max result rect.

preserve_rgb_of_zero_alpha can influence the bounds computation process (both result_rect and max_result_rect) and must be respected if the effect behaves differently depending on this setting.

46.9 The "Size" Of A Layer

As with non-smart effects, each smart effect can arbitrarily shrink or expand its requested input. They cannot depend on a fixed frame size, and the size of the input may change over time.

For example, the user could apply an animated drop shadow to a layer, which would add pixels to different edges of the layer at different times, depending on the direction in which the shadow is cast.

Some effects (for example, those which need to align one layer against another) need some notion of "size." This could be defined two ways, each with advantages and disadvantages.

The size of the original layer, before any effects and downsampling are applied, is given in_data>width/height. As this value is unaffected by subsequent effects, it can act an absolute reference for things like center points.

However, this is not fool-proof, as the user could have applied a distortion or translation effect. Also, this value is available only for the layer to which the effect is applied, not other layer parameters.

...or...

Every layer input has a max_result_rect which encompasses all pixel data, in some sense the master "size" of a layer.

It is available for all layers, but changes over time according to previously applied effects, possibly in ways the user might not expect (as in the drop shadow example above).

Note that the ref_width/height and max_result_rect for an input may be obtained without rendering, by calling checkout_layer with an empty request_rect.

This is fairly efficient, and can be useful if the layer "size" is needed first to determine exactly which pixels are required for rendering.

This is an example of requesting a layer in pre-render and then never calling checkout_layer (in this case, there are none).

46.10 Flag On The Play

Normally, the max_result_rect of a given PF_RenderRequest will be cropped to the bounds of any applied mask.

However, if PF_OutFlag2_REVEALS_ZERO_ALPHA is set, the max_result_rect will be the size of the layer.

46.11 PF_Cmd_SMART_RENDER

The effect will receive at most one PF_Cmd_SMART_RENDER call for each pre-render.

Note that render may never be called at all. After Effects may have only wanted to to perform some bounds computations, or it may have subsequently discovered that an effect's output is not needed at all (which can happen, for example, if the pre-render phase for a track matter returns a rectangle that does not intersect the effect's output.)

All effects must be able to handle Pre-Render without Render without leaking resources or otherwise entering an unstable state.

During PF_Cmd_SMART_RENDER, the extra parameter points to a PF_SmartRenderExtra.

46.12 PF_SmartRenderExtra

Member	Purpose
PF_SmartRenderInput	Consists of a <i>PF_RenderRequest</i> , the bitdepth, and a pointer to pre_render_data (allocated during <i>PF_Cmd_SMART_PRE_RENDER</i>). This PF_SmartRenderInput is identical to that passed in the corresponding <i>PF_Cmd_SMART_PRE_RENDER</i> .
PF_SmartRenderCallbacks	
	allowed to check out output until at least one input has been checked out (unless the effect has no inputs at all). NOTE: For optimal memory usage, request the output as late as possible, and request inputs as few at a time as possible.

46.13 When To Access Layer Parameters

Parameters other than layer inputs may be freely checked out at any point. Layer inputs must be accessed during:ref:*PF_Cmd_SMART_PRE_RENDER* <*effect-basics/command-selectors.frame-selectors>*.

However, you aren't required to actually use every input.

If you check out a frame (or portion thereof) in *PF_Cmd_SMART_PRE_RENDER* and do not subsequently check it out in PF_Cmd_SMART_RENDER, it need never be rendered, greatly improving performance.

46.14 Wait, Gimme That Layer Back!

checkout_layer_pixels can only be called once with the checkout_id used earlier in PreRender. There has to be a one-to-one mapping on the number of checkouts made in PreRender and SmartRender. If you need to check out the pixels of a layer more than once, perhaps because of the structure of your code, just use more than one checkout_id. In PreRender, call checkout_layer on the same layer with different unique checkout_ids. Then in SmartRender, use a different one of those checkout_ids each time checkout_layer_pixels is called in SmartRender.

Effect UI & Events

Effects can provide custom UI in two areas: (1) the Effect Controls Window (custom ECW UI), and (2) the Composition or Layer Windows (Custom Comp UI).

Effects that use custom UI should set PF_OutFlag_CUSTOM_UI (from *PF_OutFlags* during PF_Cmd_GLOBAL_SETUP (from *Global Selectors*), and handle the PF_Cmd_EVENT selector.

Custom ECW UI allows an effect to provide a parameter with a customized control, which can be used either with standard parameter types or *Arbitrary Data Parameters*.

Parameters that have a custom UI should set PF_PUI_CONTROL (from Parameter UI Flags) when adding the parameter.

Custom Comp UI allows an effect to provide direct manipulation of the video in the Composition or Layer Windows.

When the effect is selected, the Window can overlay custom controls directly on the video, and can handle user interaction with those controls, to adjust parameters more quickly and naturally.

Effects should register themselves to receive events by calling PF_REGISTER_UI.

After Effects can send events to effects for user interface handling and parameter management, integrating effects into its central message queue.

While many events are sent in response to user input, After Effects also sends events to effects which manage arbitrary data parameters.

The type of event is specified in *PF_EventExtra->e_type* and the various events are described below.

47.1 Events

Event	Indicates		
PF_Event	The wise Context (probably by opening a window) for events.		
	The plug-in is allowed to store state information inside the context using the context handle.		
	<i>PF_EventUnion</i> contains valid context and type, but everything else should be ignored.		
PF_Event			
	PF_EventUnion is empty.		
PF_Event	The userIchicked within the effect's UI. PF_EventUnion contains a PF_DoClickEventInfo.		
	Handle the mouse click and respond, passing along drag info; see sample code), within a context.		
	NOTE: As of 7.0, do not block until mouse-up; instead, rely on PF_Event_DRAG.		
PF_Event	_AlBOA&Click Event, PF_EventUnion contains a PF_DoClickEventInfo.		
	Request this by returning send_drag == TRUE from PF_Event_DO_CLICK.		
	Do this so After Effects can see new data from the user's changes.		
PF_Event	PF_Event_DrawWPF_EventUnion contains a PF_DrawEventInfo.		
PF_Event	PF_Event The Accept WAS Ideactivated a context (probably by bringing another window into the foreground).		
	PF_EventUnion is empty.		
PF_Event	_ <u>Æጀመፄቒ፟፟፠t</u> ኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒኒ		
PF_Event	_AL Conflext is open but nothing is happening. PF_EventUnion is empty.		
PF_Event	PF_Event The Jude useCisRover the plug-in's UI. Set the cursor by changing the PF_CursorType in the		
	PF_AdjustCursorEventInfo.		
	Use OS-specific calls to implement a custom cursor; tell After Effects you've done so by setting		
	PF_CursorType to PF_Cursor_CUSTOM.		
	Use an After Effects cursor whenever possible to preserve interface continuity.		
	Keystooken PF_EventUnion contains a PF_KeyDownEvent.		
PF_Event	NewighE_Stx Northication that the mouse is no longer over a specific view (layer or comp only).		

PF_EventExtra

This structure provide context information for the current event. After Effects passes a pointer to this structure in the extra parameter of the *Entry Point* function.

The PF_EventUnion (sent in the PF_EventExtra) varies with the event type, and contains information specific to that event.

Member	Purpose
contextH	Handle to the PF_Context.
	This drawing context is used with the <i>Drawbot suites</i>
	for drawing, and also for the <i>UI Callbacks</i> .
e_type	Which <i>event</i> is occurring.
u	A PF_EventUnion containing information specific to
	the event.
effect_win	A PF_EffectWindowInfo about the event if it oc-
	curs within the effects window.
	Otherwise, as of After Effects 5.0, effect_win can be
	replaced by a PF_WindowUnion.
	This struct contains both a PF_EffectWindowInfo
	and an PF_ItemWindowInfo, which (for now) is
	simply the port rectangle for the item window.
	Replacement only occurs if
	PF_USE_NEW_WINDOW_UNION was defined during
	compilation; otherwise, it will continue to be just a
	PF_EffectWindowInfo.
cbs	Pointer to <i>UI Callbacks</i> , which are needed to translate
	points between layer, composition, and screen coordi-
	nate systems.
evt_in_flags	Event Input Flags. This currently contains only one
	value, PF_EI_DONT_DRAW, which you should check
	before drawing!
evt_out_flags	One or more of the following, combined with a bitwise
	OR operation:
	• PF_EO_NONE
	• PF_EO_HANDLED_EVENT tells After Effects
	you've handled the event.
	• PF_EO_ALWAYS_UPDATE forces After Effects
	to rerender the composite in response to every
	click or drag; this is the same behavior generated
	by 'alt-scrubbing' the parameter value.
	PF_EO_NEVER_UPDATE prevents After Effects
	from rerendering the composite until the user
	stops clicking and dragging.
	• PF_EO_UPDATE_NOW tells After Effects to up-
	date the view immediately after the event returns
	after calling PF_InvalidateRect

48.1 PF_Context

PF_Context details the event's UI context.

Member	Purpose
magic	Do not change.
w_type	The window type. If you have Custom Comp and ECW UIs in the same plug-in, this is the way to differentiate between them (what kind of masochist are you, anyway?). • PF_Window_COMP, • PF_Window_LAYER, • PF_Window_EFFECT
reserved_flt	Do not change.
plugin_state[4]	An array of 4 A_longs which the plug-in can use to store state information for a given context.
reserved_drawref	A DRAWBOT_DrawRef for use with the <i>Drawbot suites</i> .
*reserved_paneP	Do not change.

48.2 PF_EffectWindowInfo

If an event occurs in the ECP, an PF_EffectWindowInfo is sent in PF_EventExtra.

Member	Purpose	
index	This indicates which parameter in the effect window is being affected. The controls are numbered	
	from 0 to the number of controls minus 1.	
area	This indicates if the control title (PF_EA_PARAM_TITLE) or the control itself	
	(PF_EA_CONTROL) are being affected. The title is the area still visible when the parame-	
	ter's topic ("twirly") is spun up.	
current_frameF_Rect indicating the full frame of the area occupied by the control.		
param_tit	param_titleA_PF_aRect indicating the title area of the control.	
horiz_off	horiz_offsA horizontal offset from the left side of the title area in which to draw into the title.	

PF_EventUnion

The PF_EventUnion in PF_EventExtra is a union of the four following structures.

49.1 Click

A mouse click or drag occurred within the custom UI's area.

49.1.1 PF_DoClickEventInfo

Member	Purpose	
when	The (OS-level) time at which the click occurred.	
screen_poi	screen_poinWhere, in screen coordinates, the click occurred. For Custom Comp UI, these coordinates can be	
	converted to composition coordinates using the <i>UI Callbacks</i> . See the CCU sample project for an	
	example.	
num_clicks	The number of clicks that occurred.	
modifiers	Which modifier keys (if any) were held down during click.	
continue_reArcarray of 4 A_intptr_t the plug-in can use to store information during a click-drag-drag		
	sequence.	
send_drag	Set this flag to TRUE to indicate continued dragging. The next click event will then effectively be	
	a drag event.	
last_time	Set when the drag event ends (the user has released the mouse button).	

49.2 Draw

After Effects needs your custom UI to refresh.

Note: when handling draw requests, use the image dimensions provided in *PF_InData* (rather that the dimensions of your input layer, as you would during *PF_Cmd_RENDER*).

49.2.1 PF_DrawEventInfo

Mem-	Purpose
ber	
update_	Athetrectangle in which to draw, in the context window's coordinate system. These coordinates can be
	converted to different coordinate systems using the <i>UI Callbacks</i> . See the CCU sample project for an
	example.
depth	Pixel depth of the drawing context.

49.3 Keydown

The user pressed a key, and the effect's UI is active.

Use the macros in AE_EffectUI.h to access and manipulate the key codes received.

Member	Purpose
when	Time at which the click occurred.
screen_point	Screen coordinate of the mouse pointer when the key was pressed. For Custom Comp UI, these coordinates can be converted to composition coordinates using the <i>UI Callbacks</i> . See the CCU sample project for an example.
lana anda	ample.
key_code	Either a character code (for printable characters, we use the unshifted upper case version; A not a, 7 not &), or a
	control code:
	PF_ControlCode_Unknown
	• PF_ControlCode_Space
	• PF_ControlCode_Backspace
	• PF_ControlCode_Tab
	• PF_ControlCode_Return
	• PF_ControlCode_Enter
	• PF_ControlCode_Escape
	• PF_ControlCode_F1
	• PF_ControlCode_F24
	PF_ControlCode_PrintScreen
	PF_ControlCode_ScrollLock PF_ControlCode_Page
	• PF_ControlCode_Pause
	• PF_ControlCode_Insert
	PF_ControlCode_Delete PF_ControlCode_Home
	PF_ControlCode_HomePF_ControlCode_End
	• PF_ControlCode_PageUp
	• PF_ControlCode_PageDown
	• PF_ControlCode_Help
	• PF_ControlCode_Clear
	• PF_ControlCode_Left
	• PF_ControlCode_Right
	• PF_ControlCode_Up
	• PF_ControlCode_Down
	• PF_ControlCode_NumLock
	• PF_ControlCode_Command
	• PF_ControlCode_Option
	• PF_ControlCode_Alt =
	PF_ControlCode_Option
	• PF_ControlCode_Control
	• PF_ControlCode_Shift
	• PF_ControlCode_CapsLock
	PF_ControlCode_ContextMenu
modifiers	Which (if any) modifier keys were down during the key
	press.
	• PF_Mod_NONE
	• PF_Mod_CMD_CTRL_KEY (cmd on Mac, ctrl on Windows)
	• PF_Mod_SHIFT_KEY
	• PF_Mod_CAPS_LOCK_KEY
	• PF_Mod_OPT_ALT_KEY (option on Mac, alt on
	Windows)
	• PF_Mod_MAC_CONTROL_KEY
19.3. Keydown	179

49.4 AdjustCursor

The cursor has moved onto (but not off of) the effect's custom UI, to allow the effect to change the cursor.

49.4.1 PF_AdjustCursorEventInfo

Mem-	Purpose		
ber			
scree	Screentcoordinate of the mouse pointer. For Custom Comp UI, these coordinates can be converted to		
	composition coordinates using the UI Callbacks. See the CCU sample project for an example.		
modifi	difield bat, if any, modifier keys were held down when the message was sent.		
set_cı	cussethis to your desired cursor, or PF_Cursor_CUSTOM if you have set the cursor yourself using OS-		
	specific calls. See AE_EffectUI.h for a complete enumeration of built-in cursors. If you don't want to		
	override the cursor, set this to PF_Cursor_NONE, or simply ignore this message.		

49.5 Arbitrary Parameters Event

After Effects needs your plug-in to manage it's arbitrary data parameter(s).

Though arbitrary data types are not required for custom UI support, $PF_ArbParamsExtra$ follows the EventInfo model.

49.5.1 PF_ArbParamsExtra

Member	Purpose
which_function	A PF_FunctionSelector indicating which func-
	tion is called
id	Used by After Effects; will match the ID assigned to the
	arbitrary data type during <i>PF_Cmd_PARAM_SETUP</i> .
padding	Used for byte-alignment
	(One of these will be passed; see Arbitrary Data Param-
u {	eters)
new_func_params	
dispose_func_params	
copy_func_params	
flat_size_func_params	
flatten_func_params	
unflatten_func_params	
interp_func_params	
compare_func_params	
<pre>print_size_func_params</pre>	
print_func_params	
scan_func_params	
}	

Custom UI & Drawbot

Custom UI uses a composited drawing model using Drawbot. The Drawbot suites can be used for:

- 1. Basic 2D path drawing: Lines, Rect, Arc, Bezier
- 2. Stroking/Filling/Shading paths
- 3. Image drawing: Compositing an ARGB/BGRA buffer onto the surface
- 4. Pushing/popping surface state
- 5. Text drawing, if supplier supports it (clients should first check if text drawing is supported before actual drawing)

Drawing may only occur during PF_Event_DRAW (and not during PF_Event_DRAG or PF_Event_DO_CLICK).

To use Drawbot, first get the drawing reference by passing in PF_Context to a new suite call PF_GetDrawingReference.

If a non-NULL drawing reference is returned, use it to get the supplier and surface references from *DRAW-BOT_DrawbotSuite*.

The Drawbot suites include DRAWBOT_DrawbotSuite, DRAWBOT_SupplierSuite, DRAWBOT SurfaceSuite, DRAWBOT PathSuite.

50.1 Make Your Custom UI Look Not So "Custom"

Use the new PF_EffectCustomUIOverlayThemeSuite to match the host application UI. Your users will thank you.

50.2 Redrawing

In order to redraw a specific area of a pane, we recommend the following:

- 1) Call PF_InvalidateRect (from *PF_AppSuite*) from the effect. This will cause a lazy display redraw, and will update at the next available idle moment. This rect is in coordinates related to the associated pane. Using a NULL rect will update the entire pane.
- 2) Set the *event outflag* to PF_EO_UPDATE_NOW, which will cause an immediate draw event for the specified pane when the current event returns.

If an effect needs to update more than one window at a time, it should set PF_OutFlag_REFRESH_UI (from *PF_OutFlags*), which will cause a redraw of the entire ECW, comp, and layer windows.

50.3 HiDPI and Retina Display Support

To support HiDPI and Retina Displays, you can use offscreen images that are twice the size, and then use the Transform function from *Drawbot_SurfaceSuite* to scale the image down in half before drawing it.

50.4 PF_EffectCustomUlSuite

Enables an effect to get the drawing reference. This is the first call needed to use Drawbot.

50.4.1 PF_EffectCustomUlSuite1

Function	Purpose
PF_GetDrawingReference	Get the drawing reference.
	<pre>PF_GetDrawingReference(const PF_ContextH effect_contextH, DRAWBOT_DrawRef *referenceP0);</pre>

50.5 Drawbot_DrawbotSuite

Using the Drawbot reference, get the supplier and surface references.

50.5.1 Drawbot_DrawbotSuite1

Function	Purpose
GetSupplier	Get the supplier reference.
	Needed to use Drawbot_SupplierSuite.
	GetSupplier(
	DRAWBOT_DrawRef in_drawbot_ref,
	<pre>DRAWBOT_SupplierRef *out_supplierP);</pre>
GetSurface	Get the surface reference.
	Needed to use Drawbot_SurfaceSuite.
	GetSurface(
	DRAWBOT_DrawRef in_drawbot_ref,
	<pre>DRAWBOT_SurfaceRef *out_surfaceP);</pre>

50.6 Drawbot_SupplierSuite

Calls to create and release drawing tools, get default settings, and query drawing capabilities.

• kDRAWBOT PixelLavout 32ARGB Straight.

50.6.1 Drawbot_SupplierSuite1

Function	Purpose
NewPen	Create a new pen. Release this using
	ReleaseObject from Drawbot_SupplierSuite.
	NewPen (
	DRAWBOT_SupplierRef in_supplier_
	⇔ref,
	const DRAWBOT_ColorRGBA *in_colorP,
	float in_size,
	DRAWBOT_PenRef *out_penP);
NewBrush	Create a new brush. Release this using
	ReleaseObject from Drawbot_SupplierSuite.
	NewBrush(
	DRAWBOT_SupplierRef in_supplier_
	⇔ref,
	const DRAWBOT_ColorRGBA *in_colorP,
	DRAWBOT_BrushRef *out_brushP);
SupportsText	Check if current supplier supports text.
	SupportsText(
	DRAWBOT_SupplierRef in_supplier_ref,
	DRAWBOT_Boolean *out_supports_
	<pre>→textB);</pre>
GetDefaultFontSize	Get the default font size.
	GetDefaultFontSize(
	DRAWBOT_SupplierRef in_supplier_ref,
	<pre>float</pre>
NewDefaultFont	Create a new font with default settings.
NewDelaultront	You can pass the default font size from
	GetDefaultFontSize.
	Release this using ReleaseObject from Draw-
	bot_SupplierSuite.
	NewDefaultFont(
	DRAWBOT_SupplierRef in_supplier_ref,
	float in_font_sizeF,
	<pre>DRAWBOT_FontRef *out_fontP);</pre>
NewImageFromBuffer	Create a new image from buffer passed to in_dataP.
Newimageriombarrer	Release this using ReleaseObject from <i>Draw</i> -
	bot_SupplierSuite.
	NewImageFromBuffer(
	DRAWBOT_SupplierRef in_supplier_ref,
	int in_width,
	int in_height,
	<pre>int</pre>
	DRAWBOT_PixelLayout in_pl,
	const void *in_dataP,
	DRAWBOT_ImageRef *out_imageP);
	DRAWBOT_PixelLayout can be one of the following:
	<pre>ing:</pre>
	• kDRAWBOT_FixelLayout_24RGB,
TO C. Duranda at One Handada	• kDRAWROT PivelLavout 32RCB
50.6. Drawbot_SupplierSuite	• ARGB (A is ignored),
	• kDRAWBOT_PixelLayout_32BGR,
	• BGRA (A is ignored),
	• kDDAWBOT Divellayout 32ABCB Straig

50.7 Drawbot_SurfaceSuite

Calls to draw on the surface, and to query and set drawing settings.

50.7.1 Drawbot_SurfaceSuite1

Function	Purpose
PushStateStack	Push the current surface state onto the stack. It should
	be popped to retrieve old state. It is required to restore state if you are going to clip or transform a surface or change the interpolation or anti-aliasing policy.
	<pre>PushStateStack(DRAWBOT_SurfaceRef in_surface_ref);</pre>
PopStateStack	Pop the last pushed surface state off the stack.
	PopStateStack(DRAWBOT_SurfaceRef in_surface_ref);
PaintRect	Paint a rectangle with a color on the surface.
	PaintRect(DRAWBOT_SurfaceRef in_surface_ →ref, const DRAWBOT_ColorRGBA *in_colorP, const DRAWBOT_RectF32 *in_rectPR);
FillPath	Fill a path using a brush and fill type.
	FillPath(DRAWBOT_SurfaceRef in_surface_ref, DRAWBOT_BrushRef in_brush_ref, DRAWBOT_PathRef in_path_ref, DRAWBOT_FillType in_fill_type); DRAWBOT_FillType is one of the following: • kDRAWBOT_FillType_EvenOdd, • kDRAWBOT_FillType_Winding
StrokePath	Stroke a path using a pen.
	StrokePath(DRAWBOT_SurfaceRef in_surface_ref, DRAWBOT_PenRef in_pen_ref, DRAWBOT_PathRef in_path_ref);
Clip	Clip the surface.
	Clip(DRAWBOT_SurfaceRef in_surface_ref, DRAWBOT_SupplierRef in_supplier_ref, const DRAWBOT_Rect32 *in_rectPR);
GetClipBounds	Get clip bounds.
	GetClipBounds(DRAWBOT_SurfaceRef in_surface_ref, DRAWBOT_Rect32 *out_rectPR);
IsWithinClipBounds	Checks whether a rect is within the clip bounds.
	<pre>IsWithinClipBounds(DRAWBOT_SurfaceRef in_surface_ref, const DRAWBOT_Rect32 *in_rectPR, DRAWBOT_Boolean *out_withinPB);</pre>
Transform	Transform the last surface state.
	Transform(
188	DRAWBOT_Su Chapter 50. Custom UI & Drawbot → ref, const DRAWBOT_MatrixF32 *in_matrixP);
DrawString	Draw a string

50.8 Drawbot_PathSuite

Calls to draw paths.

50.8.1 Drawbot_PathSuite1

Function	Purpose
MoveTo	Move to a point.
	MoveTo(DRAWBOT_PathRef in_path_ref, float in_x, float in_y);
LineTo	Add a line to the path.
	LineTo(DRAWBOT_PathRef in_path_ref, float in_x, float in_y);
BezierTo	Add a cubic bezier to the path.
	<pre>BezierTo(DRAWBOT_PathRef</pre>
AddRect	Add a rect to the path.
	AddRect(DRAWBOT_PathRef in_path_ref, const DRAWBOT_RectF32 *in_rectPR);
AddArc	Add a arc to the path. Zero start degrees == 3 o'clock. Sweep is clockwise. Units for angle are in degrees.
	AddArc(DRAWBOT_PathRef in_path_ref, const DRAWBOT_PointF32 *in_centerP, float in_radius, float in_start_angle, float in_sweep);
Close	Close the path.
	Close(DRAWBOT_PathRef in_path_ref);

50.9 PF_EffectCustomUIOverlayThemeSuite

This suite should be used for stroking and filling paths and vertices on the Composition and Layer Windows. After Effects is using this suite internally, and we have made it available to make custom UI look consistent across effects. The foreground/shadow colors are computed based on the app brightness level so that custom UI is always visible regardless of the application's Brightness setting in the Preferences.

50.9.1 PF_EffectCustomUIOverlayThemeSuite1

Function	Purpose
PF_GetPreferredForegroundColor	Get the preferred foreground color.
	PF_GetPreferredForegroundColor(
	DRAWBOT_ColorRGBA *foreground_colorP);
PF_GetPreferredShadowColor	Get the preferred shadow color.
	PF_GetPreferredShadowColor(
	DRAWBOT_ColorRGBA *shadow_colorP);
PF_GetPreferredStrokeWidth	Get the preferred foreground & shadow stroke width.
	PF_GetPreferredStrokeWidth(
	<pre>float *stroke_widthPF);</pre>
PF_GetPreferredVertexSize	Get the preferred vertex size.
	PF_GetPreferredVertexSize(
	<pre>float *vertex_sizePF);</pre>
PF_GetPreferredShadowOffset	Get the preferred shadow offset.
	PF_GetPreferredShadowOffset(
	A_LPoint *shadow_offsetP);
PF_StrokePath	Stroke the path with the overlay theme foreground color.
	Optionally draw the shadow using the overlay theme shadow color. Uses overlay theme stroke width for
	stroking foreground and shadow strokes.
	PF_StrokePath(
	<pre>const DRAWBOT_DrawRef drawbot_ref,</pre>
	<pre>const DRAWBOT_PathRef path_ref PF_Boolean draw_shadowB);</pre>
DE Eddinoth	
PF_FillPath	Fills the path with overlay theme foreground color. Optionally draw the shadow using the overlay theme
	shadow color.
	PF_FillPath(
	<pre>const DRAWBOT_DrawRef drawbot_ref, const DRAWBOT_PathRef path_ref</pre>
	PF_Boolean draw_shadowB);
PF_FillVertex	Fills a square vertex around the center point using the
_	overlay theme foreground color and vertex size.
	PF_FillVertex(
	<pre>const DRAWBOT_DrawRef drawbot_ref,</pre>
	<pre>const A_FloatPoint *center_pointP PF_Boolean draw_shadowB);</pre>
	TI_BOOTCAII araw_SiladowB),

UI Callbacks

After Effects provides callbacks for transposing between coordinate systems, and obtaining OS-specific information about drawing contexts, without guesswork or asking the OS directly. Use these callbacks! Pointers to these callbacks are provided in PF_EventCallbacks. Use the macros in AE_EffectUI.h and AE_EffectCB.h to access these routines.

It is possible to build a functioning plug-in which utilizes a custom UI without implementing the coordinate system transposition callbacks. However, the moment a user zooms into the layer panel or rotates a layer, your plug-in will behave badly. We added these macros and callbacks so that custom user interfaces could be easily integrated into the After Effects UI, without inflicting user interface overhead on developers. Again, please use them!

These macros default the refcon and context handle for simplicity. The refcon assumes you have a local variable named "extra". The default context is the current context. These default parameters are defined in the PF_EventCallbacks structure (in AE_EffectUI.h). You can override the defaults by accessing the callbacks through the PF_EventExtra structure. We don't recommend (or support) modification of the macros in the header file. Don't do it!

Function	Purpose
layer_to_comp	Transforms layer panel coordinates to the composition
	panel coordinates.
	PF_Err layer_to_comp (
	<pre>void *refcon,</pre>
	PF_ContextH context,
	A_long curr_time,
	A_long time_scale, PF_FixedPoint *pt);
comp_to_layer	Transforms composition panel coordinates to the layer panel coordinates.
	PF_Err comp_to_layer (
	<pre>void *refcon,</pre>
	PF_ContextH context,
	A_long curr_time,
	A_long time_scale, PF_FixedPoint *pt);
	rr_rixedroinc *pc),
get_comp2layer_xform	Returns the matrix used to convert from the composition
	panel to the layer panel. If *exists returns FALSE,
	the matrix cannot be computed because the layer scales
	to zero.
	<pre>PF_Err get_comp2layer_xform (</pre>
	<pre>void *refcon,</pre>
	PF_ContextH context,
	A_long curr_time,
	<pre>long time_scale, long *exists,</pre>
	PF_FloatMatrix *comp2layer);
	Det made de la formación de la
get_layer2comp_xform	Returns the transformation matrix used to convert from
	the layer panel to the composition panel. This always exists.
	<pre>PF_Err get_layer2comp_xform (void</pre>
	PF_ContextH context,
	A_long curr_time,
	A_long time_scale,
	<pre>PF_FloatMatrix *layer2comp);</pre>
source_to_frame	Transforms the source coordinates in the current context
Source_to_frame	to screen coordinates. Screen (frame) coordinates are
	affected by the current zoom level.
	·
	<pre>PF_Err source_to_frame(void *refcon,</pre>
	PF ContextH context,
	PF_FixedPoint *pt);
<u></u>	Transformed the concerns and instant identifically
frame_to_source	Transforms the screen coordinates identified by *pt to the source coordinates of the current context.
	PF_Err frame_to_source(
	void *refcon,
	<pre>PF_ContextH context, PF_FixedPoint *pt);</pre>
PF_GET_PLATFORM_DATA	Retrieves platform-specific data. For plug- ins loaded with localized resource files,
194	PF_PlatData_RES_FILE_PATH Will Callback
	to the external file, not the plug-in file. Use
	PF_PlatData_EXE_FILE_PATH if you want

the path of your plug-in.

Tips & Tricks

52.1 UI Performance

Experiment with PF_EO_ALWAYS_UPDATE and PF_EO_NEVER_UPDATE from *PF_EventExtra*, to find a happy medium between responsiveness and accuracy.

On macOS, the foreground and background colors are not set to white and black when custom UI draw events are sent.

This is by design; you don't have to change the background color when you're drawing directly into our context.

52.2 How Deep Are My Pixels?

There is no way to determine the bit depth of the layer(s) being processed during events.

However, you can cache the last-known pixel depth in your sequence data.

Better still, you can have your fixed and float slider parameters rely on the PF_ValueDisplayFlags in their parameter definitions; if you use this, it will have your parameters' UI respond to the user's preferences for pixel display values.

You can also check the depth of your input world during PF_Cmd_RENDER.

52.3 Arbitrary Data

An arbitrary data parameter is an excellent way to manage your custom UI.

Store state, preference, and last-item-used information in an arb, and you'll always be able to recover it.

After Effects manages parameters with a much richer message stream than custom UIs.

52.4 Custom UI Implementation for Color Sampling, Using Keyframes

A plug-in may want to get a color from a layer within a composition. The user would use the eyedropper associated with a color parameter, or the plug-in's custom composition panel UI, to select the point.

During the click event, the plug-in converts the coordinates of the click into layer space, and stores that information in sequence data. It then forces a re-render, during which it has access to the color of the layer point corresponding to the stored coordinates.

The plug-in stores the color value in sequence data, and cancels the render, requesting a redraw of the affected parameter(s).

Finally, during the draw, the plug-in adds appropriate keyframes to its color parameter stream using the AEGP_KeyframeSuite.

Yes, this means the effect needs to Cheating Effect Usage of AEGP Suites and use the AEGP API.

Audio

After Effects can process audio encoded at up to 96Khz, floating point (24-bit) resolution, mono or stereo.

We provide high quality resampling.

PF_InData and PF_OutData both contain information specific to audio handling.

While audio isn't the focus of After Effects' feature set, it is an important component of compositing and previsualization workflows.

Also, several engineers on our team are audio fanatics, and ensure that our audio effects (and the whole audio pipeline) are of the highest quality.

198 Chapter 53. Audio

Global Outflags

 ${\tt PF_OutFlag_I_USE_AUDIO}\ is\ for\ visual\ effects\ that\ check\ out\ audio\ data,\ but\ don't\ modify\ it.$

$\mathsf{CHAPTER}\, 55$

Audio Data Structures

The following data types are used by After Effects to describe audio data.

Structure	Description
PF_SoundForm	halindicates whether the audio is in unsigned pulse code modulation (PCM), signed PCM, or float-
	ing point format.
PF_SoundSamp	Sanniples are in 1, 2, or 4 byte format.
PF_SoundChar	raledisates whether the audio is mono or stereo.
PF_SoundForm	accontains the sampling rate, number of channels, sample size, and format of the audio to which
	it refers.
PF_SoundWorl	dUse PF_SoundWorlds to represent audio. In addition to a PF_SoundFormatInfo, they
	contain the length of the audio, and a pointer to the actual audio data.

 $\label{lem:pf_sound} $$\operatorname{PF_SoundSampleSize},$ and $\operatorname{PF_SoundChannels}$ are all contained within a $\operatorname{PF_SoundFormatInfo}.$$

PF_SoundWorlds contain a PF_SoundFormatInfo, and further instance-specific information.

Audio-Specific Float Slider Variables

PF_Param_FLOAT_SLIDERs contain several parameters not found in other sliders; flags, phase, and curve tolerance.

56.1 Flags

The only flag available is PF_FSliderFlag_WANT_PHASE.

This registers the effect to receive updated phase information from After Effects during audio rendering.

To understand what this flag does, turn it off and check your output.

56.2 Phase

This is where the requested phase value is stored.

56.3 Curve Tolerance

Curve tolerance is used by After Effects to subdivide the audio effects' time-variant parameters. Set this to zero for default behavior (or for non-audio FLOAT_SLIDER parameters).

56.4 What's Zero, Really?

When amplitude is zero, After Effects is at -192db.

Accessing Audio Data

Use PF_CHECKOUT_LAYER_AUDIO from Interaction Callbacks to retrieve an audio layer.

This layer is opaque; use PF_GET_AUDIO_DATA to access specific details about that audio.

As with pixel data, it's important that you check in the audio as soon as possible.

If your effect requires as input a time span different from the output time span, update the startsampl and endsampl field in PF_OutData during PF_Cmd_AUDIO_SETUP from Frame Selectors.

57.1 Extending Audio Clips

You cannot extend the length of an audio clip through the API.

However, it is a relatively simple matter for the user to extend the length of the clip before applying your effect. Apply time remapping to the layer and simply extend the out point.

If you're adding a delay effect to a sounds clip, you'd want to allow it time to fade away instead of truncating the sound at the original end point.

Document the steps users should take when applying your effect.

Audio Considerations

The After Effects audio API supports sampling rates up to 96Khz, in as many formats as possible.

In the same way that plug-ins' pixel manipulation functions should remain "resolution independent", audio plug-ins should be sample rate- and bit depth-independent.

Your plug-in can't know anything about the final output format of the audio in question; it might get stretched, normalized, truncated, or phase-inverted between the application of your plug-in and the final output.

Audio filters encounter different issues than do image filters.

Investigate the SDK sample for one possible implementation of audio rendering.

AEGPs

The After Effects General Plug-in (AEGP) API is powerful and broad, offering functionality beyond what is available to effect plug-ins.

To users, AEGPs appear to be part of After Effects.

They can add, intercept, and trigger menu commands, access the keyframe database, and register functions as part of After Effects' internal messaging.

AEGPs can add and remove items to projects and compositions, add and remove filters and keyframes.

Once its command is triggered, AEGPs use the numerous PICA function suites (described in this section) to work with every After Effects item.

AEGPs can publish function suites for plug-ins, manipulate all project elements, change interpretations, replace files and determine which external files are used to render a project.

There are several specialized types of AEGP; Keyframers, Artisans, and I/O modules (AEIOs). They are all still AEGPs, but have access to specialized messaging streams, for which they register with After Effects.

210 Chapter 59. AEGPs

What's New?

For what's new in CC releases, see What's New.

60.1 What's New In CS6?

3D is a major theme of AE CS6. A new AEGP_LayerFlag_ENVIRONMENT_LAYER has been added. Many new *layer streams* were added.

Additionally, AEGP_LayerStream_SPECULAR_COEFF was renamed to AEGP_LayerStream_SPECULAR_INTENSITY, AEGP_LayerStream_SHININESS_COEFF was renamed to AEGP_LayerStream_SPECULAR_SHININESS, and AEGP_LayerStream_METAL_COEFF was renamed to just AEGP_LayerStream_METAL.

A new suite, *AEGP_RenderQueueMonitorSuite1*, provides all the info a render queue manager needs to figure out what is happening at any point in a render.

Mask Suite is now at version 6, and provides functions to get and set the mask feather falloff type. *Mask Outline Suite* is now at version 3, and provides access to get and set mask outline feather information.

Composition Suite is now at version 9. AEGP_CreateTextLayerInComp and AEGP_CreateBoxTextLayerInComp now have a new parameter, select_new_layerB.

Render Suite is now at version 3, adding a new function to get the GUID for a render receipt.

Finally, we have added two new read-only *Dynamic Stream Suite* flags: AEGP_DynStreamFlag_SHOWN_WHEN_EMPTY and AEGP_DynStreamFlag_SKIP_REVEAL_WHEN_UNHIDDEN.

Overview

AEGPs use Plug-In Component Architecture (PICA) function suites to access all functionality.

They may also publish their own function suites, for use by effect plug-ins (since plug-in load order varies, AEGPs can't depend on suites not provided by After Effects).

AEGPs can also request a suite and, if it's not present, provide replacement functionality themselves.

61.1 AEGP Communication With After Effects

For effect plug-ins, all communication with After Effects occurs through a single entry point function. This is not the case with AEGPs.

While After Effects *does* call the entry point function designated in the AEGP's PiPL (which is still required), all subsequent communication between After Effects and AEGPs is handled by the hook functions the AEGP registers.

This registration must be performed from within the plug-in's entry function, using the *Register Suite*.

61.2 Different Tasks, Same API

AEGPs work in the same manner, regardless of specialization.

They can be simple, just adding one menu item to trigger an external application, or complex like Artisans.

While any plug-in can access any function suite, only plug-ins of the appropriate type will have access to all the required parameters.

Only Artisans will have render contexts, and only AEIO plug-ins will receive input and output specifications; messaging is dependent upon which hook functions are registered.

Data Types

Whenever possible, After Effects presents plug-ins with opaque data types, and provides accessor functions for manipulating them. For example, video frames are represented using the opaque AEGP_WorldH. While in some cases it might be more efficient to simply modify the underlying structure, by maintaining the opaqueness of the data types we allow for changes to our implementation without making you recompile (and redistribute) your plug-ins.

62.1 AEGP API Data Types

Туре	Describes	Manage Using
AEGP_Mer	HElmist 1steructure contains more than just the referenced memory. So it	AEGP Memory
	should not be dereferenced directly. Use AEGP_LockMemHandle in the	Suite
	AEGP Memory Suite to get a pointer to the memory referenced by the	
	AEGP_MemHandle. And of course, unlock it when you're done.	
AEGP_Pro	jEhret Eurrent After Effects project. Projects are a set of elements arranged hi-	AEGP Project Suite
	erarchically in a tree to preserve semantic relationships. Interior nodes of the	
	tree are folders. As of CS6, there will only ever be one open project.	
AEGP Ite	mAn abstraction describing any element of a project, including folders. An item	AEGP Item Suite
_	is anything that can be selected. Since multiple object types can be selected,	
	we treat them as AEGP_ItemHs until more specificity is required.	
AEGP Co	LA setion selected items.	AEGP Collection
71E01 _00.	14 Octorbane tee rems.	Suite
AECD Cor	PA composition is a sequence of renderable items that, together, produce output.	AEGP Composition
AEGP_COI	A composition exists over a time interval. Multiple compositions can exist	Suite Suite
	within one project.	Suite
700 D		AEGP Footage
AEGP_FO	tAn item that can be rendered. Folders and compositions are the only items that	U
7.7.5-	are not footage.	Suite
AEGP_La	eAth element of a composition. Layers are rendered in sequence, which al-	AEGP Layer Suite
	lows for occlusions. Solids, text, paint, cameras, lights, images, and image	
	sequences are all represented as layers.	
	Layers may be defined over sub-intervals of the composition's time interval.	
	1.A) Hrame of pixels.	AEGP World Suite
AEGP_Ef	eAn Reffect applied to a layer. An effect is a function that takes as its argument	AEGP Effect Suite
	a layer (and possibly other parameters) and returns an altered version of the	
	layer for rendering.	
AEGP St	eAmp partimeter stream attached to a layer, in a composition. See the descrip-	AEGP Stream Suite,
_	tion of AEGP_GetNewLayerStream from AEGP_StreamSuite5 for a full	AEGP Dynamic
	list of stream types.	Stream Suite AEGP
	not of stream types.	Keyframe Suite
AEGP Mas	kAemfask applied to a layer. An AEGP_MaskRefH is used to access details	AEGP Mask Suite
111101 _1101	about the mask stream, not the specific points which constitute the mask. A	TIEGT MUSIC SUITE
	mask is a rasterized path (sequence of vertices) that partitions a layer into two	
	pieces, allowing each to be rendered differently.	
ADOD M-		AEGP Mask Outline
ALGP_Ma:	kThet specific applints which constitute the mask. The points in a mask outline	
	are ordered, and the mask need not be closed.	Suite
AEGP_Te	tRepresents the actual text associated with a text layer.	AEGP Text Docu-
		ment Suite
AEGP_Tex	tAutherienees to all the paths that make up the outlines of a given text layer.	AEGP Text Layer
		Suite
	kEhet/data associated with a given timeline marker.	AEGP Marker Suite
AEGP_Pe	sA ś bend of data containing the current preferences.	AEGP Persistent
		Data Suite
AEGP_Rei	dEheogettings associated with a render request.	AEGP Render Op-
	·	tions Suite
AEGP Lar	eFlicesetting@associated with a layer render request.	AEGP Layer Ren-
5	4	der Options Suite
AEGP Fr	mA Reference to a rendered frame.	AEGP Render Suite
	tAmitemin the render queue.	AEGP Render
ALGY_KQ.	Loguinemin die tender quede.	
		Queue Suite AEGP
		Render Queue Item
		Suite
メガcDΔFG	PAPIDATA TYPESE, attached to a specific AEGP_RQItemRef in the render	AEGP Output Mc 2 /1
#11 G L		1 0 4
	queue.	ule Suite
	n Ellieaduadio settings used for a given layer.	AEGP Sound Data

62.2 Nasty, Brutish, and Short

Information about layers, streams, and many other items doesn't survive long; it's often invalidated by user activity.

Anything that modifies the quantity (not quality) of items will invalidate references to those items; adding a keyframe to a stream invalidates references to that stream, but forcing a layer to be rendered doesn't invalidate references to it. Do not cache layer pixels.

Caching references between calls to a specific hook function within your plug-in is not recommended; acquire information when you need it, and forget (release) it as soon as possible.

62.3 Were You Just Going To Leave That Data Lying Around?

When you ask After Effects to populate and return handles to data structures, it's important that you clean up after yourself. For the following data types, you must call the appropriate disposal routines.

62.4 Data Types Requiring Disposal

Data Type	Disposal function
AEGP_Collection	2HEGP_DisposeCollection, from AEGP_CollectionSuite2
AEGP_FootageH	AEGP_DisposeFootage, from AEGP_FootageSuite5
AEGP_WorldH	AEGP_Dispose, from AEGP_WorldSuite3
	Or AEGP_DisposeTexture, from AEGP_CanvasSuite8, if layer texture created using
	AEGP_RenderTexture)
AEGP_EffectRef	AEGP_DisposeEffect, from AEGP_EffectSuite4
AEGP_MaskRefH	AEGP_DisposeMask, from AEGP_MaskSuite6
AEGP_RenderOpt:	CATESIP_Dispose, from AEGP_RenderQueueMonitorSuite1
AEGP_LayerRende	rAMSPi_drisspose, from AEGP_LayerRenderOptionsSuite1
AEGP_RenderRece	iAptGP_DisposeRenderReceipt, from AEGP_CanvasSuite8

Implementation

Because the functionality available through the AEGP API is so vast, and the integration with After Effects so complete, a good deal of design work is necessary to ensure that your plug-in behaves appropriately in all situations.

AEGPs interact with After Effects through PICA function suites.

AEGPs are not loaded in a specific order.

Check the version of the AEGP API (from within your AEGP's entry point function) to confirm whether a given suite will be available.

AEGPs may also use any effect API suite function which doesn't require a PF_ProgPtr (obtained by effects from PF_InData).

63.1 Entry Point

```
A_Err AEGP_PluginInitFuncPrototype(
struct SPBasicSuite *pica_basicP,
A_long major_versionL,
A_long minor_versionL,
AEGP_PluginID aegp_plugin_id,
AEGP_GlobalRefcon *global_refconP)
```

The plug-in's entry point, exported in the *PiPL Resources*, is called just once during launch; all other calls to the AEGP go to the functions it's registered.

This is very different from the effect plug-in model, where all communication comes through the same entry point.

Because plug-in load order may vary, it's never a good idea to acquire suites not provided by After Effects during your entry point function. Rather, wait until the appropriate hook function(s).

The AEGP API Versions can help distinguish between different versions of After Effects, in case the AEGP needs to behave differently or handle different behavior.

Those other functions are registered as callback hooks. An AEGP that adds menu items must register an Update-MenuHook function (with a function signature as described in AE_GeneralPlug.h) which After Effects can call to determine whether or not to enable those items. Similarly, plug-ins which process commands register a Command-Hook (one for all commands).

63.2 Specialization

AEGP RegisterSuite.

AEIOs and Artisans must register with After Effects in order to receive the messaging streams on which they depend. Like everything else in the AEGP API, this is done through a function suite; in this case, the aptly-named

63.3 Example: Adding A Menu Item

During your entry point function, use AEGP_GetUniqueCommand() from Command Suite to obtain a command ID from After Effects, for use with AEGP_InsertMenuCommand. Use a different ID for each menu item you add.

Using AEGP_RegisterSuite's AEGP_RegisterCommandHook(), tell After Effects which function to call when your menu item(s) are selected. The function you register using AEGP_RegisterUpdateMenuHook() enables and disabling your menu item(s). Your menu item(s) will be permanently disabled unless you register a menu updating function.

No matter how many menu items you add, you register only one CommandHook. When called, determine which menu item was chosen (based on the command ID), use AEGP PICA suite functions to determine the current state of the project, and act accordingly. For example, keyframing plug-ins may want to disable their menu items unless a (keyframe-able) parameter stream is part of the current selection.

63.4 Private Data

Unlike effects, AEGPs are never unloaded during an After Effects session. Still, that doesn't mean that relying on static and global variables is a good idea.

All hook functions are passed a plugin_refconPV for storage information specific to that function. Many AEGP Suite functions take the aegp_plugin_id as a parameter; store it in the global_refconPV you are passed, either in a structure you allocate or just the ID itself.

Where possible, use these refcons to store information, not statics and global variables. This becomes especially important when dealing with multi-threading issues.

Use global_refconPV for your globals (like your aegp_plugin_id) and refcon for hook-function-specific storage.

A potential "multiple instances of After Effects" gotcha; when a second, command-line instance of After Effects is launched, all of an AEGP's handles are duplicated. If this causes problems (and it may), provide code that attaches saved handles to specific instantiations of your plug-in.

63.5 Threading

AEGP supports no threading at all. Everything must be done from the main thread, either in response to a callback, or from the idle hook.

There is one call that is thread safe: AEGP_CauseIdleRoutinesToBeCalled().

But since SPBasicSuite itself is not thread safe, you'll need to stash off the function pointer in the main thread.

63.5. Threading 221

AEGP Suites

As mentioned earlier, AEGPs do everything through suites. The following suites are used by all types of AEGPs, and may be called from within any hook function (except for the RegisterSuite, which must be used from within the AEGP's entry point). Following is a description of each function in every suite, and, where appropriate details on using those functions.

Suite	Description
Memory Suite	Manage memory resources. Use this suite! Whenever memory-related errors are encountered, After Effe
Command Suite	Manage your AEGP's menu items. Used in conjunction with the Register Suite.
Register Suite	Used in conjunction with the Command Suite to add functions to menu commands. AEIOs and Artisans
Project Suite	Reads and modifies project data.
Item Suite	Manages items within a project or composition. Folders, Compositions, Solids, and Footage are all item
Collection Suite	Query which items are currently selected, and create your own selection sets. It's often a good UI move
Composition Suite	Manages (and creates) compositions in a project, and composition-specific items like solids.
Footage Suite	Manages footage.
Layer Suite	Provides information about the layers within a composition, and the relationship(s) between the source a
Effect Suite	Provides access to the effects applied to a layer. Use Stream suites to obtain effect keyframe information
Stream Suite	Used to access the values of a layer's keyframe properties.
Dynamic Stream Suite	Used to access the characteristics of dynamic streams associated with a layer.
Keyframe Suite	Used to access and manipulate all keyframe data.
Marker Suite	Used to manipulate markers. Use AEGP_GetNewCompMarkerStream() (in AEGP_CompSuite11)
Mask Suite	Provides access to retrieve information about a layer's masks.
Mask Outline Suite	Used in conjunction with Stream Suite, this suite provides detailed information about the path rendered
Text Document Suite	Used to access the actual text on a text layer.
Text Layer Suite	Used to access the paths that make up the outlines of a text layer.
Utility Suite	Supplies error message handling, AEGP version checking and access to After Effects' undo stack.
Persistent Data Suite	Query and manage all persistent data (i.e., the preferences file). AEGPs can also add their own data to the
Color Settings Suite	Obtain information on After Effects' current color management settings.
Render Suite	Get rendered frames (and audio samples) from within an AEGP.
World Suite	Allocate, dispose of, and query AEGP_Worlds. Also provides a way to convert a PF_EffectWorld in
Composite Suite	Exposes After Effects' compositing functionality, including transfer modes, track matting, and good old

Suite	Description
Sound Data Suite	Functions for managing and accessing sound data.
Render Queue Suite	Add and remove items from the render queue.
Render Queue Item Suite	Query and modify items in the render queue.
Render Options Suite	Query and manage all items exposed in a render queue item's options dialog.
Output Module Suite	Query and modify the output modules attached to items in the render queue.
PF Interface Suite	The functions in this suite, while technically part of the AEGP API, are for use by effects.
AEGP Iterate Suite	Gives AEGPs a way to have a function (which has the required signature) to be run on any or all availab
File Import Manager Suite	Registers AEGP file and project importers as part of After Effects' file handling.

64.1 Fail Gracefully

If a suite isn't present, make every attempt to fail gracefully. Show the user a message indicating the nature of the problem. Attempt to acquire and use an earlier version of the same suite.

Since AEGPs are so deeply integrated with After Effects, make sure that users know who or what is encountering a given problem.

Identify yourself! Provide support and/or help information to the user whenever possible.

64.2 Handling Handles

Use the AEGP Memory Suite to manage memory used by the AEGP. Whenever memory related errors are encountered, After Effects can report errors for you to find early on.

AEGP_MemHandle is a structure that contains more than just the referenced memory. So it should not be dereferenced directly. Use AEGP_LockMemHandle to get a pointer to the memory referenced by the AEGP_MemHandle.

And of course, unlock it when you're done.

64.2.1 AEGP_MemorySuite1

Function	Purpose
AEGP_NewMemHandle	Create a new memory handle. This memory is guaranteed to be 16-byte aligned. plugin_id is the ID passed in through the main Entry Point, or alternatively what you obtained from AEGP_RegisterWithAEGP() (from AEGP_UtilitySuite6). Use what Z to identify the memory you are asking for. After Effects uses the string to display any related error messages. AEGP_NewMemHandle(AEGP_PluginID *plugin_id, const A_char *whatZ, AEGP_MemSize size, AEGP_MemFlag flags, AEGP_MemHandle *memPH);
AEGP_FreeMemHandle	Release a handle you allocated using AEGP_NewMemHandle().
	AEGP_FreeMemHandle(AEGP_MemHandle memH);
AEGP_LockMemHandle	Locks the handle into memory (cannot be moved by OS). Use this function prior to using memory allocated by AEGP_NewMemHandle. Can be nested.
	AEGP_LockMemHandle(AEGP_MemHandle memH, void **ptr_to_ptr);
AEGP_UnlockMemHandle	Allows OS to move the referenced memory. Always balance lock calls with unlocks. AEGP_UnlockMemHandle(
	AEGP_MemHandle memH);
AEGP_GetMemHandleSize	Returns the allocated size of the handle. AEGP_GetMemHandleSize AEGP_MemHandle_ →memH, AEGP_MemSize *sizeP);
AEGP_ResizeMemHandle	Changes the allocated size of the handle.
	AEGP_ResizeMemHandle(const char *whatZ, AEGP_MemSize new_size, AEGP_MemHandle memH);
AEGP_SetMemReportingOn	If After Effects runs into problems with the memory handling, the error should be reported to the user. Make use of this during development! Only memory allocated and then leaked using this suite is reported using this call, so for example memory allocated using <i>PF_HandleSuite1</i> will not be reported. AEGP_SetMemReportingOn(A_Boolean turn_OnB);
AEGP_GetMemStats 2 26	Obtain information about the number of currently allocated handles and their total size. Only memory allocated using this suite is tracked and reported using this call, so for example memory allocated using the state of the size of t

cated using *PF HandleSuite1* will not be reported here.

64.3 Managing Menu Items

Command Suites allow you to create and handle any menu events.

To add your own menu commands, you must also use *Register Suite* to assign handlers to menu events.

64.3.1 AEGP_CommandSuite1

Function	Purpose
AEGP_GetUniqueCommand	Obtain a unique command identifier. Use the Register
	Suite to register a handler for the command.
	AEGP_GetUniqueCommand(
	AEGP_Command *unique_commandP);
	Note: On occasion After Effects will send command 0
	(zero), so don't use that as part of your command han-
	dling logic.
AEGP_InsertMenuCommand	Add a new menu command. Using nameZ = "-" will
	insert a separator. menu_ID can be:
	• AEGP_Menu_NONE
	• AEGP_Menu_APPLE
	• AEGP_Menu_FILE
	• AEGP_Menu_EDIT
	• AEGP_Menu_COMPOSITION
	• AEGP_Menu_LAYER
	• AEGP_Menu_EFFECT
	AEGP_Menu_WINDOW
	AEGP_Menu_FLOATERS AEGR_Menu_KE_AEGR_GET
	AEGP_Menu_KF_ASSISTAEGP_Menu_IMPORT
	• AEGP_Menu_SAVE_FRAME_AS
	• AEGP_Menu_PREFS
	• AEGP_Menu_EXPORT
	• AEGP_Menu_ANIMATION
	• AEGP_Menu_PURGE
	AEGP_Menu_NEW - Supported in CC and later
	Locations can be set to a specific location in the menu
	or can be one assigned by After Effects:
	• AEGP_MENU_INSERT_SORTED
	• AEGP_MENU_INSERT_AT_BOTTOM
	• AEGP_MENU_INSERT_AT_TOP
	For AEGP_Menu_WINDOW, the BOTTOM and TOP
	options haven't been supported since CS4 and will re-
	turn an error. We recommend SORTED.
	AEGP_InsertMenuCommand(
	AEGP_Command,
	<pre>const A_char *nameZ,</pre>
	AEGP_MenuID menu_id,
	A_long after_itemL);
AEGP_RemoveMenuCommand	Remove a menu command. If you were so motivated,
	you could remove ALL of the After Effects menu items.
	AEGP RemoveMenuCommand(
	AEGP_Command command);
AEGP_SetCommandName	Set menu name of a command.
	AEGP_SetCommandName(
	AEGP_Command command,
	<pre>const A_char *nameZ);</pre>
AEGP_EnableCommand	Enable a menu command.
_	AEGP_EnableCommand(
64.3. Managing Menu Items	AEGP_Command command); 229
	220
AEGP_DisableCommand	Disable a menu command.
	AEGP_DisableCommand(

64.4 Registering with After Effects

Register functions for After Effects' use.

64.4.1 AEGP_RegisterSuites5

Function	Purpose
AEGP_RegisterCommandHook	Register a hook (command handler) function with After
	Effects.
	If you are replacing a function which After Effects also
	handles, AEGP_HookPriority determines whether
	your plug-in gets it first.
	• AEGP_HP_BeforeAE
	• AEGP_HP_AfterAE
	For each menu item you add, ob-
	tain your own AEGP_Command using
	AEGP_GetUniqueCommand() (from
	AEGP_CommandSuite1) prior registering a single
	command_hook_func.
	Determine which command was sent within this hook
	function, and act accordingly.
	Currently, AEGP_HookPriority is ignored.
	AECD PagistarCommandilastr
	AEGP_RegisterCommandHook(AEGP_PluginID aegp_plugin_id,
	AEGP_HookPriority hook_priority,
	AEGP_Command command,
	AEGP_CommandHook command_hook_func
	<pre>void *refconPV);</pre>
AEGP_RegisterUpdateMenuHook	Register your menu update function (which determines
AEGI_NegIsteropuatemenunook	whether or not items are active), called every time any
	menu is to be drawn.
	This hook function handles updates for all menus.
	AEGP_RegisterUpdateMenuHook(
	AEGP_PluginID aegp_plugin_id,
	AEGP_UpdateMenuHook update_menu_hook_ func,
	<pre>void *refconPV);</pre>
AEGP_RegisterDeathHook	Register your termination function. Called when the application quits.
	prication quits.
	AEGP_RegisterDeathHook(
	AEGP_PluginID aegp_plugin_id,
	AEGP_DeathHook death_hook_func, void *refconPV);
	, ,
AEGP_RegisterVersionHook	Currently not called.
AEGP_RegisterAboutStringHook	Currently not called.
AEGP_RegisterAboutHook	Currently not called.
AEGP_RegisterArtisan	Register your Artisan. See <i>Artisans</i> for more details.
	AEGP_RegisterArtisan(
	A_Version api_version,
	A_Version Artisan_version,
	long aegp_plugin_id,
	void *aegp_refconPV,
	<pre>const A_char</pre>
	PR_ArtisanEntryPoints *entry_funcsP);
AHOD Devision TO	
AEGP_RegisterIO	Register your AEIO plug-in. See <i>AEIOs</i> for more details.
232	Chapter 64. AEGP Suites AEGP_RegisterIO (
	AEGP_Registerio (AEGP_PluginID aegp_plugin_
	AEGF_FIUGINID aegp_prugin_
	AEGP TORefcon aegp

64.5 Manage Projects

These functions access and modify project data. Support for multiple projects is included to prepare for future expansion; After Effects currently adheres to the single project model.

To save project-specific data in After Effects' preferences (and thus, outside the projects themselves), use the *Persistent Data Suite*.

Use caution: the functions for opening and creating projects do not save changes to the project currently open when they are called!

64.5.1 AEGP_ProjSuite6

Function	Purpose
AEGP_NumProjects	Currently will never return more than 1. After Effects
	can have only one project open at a time.
	AEGP_GetNumProjects(
	A_long *num_projPL)
AEGP_GetIndProject	Retrieves a specific project by index.
AEGF_GetIndF10Jett	
	AEGP_GetProjectProjectByIndex(
	A_long proj_indexL, AEGP_ProjectH *projPH);
AEGP_GetProjectName	Get the project name (up to
	AEGP_MAX_PROJ_NAME_LEN + 1) in length.
	AEGP_GetProjectName(
	AEGP_ProjectH projH,
	A_char *nameZ);
AEGP_GetProjectPath	Get the path of the project (empty string the project
-	hasn't been saved yet).
	The path is a handle to a NULL-terminated
	A_UTF16Char string, and must be disposed with
	AEGP_FreeMemHandle.
	AEGP_GetProjectPath(
	AEGP_ProjectH projH,
	AEGP_MemHandle *unicode_pathPH)
AEGP_GetProjectRootFolder	Get the root of the project, which After Effects also
	treats as a folder.
	AEGP_GetProjectRootFolder(
	AEGP_ProjectH projH,
	AEGP_ItemH *root_folderPH)
AEGP_SaveProjectToPath	Saves the entire project to the specified full path.
	The file path is a NULL-terminated UTF-16 string with
	platform separators.
	AEGP_SaveProjectToPath(
	AEGP_ProjectH projH,
	<pre>const A_UTF16Char *pathZ);</pre>
AEGP_GetProjectTimeDisplay	Retrieves the current time display settings.
	AEGP_GetProjectTimeDisplay(
	AEGP_ProjectH projH,
	AEGP_TimeDisplay3 *time_displayP);
	<pre>typedef struct { AEGP_TimeDisplayMode</pre>
	→display_mode;
	AEGP_SourceTimecodeDisplayMode _
	<pre>→footage_display_mode;</pre>
	A_Boolean
	→display_dropframeB; A_Boolean use_
	A_Boolean use_ →feet_framesB;
	A_char
4.5. Managa Drainata	→timebaseC;
4.5. Manage Projects	A_char frame 33
	<pre>→per_footC; AEGP_FramesDisplayMode</pre>
	ALGP_framesDIsplayMode Irames_ →display_mode;
	TECH Time Diem land

64.5.2 AEGP_TimeDisplay2

Note: Values in unused fields persist when After Effects is using a different display type.

Member	Description
AEGP_TimeDisplayType type;	One of the following:
	• AEGP_TimeDisplayType_TIMECODE
	• AEGP_TimeDisplayType_FRAMES
	AEGP_TimeDisplayType_FEET_AND_FRAMES
A_char timebaseC;	0 - 100. Only used for
	AEGP_TimeDisplayType_TIMECODE.
A_Boolean non_drop_30B;	When the timebase is 30 and the item's framerate is
	29.97, determines whether to display as non-drop frame.
A_char frames_per_footC;	Only used for AEGP_TimeDisplayType_FEET_AND_FRAMES
A_long starting_frameL;	Usually 0 or 1. Not used when type is usually 0 or 1, not
	used for AEGP_TimeDisplayType_TIMECODE.
A_Boolean auto_timecode_baseB;	If TRUE, the project timecode display setting is set to
	auto.

64.6 Control Items Within Projects

Accesses and modifies items within a project or composition.

Anything in the project bin is an AEGP_Item. Note that cameras have no source, and thus have no AEGP_ItemH.

Unless more specificity is required for the function(s) you're using, remain as abstract as possible; AEGP_Comps are passed into and returned from most functions as AEGP_Items.

64.6.1 AEGP ItemSuite9

Function	Purpose
AEGP_GetFirstProjItem	Retrieves the first item in a given project.
	AEGP_GetFirstProjItem(
	AEGP_ProjectH projectH,
	AEGP_ItemH *itemPH);
AEGP_GetNextProjItem	Retrieves the next project item; *next_itemPH will be NULL after the last item.
	AEGP_GetNextProjItem(
	AEGP_ProjectH projectH,
	AEGP_ItemH itemH,
	AEGP_ItemH *next_itemPH);

Table 2 – continued from previous page

Function	Purpose
AEGP_GetActiveItem	If the Project window is active, the active item is the selected item (if only one item is selected). If a Composition, Timeline, or Footage window is active, returns the parent of the layer associated with the front-most tab in the window. Returns NULL if no item is active. AEGP_GetActiveItem(AEGP_ItemH *itemPH,
AEGP_IsItemSelected	Returns true if the Project window is active and the item is selected. AEGP_IsItemSelected(AEGP_ItemH itemH, A_Boolean *selectedPB)
AEGP_SelectItem	Toggles the selection state of the item, and (depending on deselect_othersB) can deselect other items. This call selects items in the Project panel. To make selections in the Composition panel, use AEGP_SetSelection from AEGP_CompSuite11. AEGP_SelectItem(AEGP_ItemH itemH, A_Boolean selectB, A_Boolean deselect_othersB);
AEGP_GetItemType	Gets type of an item. Note: solids don't appear in the project, but can be the source to a layer. AEGP_GetItemType(AEGP_ItemH
AEGP_GetTypeName	Get name of type. (name length up to AEGP_MAX_TYPE_NAME_LEN + 1). AEGP_GetTypeName(AEGP_ItemType item_type, A_char *nameZ);
AEGP_GetItemName	Get item name. (name length has no limit). unicode_namePH points to A_UTF16Char (contains null terminated UTF16 string). It must be disposed with AEGP_FreeMemHandle. AEGP_GetItemName(

Table 2 – continued from previous page

Function	Purpose
AEGP_SetItemName	Specifies the name of the AEGP_ItemH. (name length
Abdi_Jetitemwame	has no limit). Undoable.
	AEGP_SetItemName(
	AEGP_ItemH itemH,
	<pre>const A_UTF16Char *nameZ);</pre>
AEGP_GetItemID	Returns the item's unique ID, which persists across
	saves and loads of the project.
	AEGP_GetItemID(
	AEGP_ItemH itemH,
	A_long *item_idPL);
AEGP_GetItemFlags	Get properties of an item.
	AEGP_GetItemFlags(
	AEGP_ItemH itemH,
	AEGP_ItemFlags *item_flagsP);
	Flag values (may be OR'd together):
	• AEGP_ItemFlag_MISSING
	• AEGP_ItemFlag_HAS_PROXY
	AEGP_ItemFlag_USING_PROXYAEGP_ItemFlag_MISSING_PROXY
	• AEGP_ItemFlag_HAS_VIDEO
	• AEGP_ItemFlag_HAS_AUDIO
	• AEGP_ItemFlag_STILL
	• AEGP_ItemFlag_HAS_ACTIVE_AUDIO
	Unlike the HAS_AUDIO flag, this bit flag will set only
	if the comp has at least one layer where audio is actually
	on.
AEGP_SetItemUseProxy	Toggle item's proxy usage. Undoable.
	AEGP_SetItemUseProxy(
	AEGP_ItemH itemH,
	A_Boolean use_proxyB);
AEGP_GetItemParentFolder	Get folder containing item.
	AEGP_GetItemParentFolder(
	AEGP_ItemH itemH,
	AEGP_ItemH *parent_itemPH);
AEGP_SetItemParentFolder	Sets an item's parent folder. Undoable.
	AEGP_SetItemParentFolder(
	AEGP_ItemH itemH,
	AEGP_ItemH parent_folderH);
AEGP_GetItemDuration	Get duration of item, in seconds.
	AEGP_GetItemDuration(
	AEGP_ItemH itemH, A_Time *durationPT);

Table 2 – continued from previous page

Function	Purpose
AEGP_GetItemCurrentTime	Get current time within item. Not updated while rendering.
	<pre>AEGP_GetItemCurrentTime(AEGP_ItemH itemH, A_long *curr_timePT);</pre>
AEGP_GetItemDimensions	Get width and height of item.
	AEGP_GetItemDimensions(AEGP_ItemH itemH, A_long *widthPL) A_long *heightPL);
AEGP_GetItemPixelAspectRatio	Get the width of a pixel, assuming its height is 1.0, as numerator over denominator. AEGP_GetItemPixelAspectRatio(AEGP_ItemH itemH, A_Ratio *ratioPRt);
AEGP_DeleteItem	Removes item from all compositions. Undo-able. Do not use the AEGP_ItemH after calling this function. AEGP_DeleteItem(AEGP_ItemH itemH);
AEGP_GetItemSolidColor	Removed in AEGP_ItemSuite4. See AEGP_GetSolidFootageColor from AEGP_FootageSuite5 Given a solid item, return its color. AEGP_GetItemSolidColor(AEGP_ItemH itemH, PF_Pixel *PF_Pixel);
AEGP_SetSolidColor	Removed in AEGP_ItemSuite4. See AEGP_SetSolidFootageColor from AEGP_FootageSuite5. Sets the color of an existing solid (error if itemH is not a solid). AEGP_SetSolidColor(AEGP_ItemH itemH, AEGP_ColorVal color);
AEGP_SetSolidDimensions	Removed in AEGP_ItemSuite4. See AEGP_SetSolidFootageDimensions from AEGP_FootageSuite5. Sets the dimensions of an existing solid (error if itemH is not a solid). AEGP_SetSolidDimensions(AEGP_ItemH itemH, A_short widthS, A_short heightS);

Table 2 – continued from previous page

Function	ntinued from previous page Purpose
AEGP_CreateNewFolder	Creates a new folder in the project. The newly created folder is allocated and owned by After Effects. Passing NULL for parent_folderH0 creates the folder at the project's root. AEGP_CreateNewFolder(const A_UTF16Char *nameZ, AEGP_ProjectH projH), AEGP_ItemH parentH0), AEGP_ItemH *new_folderPH);
AEGP_SetItemCurrentTime	Sets the current time within a given itemH. AEGP_SetItemCurrentTime(AEGP_ItemH itemH, const A_Time *new_timePT);
AEGP_GetItemCommentLength	Removed in ItemSuite9. Retrieves the length (in characters) of the itemH's comment. AEGP_GetItemCommentLength(AEGP_ItemH itemH, A_u_long *buf_sizePLu);
AEGP_GetItemComment	Updated to support Unicode in ItemSuite9, available in 14.1. Retrieves the itemH's comment. AEGP_GetItemComment(AEGP_ItemH itemH, AEGP_MemHandle *unicode_namePH);
AEGP_SetItemComment	Updated to support Unicode in ItemSuite9, available in 14.1. Sets the itemH's comment. AEGP_SetItemComment(AEGP_ItemH itemH, const A_UTF16Char *commentZ);
AEGP_GetItemLabel	Retrieves an item's label. AEGP_GetItemLabel(AEGP_ItemH itemH, AEGP_LabelID *labelP);
AEGP_SetItemLabel	Sets an item's label. AEGP_SetItemLabel(AEGP_ItemH itemH, AEGP_LabelID label);
AEGP_GetItemMRUView	Gets an item's most recently used view. The view can be used with two calls in the AEGP_ColorSettingsSuite, to perform a color transform on a pixel buffer from working to view color space. AEGP_GetItemMRUView(AEGP_ItemH itemH, AEGP_ItemViewP *mru_viewP);

Note: AEGP_RenderNewItemSoundData() used to be here, but is now part of AEGP_RenderSuite4.

64.7 Managing Selections

This suite manages selection states, mirroring the functionality supplied by vectors in the C++ Standard Template Library.

Many types of items may be simultaneously selected in After Effects; AEGP_CollectionItems are unions of layer, mask, effect, stream, mask vertex, and keyframe items.

First acquire the current collection, then iterate across its members to ensure that whatever your AEGP does is applicable to each.

We've added AEGP_Collection2H and AEGP_CollectionItemV2 so that selected dynamic streams can be handled with the AEGP_CollectionSuite.

64.7.1 AEGP_CollectionSuite2

Function	Purpose
AEGP_NewCollection	Creates and returns a new, empty collection. To obtain the current composition's selection as a collection, use AEGP_GetNewCollectionFromCompSelection.
	AEGP_NewCollection(AEGP_PluginID plugin_id, AEGP_Collection2H *collectionPH);
AEGP_DisposeCollection	Disposes of a collection.
	AEGP_DisposeCollection(AEGP_Collection2H collectionH);
AEGP_GetCollectionNumItems	Returns the number of items contained in the given collection.
	AEGP_GetCollectionNumItems(AEGP_Collection2H collectionH, A_u_long *num_itemsPL);
AEGP_GetCollectionItemByIndex	Retrieves (creates and populates) the index'd collection item.
	AEGP_GetCollectionItemByIndex(AEGP_Collection2H collectionH, A_u_long indexL, AEGP_CollectionItemV2 *itemP);
AEGP_CollectionPushBack	Adds an item to the given collection.
	AEGP_CollectionPushBack(AEGP_Collection2H →collectionH, const AEGP_CollectionItemV2 *itemP);
AEGP_CollectionErase	Removes an index'd item (or items) from a given collection. NOTE: this range is exclusive, like STL iterators. To erase the first item, you would pass 0 and 1, respectively.
	AEGP_CollectionErase(AEGP_Collection2H collectionH, A_u_long index_firstL, A_u_long index_lastL);

64.7.2 Ownership Of Collection Items

When AEGP_StreamRefHs are inserted into a collection, they are adopted by the collection; do not free them. AEGP_EffectRefHs, on the other hand, are not adopted, and must be freed by the calling AEGP.

64.8 Manipulate Compositions

Provide information about the compositions in a project, and create cameras, lights, and solids.

64.8.1 AEGP_CompSuite11

Function	Purpose
AEGP_GetCompFromItem	Retrieves the handle to the composition, given an item handle. Returns NULL if itemH is not an AEGP_CompH.
	AEGP_GetCompFromItem(AEGP_ItemH itemH, AEGP_CompH *compPH);
AEGP_GetItemFromComp	Used to get the item handle, given a composition handle. AEGP_GetItemFromComp(AEGP_CompH compH, AEGP_ItemH *itemPH);
AEGP_GetCompDownsampleFactor	Returns current downsample factor. Measured in pixels X by Y. Users can choose a custom downsample factor with independent X and Y. AEGP_GetCompDownsampleFactor(AEGP_CompH compH, AEGP_DownsampleFactor *dsfP);
AEGP_SetCompDownsampleFactor	Sets the composition's downsample factor. AEGP_SetCompDownsampleFactor(AEGP_CompH compH, AEGP_DownsampleFactor *dsfP);
AEGP_GetCompBGColor	Returns the composition background color. AEGP_GetCompBGColor(AEGP_CompH compH, AEGP_ColorVal *bg_colorP);
AEGP_SetCompBGColor	Sets a composition's background color. AEGP_SetCompBGColor(AEGP_CompH

Table 3 – continued from previous page

Function	Purpose
AEGP_GetCompFlags	Returns composition flags, or'd together.
	AEGP_CompFlags(AEGP_CompFlags (AEGP_CompFlags *AEGP_CompFlags); • AEGP_CompFlag_SHOW_ALL_SHY • AEGP_CompFlag_ENABLE_MOTION_BLUR • AEGP_CompFlag_ENABLE_TIME_FILTER • AEGP_CompFlag_GRID_TO_FRAME • AEGP_CompFlag_GRID_TO_FIELDS • AEGP_CompFlag_USE_LOCAL_DSF • AEGP_CompFlag_DRAFT_3D • AEGP_CompFlag_SHOW_GRAPH
AEGP_GetShowLayerNameOrSourceName	New in CC. Passes back true if the Comp's timeline shows layer names, false if source names. This will open the comp as a side effect. AEGP_GetShowLayerNameOrSourceName(AEGP_CompH compH, A_Boolean *layer_names_shownPB);
AEGP_SetShowLayerNameOrSourceName	New in CC. Pass in true to have the Comp's timeline show layer names, false for source names. This will open the comp as a side effect. AEGP_SetShowLayerNameOrSourceName(AEGP_CompH compH, A_Boolean *layer_names_shownPB);
AEGP_GetShowBlendModes	New in CC. Passes back true if the Comp's timeline shows blend modes column, false if hidden. This will open the comp as a side effect. AEGP_GetShowBlendModes(AEGP_CompH compH, A_Boolean *blend_modes_shownPB);
AEGP_SetShowBlendModes	New in CC. Pass in true to have the Comp's timeline show the blend modes column, false to hide it. This will open the comp as a side effect. AEGP_GetCompFlags(AEGP_CompH compH, A_Boolean show_blend_modesB);
AEGP_GetCompFramerate	Returns the composition's frames per second. AEGP_GetCompFramerate(AEGP_CompH compH, A_FpLong *fpsPF);
AEGP_SetCompFramerate	Sets the composition's frames per second. AEGP_SetCompFramerate(AEGP_CompH compH, A_FpLong *fpsPF);

Table 3 – continued from previous page

Function Purpose	
AEGP_GetCompShutterAnglePhase	The composition shutter angle and phase.
THE	AEGP_GetCompShutterAnglePhase(AEGP_CompH compH, A_Ratio *angle, A_Ratio *phase);
AEGP_GetCompShutterFrameRange	The duration of the shutter frame, in seconds.
	AEGP_GetCompShutterFrameRange(AEGP_CompH compH, const A_Time *comp_timeP);
AEGP_GetCompSuggestedMotionBlurSamples	Retrieves the number of motion blur samples After Effects will perform in the given composition.
	AEGP_GetCompSuggestedMotionBlurSamples(AEGP_CompH compH, A_long *samplesPL)
AEGP_SetCompSuggestedMotionBlurSamples	Specifies the number of motion blur samples After Effects will perform in the given composition. Undoable.
	AEGP_SetCompSuggestedMotionBlurSamples(AEGP_CompH compH, A_long samplesL);
AEGP_GetCompMotionBlurAdaptiveSampleLi	Mew in CC. Retrieves the motion blur adaptive sample limit for the given composition. As of CC, a new comp defaults to 128.
	AEGP_ →GetCompMotionBlurAdaptiveSampleLimit(AEGP_CompH compH, A_long *samplesPL)
AEGP_SetCompMotionBlurAdaptiveSampleLi	mNew in CC. Specifies the motion blur adaptive sample limit for the given composition. As of CC, both the limit and the suggested values are clamped to [2,256] range and the limit value will not be allowed less than the suggested value. Undoable. AEGP_ SetCompMotionBlurAdaptiveSampleLimit (AEGP_CompH compH, A_long samplesL);
AEGP_GetCompWorkAreaStart	Get the time where the current work area starts.
	AEGP_GetCompWorkAreaStart(AEGP_CompH compH, A_Time *startPT);
AEGP_GetCompWorkAreaDuration	Get the duration of a composition's current work area, in seconds.
	AEGP_GetCompWorkAreaDuration(AEGP_CompH compH, A_Time *durationPT);

Table 3 – continued from previous page

Function	Purpose
	<u> </u>
AEGP_SetCompWorkAreaStartAndDuration	Set the work area start and duration, in seconds. Undoable. One call to this function is sufficient to set the layer's in point and duration; it's not necessary to call it twice, once for each timespace.
	AEGP_SetCompWorkAreaStartAndDuration(AEGP_CompH
AEGP_CreateSolidInComp	Creates a new solid with a specified width, height, color, and duration in the composition. Undo-able. If you pass NULL for the duration, After Effects uses its preference for the duration of a new still. If you pass NULL, or an invalid time scale, duration is set to the length of the composition.
	AEGP_CreateSolidInComp(const A_UTF16Char *utf_nameZ, A_Long widthL, A_Long heightL, const PF_Pixel *color, AEGP_CompH parent_compH, const A_Time *durationPT0, AEGP_LayerH *new_solidPH);
AEGP_CreateCameraInComp	Creates and adds a camera to the specified composition. Once created, you can manipulate the camera's parameter streams using the AEGP Stream Suite. To specify a two-node camera, use AEGP_SetLayerFlag from AEGP_LayerSuite8 to set AEGP_LayerFlag_LOOK_AT_POI.
	AEGP_CreateCameraInComp(const A_UTF16Char *utf_nameZ, A_FloatPoint center_point, AEGP_CompH parent_compH, AEGP_LayerH *new_cameraPH);
AEGP_CreateLightInComp	Creates and adds a light to the specified composition. Once created, you can manipulate the light's parameter streams using the AEGP <i>Stream Suite</i> .
	AEGP_CreateLightInComp(const A_UTF16Char *utf_nameZ, A_FloatPoint center_point, AEGP_CompH parent_compH, AEGP_LayerH *new_lightPH); Continued on post page

Table 3 – continued from previous page

Function	Purpose
AEGP_CreateComp	Creates a new composition for the project. If you don't provide a parent folder, the composition will be at the root level of the project. Undo-able.
	AEGP_CreateComp(AEGP_ItemH parent_folderHO, const A_UTF16Char *utf_nameZ, A_Long widthL, A_Long heightL, const A_Ratio *pixel_aspect_ →ratioPRt, const A_Time *durationPT, const A_Ratio *frameratePRt, AEGP_CompH *new_compPH);
AEGP_GetNewCollectionFromCompSelection	Creates a new AEGP_Collection2H from the items selected in the given composition. The plug-in is responsible for disposing of the AEGP_Collection2H.
	AEGP_GetNewCollectionFromCompSelection(AEGP_PluginID plugin_id, AEGP_CompH compH, AEGP_Collection2H *collectionPH);
AEGP_SetSelection	Sets the selection within the given composition to the given AEGP_Collection2H. Will return an error if members of the AEGP_Collection2H are not available. Don't assume that a composition hasn't changed between operations; always use a fresh AEGP_Collection2H. AEGP_SetSelection(AEGP_CompH compH, AEGP_Collection2H collectionH);
AEGP_GetCompDisplayStartTime	Gets the displayed start time of a composition. AEGP_GetCompDisplayStartTime(AEGP_CompH compH, const A_Time *start_timePT);
AEGP_SetCompDisplayStartTime	Not undo-able. Sets the displayed start time of a composition (has no effect on the duration of the composition). AEGP_SetCompDisplayStartTime (AEGP_CompH compH, const A_Time *start_timePT);
AEGP_SetCompDuration	Undoable. Sets the duration of the given composition. AEGP_SetCompDuration(AEGP_CompH

Table 3 – continued from previous page

Function	Purpose
AEGP_CreateNullInComp	Creates a "null object" in the composition (useful for translating projects from 3D applications into After Effects). If you pass NULL for the duration, After Effects uses its preference for the duration of a new still. If you pass 0, or an invalid time scale, duration is set to the length of the composition. AEGP_CreateNullInComp(const A_UTF16Char *utf_nameZ, AEGP_CompH parent_compH, const A_Time *durationPT0, AEGP_LayerH *new_null_solidPH);
AEGP_SetCompPixelAspectRatio	Sets the pixel aspect ratio of a composition. AEGP_SetCompPixelAspectRatio(AEGP_CompH compH,
AEGP_CreateTextLayerInComp	<pre>const A_Ratio *parPRt);</pre> Updated in CS6. Creates a text layer in the composition,
	<pre>and returns its AEGP_LayerH. AEGP_CreateTextLayerInComp(AEGP_CompH parent_compH, A_Boolean select_new_layerB, AEGP_LayerH *new_text_lyrPH);</pre>
AEGP_CreateBoxTextLayerInComp	Updated in CS6. Creates a new box text layer, and returns its AEGP_LayerH. AEGP_CreateBoxTextLayerInComp(AEGP_CompH parent_compH, A_Boolean select_new_layerB, A_FloatPoint box_dimensions, AEGP_LayerH *new_text_layerPH);
AEGP_SetCompDimensions	Sets the dimensions of the composition. Undoable. AEGP_SetCompDimensions (AEGP_CompH compH, A_long widthL, A_long heightL);
AEGP_DuplicateComp	Duplicates the composition. Undoable. AEGP_DuplicateComp(AEGP_CompH compH, AEGP_CompH *new_compPH);
AEGP_GetCompFrameDuration	Retrieves the duration of a frame in a composition. AEGP_GetCompFrameDuration(AEGP_CompH compH, A_Time *timeP);

Table 3 – continued from previous page

Function	Purpose
AEGP_GetMostRecentlyUsedComp	Returns the most-recently-used composition. AEGP_GetMostRecentlyUsedComp(AEGP_CompH *compPH);
AEGP_CreateVectorLayerInComp	Creates and returns a handle to a new vector layer. AEGP_CreateVectorLayerInComp(AEGP_CompH parent_compH, AEGP_LayerH *new_vec_layerPH);
AEGP_GetNewCompMarkerStream	Returns an AEGP_StreamRefH to the composition's marker stream. Must be disposed by caller. AEGP_GetNewCompMarkerStream(AEGP_PluginID aegp_plugin_id, AEGP_CompH parent_compH, AEGP_StreamRefH *streamPH);
AEGP_GetCompDisplayDropFrame	Passes back a boolean that indicates whether the speci- fied comp uses drop-frame timecode or not. AEGP_GetCompDisplayDropFrame(AEGP_CompH compH, A_Boolean *dropFramePB);
AEGP_SetCompDisplayDropFrame	Sets the dropness of the timecode in the specified composition. AEGP_SetCompDisplayDropFrame(AEGP_CompH compH, A_Boolean dropFrameB);
AEGP_ReorderCompSelection	Move the selection to a certain layer index. Use along with AEGP_SetSelection(). AEGP_SetCompDisplayDropFrame(AEGP_CompH compH, A_long index);

64.9 Work with Footage

Provides information about footage, or items in a project or composition. When getting and setting footage's interpretation, it is possible to specify incompatible options.

If you encounter warnings and errors during development, be sure to make all related changes atomically, and reassess the logic of the operation you're performing.

For example, changing the pull-down interpretation of footage won't work unless there's a difference between it's native and conformed frame rate.

Depending on what you're trying to accomplish, it may make sense to abort all of your operations at that point, inform the user of the problem encountered.

64.9.1 AEGP_FootageSuite5

Function	Purpose
AEGP_GetMainFootageFromItem	Returns an error if item isn't a footage item. Used to convert an item handle to a footage handle.
	AEGP_GetMainFootageFromItem(AEGP_ItemH
AEGP_GetProxyFootageFromItem	Returns an error if item has no proxy. Returns the proxy footage handle. Note: a composition can have a proxy.
	AEGP_GetProxyFootageFromItem(AEGP_ItemH
AEGP_GetFootageNumFiles	Returns the number of data (RGBA or audio) files, and the number of files per frame (may be greater than one if the footage has auxiliary channels).
	AEGP_GetFootageNumFiles(AEGP_FootageH footageH, A_long *num_filesPL0, A_long *files_per_frmPL0);
AEGP_GetFootagePath	Get fully realized path to footage source file. Retrieves the footage path for a piece of footage (or for the specified frame of a footage sequence). frame_numL ranges from 0 to num_main_files, as obtained using AEGP_GetFootageNumFiles from AEGP_FootageSuite5. AEGP_FOOTAGE_MAIN_FILE_INDEX is the main file. The path is a handle to a NULL-terminated A_UTF16Char string, and must be disposed with AEGP_FreeMemHandle.
	AEGP_GetFootagePath(AEGP_FootageH footageH, A_long frame_numL, A_long file_indexL, AEGP_MemHandle *unicode_pathPH);
AEGP_GetFootageSignature	Retrieves the footage signature of specified footage. AEGP_GetFootageSignature(AEGP_FootageH footageH, AEGP_FootageSignature *sigP);
	The signature will be one of the following: • AEGP_FootageSignature_NONE • AEGP_FootageSignature_MISSING • AEGP_FootageSignature_SOLID
AEGP_NewFootage	Creates a new footage item. The file path is a NULL-terminated UTF-16 string with platform separators. Note that footage filenames with colons are not allowed, since colons are used as path separators in the HFS+ file system.
4.9. Work with Footage	AEGP_NewFootage(AEGP_PluginID →aegp_plugin_id, const A_UTF16Char →*pathZ,

const AEGP FootageLaverKey

64.9.2 AEGP_FootageInterp Structure

Member	Purpose
AEGP_InterlaceLabel il;	The interlace settings for the footage item.
	A_u_long signature; // 'FIEL'
	A_short version;
	FIEL_Type type;
	FIEL_Order order;
	A_u_long reserved;
	FIEL_Type is one of the following:
	• FIEL_Type_FRAME_RENDERED
	• FIEL_Type_INTERLACED
	• FIEL_Type_HALF_HEIGHT
	• FIEL_Type_FIELD_DOUBLED
	FIEL_Type_FIELD_DOUBLED means 60 full-sized
	field doubled frames per second.
	FIEL_Order is either
	FIEL_Order_UPPER_FIRST or
AUCD Almbatabal al.	FIEL_Order_LOWER_FIRST.
AEGP_AlphaLabel al;	AECD AlabaElas Class
	AEGP_AlphaFlag flags; A_u_char redCu;
	A_u_char greenCu;
	A_u_char greencu; A_u_char blueCu;
	AEGP_AlphaFlags is one or more of the following,
	OR'd together:
	• AEGP_AlphaPremul
	• AEGP_AlphaInverted
	• AEGP_AlphaIgnore
	If AEGP_AlphaPremul is not set, straight alpha is as-
	sumed. AEGP_AlphaInverted indicates that higher
	values are transparent, instead of lower.
AEGP_PulldownPhase pd;	Indicates the phase for use in 3:2 pulldown. One of the
	following:
	• AEGP_PulldownPhase_NO_PULLDOWN,
	• AEGP_PulldownPhase_WSSWW,
	• AEGP_PulldownPhase_SSWWW,
	• AEGP_PulldownPhase_SWWWS,
	AEGP_PulldownPhase_WWWSS,AEGP PulldownPhase WWSSW,
	• AEGP_PulldownPhase_WWWSW,
	• AEGP_PulldownPhase_WWSWW,
	• AEGP_PulldownPhase_WSWWW,
	• AEGP_PulldownPhase_SWWWW,
	• AEGP_PulldownPhase_WWWWS
AEGP_LoopBehavior loop;	Indicates the number of times the footage should loop.
	A_long loops;
	A_long reserved;
A_Ratio pix_aspect_ratio;	Expresses the pixel aspect ratio of the footage (x over
P. Bulliana and C. B.	y).
A_FpLong native_fpsF;	The original framerate (in frames per second) of the
A Francisco conform for all	footage item.
A_FpLong_conform_fpsF; 64.9 Work with Footage	The framerate being used for the footage item. The pixel depth of the footage. One of the following: 253
A_rong depend;	• AEGP_Footage_Depth_1
	• AEGP_Footage_Depth_1 • AEGP_Footage_Depth_2
	• AEGP_Footage_Depth_4
	T vegi Ti oocade Thehrii 4

64.10 Manage Layers

AEGP_LayerSuite provides information about layers within a composition, and the relationship(s) between the source and layer times.

As most After Effects usage boils down to layer manipulation, this is among the largest function suites in our API.

64.10.1 AEGP_LayerSuite8

Function	Purpose
AEGP_GetCompNumLayers	Obtains the number of layers in a composition.
	AEGP_GetCompNumLayers(
	AEGP_CompH compH,
	A_long *num_layersPL);
AEGP_GetCompLayerByIndex	Get a AEGP_LayerH from a composition. Zero is the foremost layer.
	AEGP_GetCompLayerByIndex(
	AEGP_CompH compH,
	A_long layer_indexL,
	AEGP_LayerH *layerPH);
AEGP_GetActiveLayer	Get the active layer. If a Layer or effect controls palette is active, the active layer is that associated with the front-most tab in the window. If a composition or timeline window is active, the active layer is the selected layer (if only one is selected; otherwise NULL is returned).
	<pre>AEGP_GetActiveLayer(AEGP_LayerH *layerPH);</pre>
AEGP_GetLayerIndex	Get the index of the layer (0 is the topmost layer in the composition).
	AEGP_GetLayerIndex(
	AEGP_LayerH layerH,
	A_long *layer_indexPL);
AEGP_GetLayerSourceItem	Get the AEGP_ItemH of the layer's source item.
	AEGP_GetLayerSourceItem(
	AEGP_LayerH layerH,
	AEGP_ItemH *source_itemPH);
AEGP_GetLayerSourceItemID	Retrieves the ID of the given AEGP_LayerH. This
	is useful when hunting for a specific layer's ID in an
	AEGP_StreamVal.
	AEGP_GetLayerSourceItemID(
	AEGP_LayerH layerH,
	A_long *source_idPL);
	Continued on next page

Table 4 – continued from previous page

Function	Purpose
AEGP_GetLayerParentComp	Get the AEGP_CompH of the composition containing the layer.
	AEGP_GetLayerParentComp(AEGP_LayerH layerH, AEGP_CompH *compPH);
AEGP_GetLayerName	Get the name of a layer. Both utf_layer_namePH0 and utf_source_namePH0 point to null terminated UTF-16 strings. They must be disposed with AEGP_FreeMemHandle.
	AEGP_GetLayerName(AEGP_PluginID pluginID, AEGP_LayerH layerH, AEGP_MemHandle *utf_layer_namePH0, AEGP_MemHandle *utf_source_namePH0);
AEGP_GetLayerQuality	Get the quality of a layer.
	AEGP_GetLayerQuality(AEGP_LayerH layerH, AEGP_LayerQuality *qualityP);
	Layer quality is one of the following flags:
	• AEGP_LayerQual_NONE
	AEGP_LayerQual_WIREFRAMEAEGP_LayerQual_DRAFT
	• AEGP_LayerQual_BEST
AEGP_SetLayerQuality	Sets the quality of a layer (see flag values above). Undoable.
	AEGP_SetLayerQuality(AEGP_LayerH layerH, AEGP_LayerQuality quality);

Table 4 – continued from previous page

Function	Purpose
AEGP_GetLayerFlags	Get flags for a layer.
_ 1	
	AEGP_GetLayerFlags(AEGP_LayerH layerH,
	AEGP_LayerFlags *layer_flagsP);
	• AEGP_LayerFlag_NONE
	• AEGP_LayerFlag_VIDEO_ACTIVE,
	• AEGP_LayerFlag_AUDIO_ACTIVE,
	• AEGP_LayerFlag_EFFECTS_ACTIVE,
	• AEGP_LayerFlag_MOTION_BLUR,
	• AEGP_LayerFlag_FRAME_BLENDING,
	• AEGP_LayerFlag_LOCKED,
	• AEGP_LayerFlag_SHY,
	• AEGP_LayerFlag_COLLAPSE,
	• AEGP_LayerFlag_AUTO_ORIENT_ROTATION,
	• AEGP_LayerFlag_ADJUSTMENT_LAYER,
	• AEGP_LayerFlag_TIME_REMAPPING,
	• AEGP_LayerFlag_LAYER_IS_3D,
	• AEGP_LayerFlag_LOOK_AT_CAMERA,
	• AEGP_LayerFlag_LOOK_AT_POI,
	• AEGP_LayerFlag_SOLO,
	• AEGP_LayerFlag_MARKERS_LOCKED,
	• AEGP_LayerFlag_NULL_LAYER,
	• AEGP_LayerFlag_HIDE_LOCKED_MASKS,
	• AEGP_LayerFlag_GUIDE_LAYER,
	• AEGP_LayerFlag_ENVIRONMENT_LAYER,
	 AEGP_LayerFlag_ADVANCED_FRAME_BLENDING,
	True only if pixel motion frame blending is on
	for the layer.
	• AEGP_LayerFlag_SUBLAYERS_RENDER_SEPARATE
	Used to get/set the state of per-character 3D en-
	ablement on a text layer.
	• AEGP_LayerFlag_ENVIRONMENT_LAYER,
	New in CS6.
AEGP_SetLayerFlag	Sets one layer flag at a time. Undoable.
	AEGP_SetLayerFlag(
	AEGP_LayerH layerH, AEGP_LayerFlags single_flag,
	A_Boolean valueB);
	n_bootean varueb,,
AEGP_IsLayerVideoReallyOn	Determines whether the layer's video is visible. This is
	necessary to account for 'solo' status of other layers in
	the composition; non-solo'd layers are still on.
	AEGP_IsLayerVideoReallyOn(
	AEGP_LayerH layerH, A_Boolean *onPB);
	V_POOLEGII VOIIED),

Table 4 – continued from previous page

Function	ed from previous page Purpose
AEGP_IsLayerAudioReallyOn	Accounts for solo status of other layers in the composition.
	AEGP_IsLayerAudioReallyOn(AEGP_LayerH layerH, A_Boolean *onPB);
AEGP_GetLayerCurrentTime	Get current time, in layer or composition timespace. This value is not updated during rendering. NOTE: If a layer starts at other than time 0 or is timestretched other than 100%, layer time and composition time are distinct.
	AEGP_GetLayerCurrentTime(AEGP_LayerH layerH, AEGP_LTimeMode time_mode, A_Time *curr_timePT);
AEGP_GetLayerInPoint	Get time of first visible frame in composition or layer time. In layer time, the in_pointPT is always 0.
	AEGP_GetLayerInPoint(AEGP_LayerH layerH, AEGP_LTimeMode time_mode, A_Time *in_pointPT);
AEGP_GetLayerDuration	Get duration of layer, in composition or layer time, in seconds.
	AEGP_GetLayerDuration(AEGP_LayerH layerH, AEGP_LTimeMode time_mode, A_Time *durationPT);
AEGP_SetLayerInPointAndDuration	Set duration and in point of layer in composition or layer time. Undo-able.
	AEGP_SetLayerInPointAndDuration(AEGP_LayerH layerH, AEGP_LTimeMode time_mode, const A_Time *in_pointPT, const A_Time *durationPT);
AEGP_GetLayerOffset	Get the offset from the start of the composition to layer time 0, in composition time.
	AEGP_GetLayerOffset(AEGP_LayerH layerH, A_Time *offsetPT);
AEGP_SetLayerOffset	Set the offset from the start of the composition to the first frame of the layer, in composition time. Undoable.
	AEGP_SetLayerOffset(AEGP_LayerH layerH, A_Time *offsetPT);

Table 4 – continued from previous page

Function	Purpose
AEGP_GetLayerStretch	Get stretch factor of a layer.
ALGP_GetLayerStretch	AEGP_LayerH layerH, A_Ratio *stretchPRt);
AEGP_SetLayerStretch	Set stretch factor of a layer.
	AEGP_SetLayerStretch(AEGP_LayerH layerH, A_Ratio *stretchPRt);
AEGP_GetLayerTransferMode	Get transfer mode of a layer.
	AEGP_GetLayerTransferMode(AEGP_LayerH layerH, AEGP_LayerTransferMode *modeP);
AEGP_SetLayerTransferMode	Set transfer mode of a layer. Undoable.
	AEGPSetLayerTransferMode(AEGP_LayerH layerH, AEGP_LayerTransferMode *modeP);
	As of 6.5, when you make a layer a track matte, the layer in front of it will be disabled, as when you do this via the interface.
AEGP_IsAddLayerValid	Tests whether it's currently valid to add a given item to a composition. A composition cannot be added to itself, or to any compositions which it contains; other conditions can preclude successful adding too. Adding a layer without first using this function will produce undefined results.
	AEGP_IsAddLayerValid(AEGP_ItemH item_to_addH, AEGP_CompH into_compH, A_Boolean *validPB);
AEGP_AddLayer	Add an item to the composition, above all other layers. Undo-able. Use AEGP_IsAddLayerValid() first, to confirm that it's possible.
	AEGP_AddLayer(AEGP_ItemH item_to_addH, AEGP_CompH into_compH, A_Boolean *added_layerPH0);
AEGP_ReorderLayer	Change the order of layers. Undoable.
	AEGP_ReorderLayer(AEGP_LayerH layerH, A_long layer_indexL);
	To add a layer to the end of the composition, to use layer_indexL = AEGP_REORDER_LAYER_TO_END Continued on next page

Table 4 – continued from previous page

Function	Purpose
AEGP_GetLayerMaskedBounds	Given a layer's handle and a time, returns the bounds of area visible with masks applied.
	AEGP_GetLayerMaskedBounds(AEGP_LayerH layerH, const A_Time *comp_timePT, A_FloatRect *boundsPR);
AEGP_GetLayerObjectType	Returns a layer's object type.
	AEGP_GetLayerObjectType(AEGP_LayerH layerH, AEGP_ObjectType *object_type); AEGP_ObjectType_AV AEGP_ObjectType_LIGHT, AEGP_ObjectType_CAMERA, AEGP_ObjectType_TEXT
AEGP_IsLayer3D	Is the footage item a 3D layer. All AV layers are either 2D or 3D.
	AEGP_IsLayer3D(AEGP_LayerH layerH, A_Boolean *is_3DPB);
AEGP_IsLayer2D	Is the footage item a 2D layer. All AV layers are either 2D or 3D.
	AEGP_IsLayer2D(AEGP_LayerH layerH, A_Boolean *is_2DPB);
AEGP_IsVideoActive	Given composition time and a layer, see if the layer will render. Time mode is either AEGP_LTimeMode_LayerTime or AEGP_LTimeMode_CompTime.
	AEGP_IsVideoActive(AEGP_LayerH layerH, AEGP_LTimeMode time_mode, A_Time *comp_timePT, A_Boolean *is_activePB);
AEGP_IsLayerUsedAsTrackMatte	Is the layer used as a track matte?
	AEGP_IsLayerUsedAsTrackMatte(AEGP_LayerH layerH, A_Boolean fill_must_be_activeB, A_Boolean *is_track_mattePB);
AEGP_DoesLayerHaveTrackMatte	Does this layer have a Track Matte?
	AEGP_DoesLayerHaveTrackMatte(AEGP_LayerH layerH, A_Boolean *has_track_mattePB);
	Continued on post page

Table 4 – continued from previous page

Function	Purpose
AEGP_ConvertCompToLayerTime	Given a time in composition space, returns the time rel-
Indi_converedomprelayerrime	ative to the layer source footage.
	AEGP_ConvertCompToLayerTime(
	AEGP_LayerH layerH,
	<pre>const A_Time *comp_timeP,</pre>
	A_Time *layer_timeP);
AEGP_ConvertLayerToCompTime	Given a time in layer space, find the corresponding time
	in composition space.
	AEGP_ConvertLayerToCompTime(
	AEGP_LayerH layerH,
	<pre>const A_Time *layer_timePT,</pre>
	A_Time *comp_timePT);
AEGP_GetLayerDancingRandValue	Used by the dancing dissolve transfer function.
	AEGP_GetLayerDancingRandValue(
	AEGP_LayerH layerH,
	<pre>const A_Time *comp_timePT,</pre>
	A_long *rand_valuePL);
AEGP_GetLayerID	Supplies the layer's unique ID. This ID never changes during the lifetime of the project.
	AEGP_GetLayerID(
	AEGP_LayerH layerH,
	AEGP_LayerIDVal *id_valP);
AEGP_GetLayerToWorldXform	Given a layer handle and time, returns the layer-to-
	world transformation matrix.
	AEGP_GetLayerToWorldXform(
	AEGP_LayerH aegp_layerH,
	<pre>const A_Time *comp_timeP,</pre>
	A_Matrix4 *transform);
AEGP_GetLayerToWorldXformFromView	Given a layer handle, the current (composition) time,
	and the requested view time, returns the translation be-
	tween the user's view and the layer, corrected for the
	composition's current aspect ratio.
	AEGP_GetLayerToWorldXformFromView(
	AEGP_LayerH aegp_layerH,
	<pre>const A_Time *view_timeP,</pre>
	<pre>const A_Time *comp_timeP,</pre>
	A_Matrix4 *transform);
AEGP_SetLayerName	Sets the name of a layer. Undo-able. new_nameZ points
_ 1	to a null terminated UTF-16 string.
	AEGP_SetLayerName(
	AEGP_LayerH aegp_layerH,
	<pre>const A_UTF16Char *new_nameZ);</pre>

Table 4 – continued from previous page

Function	Purpose
AEGP_GetLayerParent	Retrieves the handle to a layer's parent (none if not parented).
	AEGP_GetLayerParent(AEGP_LayerH layerH, AEGP_LayerH *parent_layerPH);
AEGP_SetLayerParent	Sets a layer's parent layer.
	AEGP_SetLayerParent(AEGP_LayerH layerH, const AEGP_LayerH parent_layerH);
AEGP_DeleteLayer	Deletes a layer. Can you believe it took us three suite versions to add a delete function? Neither can we. AEGP_DeleteLayer (
	AEGP_LayerH layerH);
AEGP_DuplicateLayer	Duplicates the layer. Undoable.
	AEGP_DuplicateLayer(AEGP_LayerH orig_layerH, AEGP_LayerH *dupe_layerPH);
AEGP_GetLayerFromLayerID	Retrieves the AEGP_LayerH associated with a given AEGP_LayerIDVal (which is what you get when accessing an effect's layer parameter stream).
	AEGP_GetLayerFromLayerID(AEGP_CompH parent_compH, AEGP_LayerIDVal id, AEGP_LayerH *layerPH);
AEGP_GetLayerLabel	Gets a layer's AEGP_LabelID.
	AEGP_GetLayerLabel(AEGP_LayerH layerH, AEGP_LabelID *labelP);
AEGP_SetLayerLabel	Sets a layer's AEGP_LabelID. Undoable.
	AEGP_SetLayerLabel(AEGP_LayerH layerH, AEGP_LabelID label);
AEGP_GetLayerSamplingQuality	New in CC. Get the sampling quality of a layer.
	AEGP_GetLayerSamplingQuality(AEGP_LayerH layerH, AEGP_LayerSamplingQuality *label);
	Layer sampling quality is one of the following flags: • AEGP_LayerSamplingQual_BILINEAR • AEGP_LayerSamplingQual_BICUBIC
<u> </u>	Continued on next page

Table 4 – continued from previous page

Function	Purpose
AEGP_SetLayerSamplingQuality	New in CC. Sets the sampling quality of a layer (see flag values above). Option is explicitly set on the layer independent of layer quality. If you want to force it on you must also set the layer quality to AEGP_LayerQual_BEST with AEGP_SetLayerQuality. Otherwise it will only be using the specified layer sampling quality whenever the layer quality is set to AEGP_LayerQual_BEST. Undoable.
	AEGP_SetLayerSamplingQuality(AEGP_LayerH layerH, AEGP_LayerSamplingQuality label);

64.11 Layer Creation Notes

All layers created using AEGP calls will start at composition time 0, and have the duration of the composition.

Use AEGP_SetLayerOffset() and AEGP_SetLayerInPointAndDuration() from AEGP_LayerSuite8 to properly set the layer's time information.

When the layer stretch factor (obtained using AEGP_GetLayerStretch in *AEGP_LayerSuite8*, naturally) is not 100%, the following computation will be needed to yield the correct layer offset:

```
offset = compIn - stretch * layerIn;
```

64.12 Communication With A Layer's Effects

Access the effects applied to a layer. This suite provides access to all parameter data streams.

Use the Stream Suite to work with those streams.

An AEGP_Effect_RefH is a reference to an applied effect. An AEGP_InstalledEffectKey is a reference to an installed effect, which may or may not be currently applied to anything.

If Foobarocity is applied to a layer twice, there will be two distinct AEGP_Effect_RefHs, but they'll both return the same AEGP_InstalledEffectKey.

64.12.1 AEGP_EffectSuite4

Function	Purpose
AEGP_GetLayerNumEffects	Get number of effects applied to a layer.
	AEGP_GetLayerNumEffects(AEGP_LayerH layerH, A_long *num_effectsPL);
AEGP_GetLayerEffectByIndex	Retrieves (by index) a reference to an effect applied to the layer.
	AEGP_GetLayerEffectByIndex(AEGP_PluginID aegp_plugin_id, AEGP_LayerH layerH, AEGP_EffectIndex effect_indexL, AEGP_EffectRefH *effectPH);
AEGP_GetInstalledKeyFromLayerEffect	Given an AEGP_EffectRefH, retrieves its associated AEGP_InstalledEffectKey.
	AEGP_GetInstalledKeyFromLayerEffect(AEGP_EffectRefH
AEGP_GetEffectParamUnionByIndex	Returns description of effect parameter. Do not use the value(s) in the ParamDef returned by this function (Use AEGP_GetNewStreamValue() instead); it's provided so AEGPs can access parameter defaults, checkbox names, and pop-up strings. Use AEGP_GetEffectNumParamStreams() from AEGP_StreamSuite5 to get the stream count, useful for determining the maximum param_index. The last parameter is optional;
	AEGP_GetEffectParamUnionByIndex(AEGP_PluginID aegp_plugin_id, AEGP_EffectRefH effectH, PF_ParamIndex param_index, PF_ParamType *param_typeP PF_ParamDefUnion *uP0);
AEGP_GetEffectFlags	Obtains the flags for the given AEGP_EffectRefH.
	AEGP_EffectFlags(AEGP_EffectRefH effect_refH, AEGP_EffectFlags *effect_flagsP); Flags will be a combination of the following: • AEGP_EffectFlags_NONE • AEGP_EffectFlags_ACTIVE • AEGP_EffectFlags_AUDIO_ONLY • AEGP_EffectFlags_AUDIO_TOO • AEGP_EffectFlags_MISSING
AEGP_SetEffectFlags	Sets the flags (enumerated above) for the given AEGP_EffectRefH, masked by a different set of effect flags. AEGP_SetEffectFlags(
	AEGP_EffectRefH effect_refH,
264	AEGP_EffectFlags Chapter 64. AEGP Suites effect_flags);
AEGP_ReorderEffect	Change the order of applied effects (pass the requested index).

64.13 Exploiting Effect UI Behavior To Look Cool

Even if you manipulate a layer's effects, its effect controls won't necessarily become visible.

However, if you apply then immediately remove an effect, the layer's effect controls will be made visible.

Tricky, eh?

64.14 StreamRefs And EffectRefs

How do you get an AEGP_StreamRef for an effect? Start by getting the effect's AEGP_EffectRef, by calling AEGP GetNewEffectForEffect().

Then call AEGP_GetNewEffectStreamByIndex(), say for param index 1, which passes back a parameter stream.

Then call AEGP_GetNewParentStreamRef() - voila, your AEGP_StreamRef sir!

If you acquire references to an effect's streams, do not dispose of the AEGP_EffectRefH until you're done with the streams, or you'll unbalance After Effects' checkout mechanism. Also remember that AEGP_StreamRefHs are opaque; AEGP_StreamValue2s are not (entirely).

To get an effect's instance name (as renamed by the user), get the AEGP_StreamRef for the effect itself and call AEGP_GetStreamName.

64.15 Diving Into Streams!

Just about everything in After Effects is a stream. Effect parameters, layers, masks, and shapes are all internally represented by streams. The AEGP API can access nearly every aspect of every stream.

The After Effects timeline can contain numerous object types; each object supports a set of parameters called streams. All streams, regardless of which type of object to which they're attached, are conceptually similar (and handled similarly by After Effects. But the way you access each type of stream varies because of their containment.

A stream, once acquired, represents a value which may change over time. Not all streams *can* vary over time, and a particular stream may not be time-variant at the time of access.

There are two ways to access the value of a stream. If the stream has keyframes, you can use the *Working With Keyframes*. The values provided won't reflect the influence of expressions. Note: In any expression, the current keyframed value is always available as the variable value.

You can also use AEGP_GetNewStreamValue from *AEGP_StreamSuite5*, which samples the value of the stream at a particular time. For streams without expressions or keyframes, the time parameter is meaningless, and the function returns what essentially is the constant value of the stream. Use AEGP_SetStreamValue (which doesn't take a time as a parameter) to set these streams.

Many StreamSuite functions populate a StreamH, which your AEGP must dispose. when done. After Effects allocates and passes you a copy of the values, not a direct handle to the original value. AEGP_GetNewLayerStream() is restricted to streams for which no memory allocation is required to access their values.

64.16 Okay, What Did I Just Get?

A stream value is a large union, only one structure of which (depending on the stream type) is populated. Note the similarity to the $PF_ParamDef$.

```
typedef union {
 AEGP_FourDVal
                      four_d;
 AEGP_ThreeDVal
                     three_d;
 AEGP_TwoDVal
                     two_d;
 AEGP_OneDVal
                     one_d;
 AEGP_ColorVal
                     color;
 AEGP_ArbBlockVal
                     arbH;
 AEGP_MarkerValP
                     markerP;
 AEGP_LayerIDVal
                    layer_id;
mask_id;
 AEGP_MaskIDVal
 AEGP_MaskOutlineValH mask;
 AEGP_TextDocumentH
                      text_documentH;
} AEGP_StreamVal2;
```

64.17 Layers

AEGP_GetLayerStreamValue is used to access the parameters like anchor point and position, native to almost all layers in AE.

Use IsStreamLegal to allow you to determine if that stream type is offered on that layer.

64.18 Masks

Since a layer can have multiple masks, access the masks using AEGP_GetLayerMaskByIndex from AEGP MaskSuite6.

Masks don't have streams like layers do; they get their own enumeration. Access their streams using AEGP_GetNewMaskStream from *AEGP_StreamSuite5*.

64.19 Effects

They can have a variable number of streams/parameters, and the order and definition of them is not known when the AEGP is written.

Therefore we cannot offer an enum for selecting them, and instead you must get them by index, hence $GetNewEffectStreamByIndex\ from\ AEGP_StreamSuite5$.

64.20 Stream Suite

Access and manipulate the values of a layer's streams. For paint and text streams, use *Dynamic Streams* instead.

64.20. Stream Suite 267

64.20.1 AEGP_StreamSuite5

Function	Purpose
AEGP_IsStreamLegal	Determines if the given stream is appropriate for the given layer.
	AEGP_IsStreamLegal(AEGP_LayerH layerH, AEGP_LayerStream which_stream, A_Boolean* is_legalP);
AEGP_CanVaryOverTime	Given a stream, returns whether or not a stream is time- variant (and can be keyframed).
	AEGP_CanVaryOverTime(AEGP_StreamRefH streamH, A_Boolean *can_varyPB);
AEGP_GetValidInterpolations	Retrieves an AEGP_KeyInterpolationMask indicating which interpolation types are valid for the AEGP_StreamRefH.
	AEGP_GetValidInterpolations(AEGP_StreamRefH streamH, AEGP_KeyInterpolationMask *valid_
	AEGP_KeyInterpolationMask will be a combination of the following: • AEGP_KeyInterpMask_NONE • AEGP_KeyInterpMask_LINEAR • AEGP_KeyInterpMask_BEZIER • AEGP_KeyInterpMask_HOLD • AEGP_KeyInterpMask_CUSTOM • AEGP_KeyInterpMask_ANY
AEGP_GetNewLayerStream	Get a layer's data stream. Plug-in must dispose of streamPH. Note that this will not provide keyframe access; Use the AEGP_KeyframeSuite instead.
	AEGP_GetNewLayerStream(AEGP_PluginID id, AEGP_LayerH layerH, AEGP_LayerStream which_stream, AEGP_StreamRefH *streamPH); • AEGP_LayerStream_ANCHORPOINT, • AEGP_LayerStream_POSITION, • AEGP_LayerStream_SCALE, • AEGP_LayerStream_ROTATION, • AEGP_LayerStream_ROTATE_Z, • AEGP_LayerStream_OPACITY, • AEGP_LayerStream_AUDIO, • AEGP_LayerStream_AUDIO, • AEGP_LayerStream_TIME_REMAP, • AEGP_LayerStream_TIME_REMAP, • AEGP_LayerStream_ROTATE_X, • AEGP_LayerStream_ROTATE_Y, • AEGP_LayerStream_ROTATE_Y, • AEGP_LayerStream_ORIENTATION Only valid for AEGP_ObjectType_CAMERA:
64.20. Stream Suite	 AEGP_ObjectType_CAMERA AEGP_LayerStream_ZOOM, AEGP_LayerStream_DEPTH_OF_FIELD 26 AEGP_LayerStream_FOCUS_DISTANCE, AEGP_LayerStream_APERTURE,

• AEGP_LayerStream_BLUR_LEVEL,

64.21 Dynamic Streams

AEGP_DynamicStreamSuite accesses and manipulates paint and text streams.

Use AEGP_GetStreamGroupingType and AEGP_GetDynamicStreamFlags to identify the stream before attempting to use functions which only work on certain stream types.

Also note that, often, you can simply use *Stream Suite* calls to work with dynamic streams. On the other hand, only those functions specific to dynamic streams are in this suite.

64.21.1 AEGP_DynamicStreamSuite4

Function	Purpose
AEGP_GetNewStreamRefForLayer	Retrieves the AEGP_StreamRefH corresponding to the layer. This function is used to initiate a recursive walk of the layer's streams.
	AEGP_GetNewStreamRefForLayer(AEGP_PluginID aegp_plugin_id, AEGP_LayerH layerH, AEGP_StreamRefH *streamPH);
AEGP_GetNewStreamRefForMask	Retrieves the AEGP_StreamRefH corresponding to the mask. AEGP_GetNewStreamRefForMask(AEGP_PluginID aegp_plugin_id, AEGP_MaskRefH maskH, AEGP_StreamRefH *streamPH);
AEGP_GetStreamDepth	Retrieves the number of sub-streams associated with the given AEGP_StreamRefH. The initial layer has a depth of 0. AEGP_GetStreamDepth(AEGP_StreamRefH streamH, A_long *depthPL);
AEGP_GetStreamGroupingType	Retrieves the grouping type for the given AEGP_StreamRefH. AEGP_GetStreamGroupingType(AEGP_StreamGroupingType *group_typeP); AEGP_StreamGroupingType will be one of the following: • AEGP_StreamGroupingType_NONE • AEGP_StreamGroupingType_LEAF • AEGP_StreamGroupingType_LEAF • AEGP_StreamGroupingType_NAMED_GROUPINGTYPE_INDEXED_GROUPINGTYPE_INDE
AEGP_GetNumStreamsInGroup	Retrieves the number of streams associated with the given AEGP_StreamRefH. This function will return an error if called with an AEGP_StreamRefH with type AEGP_StreamGroupingType_LEAF. AEGP_GetNumStreamsInGroup(AEGP_StreamRefH streamH, A_long *num_streamsPL);
AEGP_GetDynamicStreamFlags	Retrieves the flags for a given AEGP_StreamRefH. AEGP_GetDynamicStreamFlags (AEGP_StreamRefH streamH, AEGP_DynStreamFlags *flagsP); AEGP_DynStreamFlags will be one of the following: • AEGP_DynStreamFlag_ACTIVE_EYEBALL means that the stream is available for reading and writing. • AEGP_DynStreamFlag_HIDDEN means that,
272	while the stream is schapterbedwrater is not currently be visible in the UI. • AEGP_DynStreamFlag_DISABLED A read-only flag Indicates whether the

A read-only flag. Indicates whether the

64.22 Working With Keyframes

Keyframes make After Effects what it is. AEGPs (and...ssshh, don't tell anyone...effects) can use this suite to add, manipulate and remove keyframes from any keyframe-able stream.

64.22.1 AEGP_KeyframeSuite3

Function	Purpose
AEGP_GetStreamNumKFs	Retrieves the number of keyframes on the given stream. Returns AEGP_NumKF_NO_DATA if the stream is not keyframe-able. Also, note that a stream without keyframes isn't necessarily constant; it can be altered by expressions.
	AEGP_GetStreamNumKFs(AEGP_StreamRefH streamH, A_long *num_kfsPL);
AEGP_GetKeyframeTime	Retrieves the time of the specified keyframe.
	AEGP_GetKeyframeTime(AEGP_StreamRefH streamH, AEGP_KeyframeIndex index, AEGP_LTimeMode time_mode, A_Time *timePT);
AEGP_InsertKeyframe	Adds a keyframe to the specified stream (at the specified composition or layer time). Returns the new keyframe's index. All indexes greater than the new index are now invalid (but you knew that). If there is already a keyframe at that time, the values will be updated.
	AEGP_InsertKeyframe(AEGP_StreamRefH streamH, AEGP_LTimeMode time_mode, const A_Time *timePT, AEGP_KeyframeIndex *key_indexP);
AEGP_DeleteKeyframe	Deletes the specified keyframe.
	AEGP_DeleteKeyframe(AEGP_StreamRefH streamH, AEGP_KeyframeIndex key_index);
AEGP_GetNewKeyframeValue	Creates and populates an AEGP_StreamValue2 for the stream's value at the time of the keyframe. The returned AEGP_StreamValue2 must be disposed of using AEGP_DisposeStreamValue.
	AEGP_GetNewKeyframeValue(AEGP_PluginID plugin_id, AEGP_StreamRefH streamH, AEGP_KeyframeIndex key_index, AEGP_StreamValue2 *valueP);
AEGP_SetKeyframeValue	Sets the stream's value at the time of the keyframe.
	AEGP_SetKeyframeValue(AEGP_StreamRefH streamH, AEGP_KeyframeIndex index, const AEGP_StreamValue2 *valP);
AEGP_GetStreamValueDimensionality	Retrieves the dimensionality of the stream's value.
	AEGP_GetStreamValueDimensionality(AEGP_StreamRefH streamH, A_short *value_dimPS);
AEGP GetStreamTemporalDimensionality 64.22. Working With Keyframes	Retrieves the temporal dimensionality of the stream.
	AEGP_GetStreamTemporalDimensionality(AEGP_StreamRefH streamH,

A_short

 $*t_dimPS);$

64.23 Adding Multiple Keyframes

Each time you call AEGP_InsertKeyframe(), the entire stream is added to the undo stack.

If you're adding one or two keyframes, this isn't a problem. However, if you're writing a keyframer, you'll want to do things the *right* way.

Before you begin adding keyframes, call the (very-appropriately-named) AEGP_StartAddKeyframes, passing it an opaque AEGP_AddKeyframesInfoH.

For each keyframe to add, call AEGP_AddKeyframes to set the time to be used (and get the newly-added keyframe's index), then AEGP_SetAddKeyframe to specify the value to be used.

Once you're finished, call AEGP_EndAddKeyframes to let know After Effects know it's time to add the changed parameter stream to the undo stack.

64.24 Marker Streams

AEGP_MarkerSuite allows for direct manipulation of marker data.

64.24. Marker Streams 277

64.24.1 AEGP_MarkerSuite2

Function	Purpose
AEGP_NewMarker	Creates a new marker.
	AEGP_NewMarker(
	AEGP_MarkerValP *markerPP);
AEGP_DisposeMarker	Disposes of a marker.
	AEGP_DisposeMarker(
	AEGP_MarkerValP markerP);
AEGP_DuplicateMarker	Duplicates a marker (didn't see <i>that</i> one coming, eh?).
	AEGP_DuplicateMarker(
	AEGP_MarkerValP markerP,
	AEGP_MarkerValP *new_markerP);
AEGP_SetMarkerFlag	Sets a marker flag's value.
	AEGP_SetMarkerFlag(
	AEGP_MarkerValP markerP,
	AEGP_MarkerFlagType flagType, A_Boolean valueB);
	Currently, AEGP_MarkerFlagType is one of the follow-
	ing:
	• AEGP_MarkerFlag_NONE
	• AEGP_MarkerFlag_NAVIGATION
AEGP_GetMarkerFlag	Gets the value (see above) of a given
	AEGP_MarkerFlagType.
	AEGP_GetMarkerFlag(
	AEGP_ConstMarkerValP markerP,
	AEGP_MarkerFlagType flagType
	A_Boolean *valueBP);
AEGP_GetMarkerString	Retrieves the UTF-16, NULL-terminated string located
	in the specified marker field. Must be disposed of by
	caller using AEGP_FreeMemHandle.
	AEGP_GetMarkerString(
	AEGP_PluginID id, AEGP_ConstMarkerValP markerP,
	AEGP_MarkerStringType strType,
	AEGP_MemHandle *unicodePH);
AEGP_SetMarkerString	Sets the specified field of a marker to the provided text.
	AEGP_SetMarkerString(
	AEGP_MarkerValP markerP,
	AEGP_MarkerStringType strType,
	<pre>const A_u_short</pre>
	A_long lengthL);
AEGP_CountCuePointParams	Returns the number of cue point parameters.
	AEGP_CountCuePointParams(
	AEGP_ConstMarkerValP markerP,
	A_long *paramsLP);
AEGP_GetIndCuePointParam	Returns the cue point param at the specified in-
278	dex (which must be between 0 and (cue point params -1). Returned Condition 64.7 AEGPNS Wifes
LIU	terminated strings, and must be disposed of by caller
	using AEGP_FreeMemHandle.

AEGP_GetIndCuePointParam(

64.25 Mask Management

Access, manipulate, and delete a layer's masks.

64.25.1 AEGP_MaskSuite6

Function	Purpose
AEGP_GetLayerNumMasks	Counts the masks applied to a layer,
	AEGP_GetLayerNumMasks(AEGP_LayerH aegp_layerH, A_long *num_masksPL);
AEGP_GetLayerMaskByIndex	Given a layer handle and mask index, returns a pointer to the mask handle. You must destroy the mask handle by using AEGP_DisposeMask().
	AEGP_GetLayerMaskByIndex(AEGP_LayerH aegp_layerH, A_long mask_indexL, AEGP_MaskRefH *maskPH);
AEGP_DisposeMask	Dispose of a mask handle.
	AEGP_DisposeMask(AEGP_MaskRefH maskH);
AEGP_GetMaskInvert	Given a mask handle, determines if the mask is inverted or not.
	AEGP_GetMaskInvert(AEGP_MaskRefH maskH, A_Boolean *invertPB);
AEGP_SetMaskInvert	Sets the inversion state of a mask.
	AEGP_SetMaskInvert(AEGP_MaskRefH mask_refH, A_Boolean invertB);
AEGP_GetMaskMode	Given a mask handle, returns the current mode of the mask. PF_MaskMode_NONE does nothing, PF_MaskMode_ADD is the default behavior. • PF_MaskMode_NONE • PF_MaskMode_ADD, • PF_MaskMode_SUBTRACT, • PF_MaskMode_INTERSECT, • PF_MaskMode_INTERSECT, • PF_MaskMode_LIGHTEN, • PF_MaskMode_DARKEN, • PF_MaskMode_DIFFERENCE, AEGP_GetMaskMode(AEGP_MaskRefH maskH, PF_MaskMode *modeP);
AEGP_SetMaskMode	Sets the mode of the given mask. AEGP_SetMaskMode(AEGP_MaskRefH maskH, PF_MaskMode mode);
AEGP_GetMaskMotionBlurState	Retrieves the motion blur setting for the given mask.
	AEGP_GetMaskMotionBlurState(AEGP_MaskRefH mask_refH, AEGP_MaskMBlur *blur_stateP);
64.25. Mask Management	AEGP_MaskMBlur will be one of the following: • AEGP_MaskMBlur_SAME_AS_LAYER

64.26 Mask Outlines

The Mask Suite above tells plug-ins about the masks on a layer, but not about the details of those masks.

This is because processing is required on After Effects' part to access the information; the information isn't just lying around.

Plug-ins access that information using this Mask Outline Suite.

64.26. Mask Outlines 283

64.26.1 AEGP_MaskOutlineSuite3

Function	Purpose
AEGP_IsMaskOutlineOpen	Given an mask outline pointer (obtainable through the <i>Stream Suite</i>), determines if the mask path is open or
	closed.
	AEGP_IsMaskOutlineOpen(
	AEGP_MaskOutlineVal *mask_outlineP, A_Boolean *openPB);
AEGP_SetMaskOutlineOpen	Sets the open state of the given mask outline.
	AEGP_SetMaskOutlineOpen(AEGP_MaskOutlineValH mask_outlineH, A_Boolean openB);
AEGP_GetMaskOutlineNumSegments	Given a mask outline pointer, returns the number of segments in the path. num_segmentsPL is the total number of segments [0N-1].
	AEGP_GetMaskOutlineNumSegments(AEGP_MaskOutlineVal *mask_outlineP, A_long *num_segmentsPL);
AEGP_GetMaskOutlineVertexInfo	Given a mask outline pointer and a point between 0 and the total number of segments. For closed mask paths, vertex[0] is the same as vertex[num_segments].
	AEGP_GetMaskOutlineVertexInfo(AEGP_MaskOutlineVal *mask_outlineP, A_long which_pointL, AEGP_MaskVertex *vertexP);
AEGP_SetMaskOutlineVertexInfo	Sets the vertex information for a given index. Setting vertex 0 is special; its in tangent will actually set the out tangent of the last vertex in the outline. Of course, which_pointL must be valid for the mask outline, or the function will return an error.
	AEGP_MaskOutlineVertexInfo(AEGP_MaskOutlineValH mask_outlineH, AEGP_VertexIndex which_pointL, AEGP_MaskVertex *vertexP);
AEGP_CreateVertex	Creates a vertex at index position. All vertices which formerly had an AEGP_VertexIndex of position or greater will have their indices incremented by one.
	AEGP_CreateVertex(AEGP_MaskOutlineValH mask_outlineH, AEGP_VertexIndex position);.
ATION Delahaman	NOTE: All masks must have at least one vertex.
AEGP_DeleteVertex	Removes a vertex from a mask. AEGP_DeleteVertex(
	AEGP_MaskOutlineValH mask_outlineH, AEGP_VertexIndex index);
AEGP_GetMaskOutlineNumFeathers	New in CS6. AEGP_DeleteVertex(
284	AEGP_MaskOutlineValH mask_outlineH, A_long Chapten64feAteGPsSuites
	New in CS6.
AEGP_GetMaskOutlineFeatherInfo	
	AEGP_GetMaskOutlineFeatherInfo(

64.27 Mask Feathering

New for CS6, masks can be feathered.

AEGP_MaskFeather is defined as follows:

```
typedef struct {
 A_long
                           segment;
                                             // mask segment where feather is
 PF_FpLong
                          segment_sF;
                                             // 0-1: feather location on segment
 PF_FpLong
                          radiusF;
                                             // negative value allowed if type == AEGP_
\hookrightarrow MaskFeatherType_INNER
                          ui_corner_angleF; // 0-1: angle of UI handle on corners
 PF_FpShort
                                             // 0-1: tension of boundary at feather pt
 PF_FpShort
                          tensionF;
  AEGP_MaskFeatherInterp interp;
  AEGP_MaskFeatherType
                          type;
} AEGP_MaskFeather;
```

```
AEGP_MaskFeatherInterp is either AEGP_MaskFeatherInterp_NORMAL or AEGP_MaskFeatherInterp_HOLD_CW.

AEGP_MaskFeatherType is either AEGP_MaskFeatherType_OUTER or AEGP_MaskFeatherType_INNER.
```

This suite enables AEGPs to get and set the text associated with text layers.

Note: to get started, retrieve an AEGP_TextDocumentH by calling AEGP_GetLayerStreamValue, above, and passing AEGP_StreamType_TEXT_DOCUMENT as the AEGP_StreamType.

64.28 Working With Text Layers

This suite enables AEGPs to get and set the text associated with text layers.

64.28.1 AEGP_TextDocumentSuite1

Function	Purpose
AEGP_GetNewText	Retrieves the UTF-16, NULL-terminated string used in the AEGP TextDocumentH.
	Note: After Effects will allocate the AEGP_MemHandle; your plug-in must dispose
	of it when done using AEGP_FreeMemHandle. AEGP_GetNewText(AEGP_PluginID id, AEGP_TextDocumentH text_docH, AEGP_MemHandle *unicodePH);
AEGP_SetText	Specifies the text to be used by the AEGP_TextDocumentH. AEGP_SetText(AEGP_TextDocumentH text_docH, const A_u_short *unicodePS, long lengthL);

64.29 Working With Text Outlines

The AEGP_TextLayerSuite provides access to the actual outlines of the text used by text layers.

Once you have a path, you can manipulate it with PF_PathQuerySuite1 and PF_PathDataSuite.

64.29.1 AEGP_TextLayerSuite1

Function	Purpose
AEGP_GetNewTextOutlines	Allocates and returns a handle to the AEGP_TextOutlinesHs associated with the specified layer. outlinesPH will be NULL if there are no AEGP_TextOutlinesHs associated with layerH (in other words, if it's not a text layer). AEGP_GetNewTextOutlines(AEGP_LayerH layerH, const A_Time *layer_timePT, AEGP_TextOutlinesH *outlinesPH);
AEGP_DisposeTextOutlines	Dispose of those outlines we allocated on your behalf! AEGP_DisposeTextOutlines(AEGP_TextOutlinesH outlinesH);
AEGP_GetNumTextOutlines	Retrieves the number of text outlines for the layer. AEGP_GetNumTextOutlines(AEGP_TextOutlinesH outlinesH, A_long *num_otlnsPL);
AEGP_GetIndexedTextOutline	Returns a PF_PathOutlinePtr for the specifed text outline. AEGP_GetIndexedTextOutline(AEGP_TextOutlinesH outlinesH, A_long path_indexL, PF_PathOutlinePtr *pathPP);

64.30 Utility Functions

The Utility suite supplies error message handling, AEGP version checking and access to the undo stack. Everything you need to keep After Effects and your plug-in tidy.

64.30.1 AEGP_UtilitySuite6

Function	Purpose
AEGP_ReportInfo	Displays dialog with name of the AEGP followed by the string passed.
	AEGP_ReportInfo(AEGP_PluginID aegp_plugin_id, const A_char *info_stringZ);

Table 5 – continued from previous page

	inued from previous page
Function	Purpose
AEGP_ReportInfoUnicode	New in CC. Displays dialog with name of the AEGP followed by the unicode string passed. AEGP_ReportInfoUnicode(AEGP_PluginID
AEGP_GetDriverSpecVersion	Returns version of AEGPDriver plug-in (use to determine supported features). AEGP_GetDriverSpecVersion(A_short *major_versionPS, A_short *minor_versionPS);
AEGP_StartQuietErrors	Silences errors. Must be balanced with AEGP_EndQuietErrors. The AEGP_ErrReportState is an opaque structure private to After Effects. AEGP_StartQuietErrors(AEGP_ErrReportState *err_stateP);
AEGP_EndQuietErrors	Re-enables errors. AEGP_EndQuietErrors(AEGP_ErrReportState *err_stateP)
AEGP_StartUndoGroup	Add action(s) to the undo queue. The user may undo any actions between this and AEGP_EndUndoGroup(). The undo_nameZ will appear in the edit menu. AEGP_StartUndoGroup(const A_char *undo_nameZ);
AEGP_EndUndoGroup	Ends the undo list. AEGP_EndUndoGroup();
AEGP_RegisterWithAEGP	Returns an AEGP_PluginID, which effect plug-ins can then use in calls to many functions throughout the AEGP API. Effects should only call this function once, during PF_Cmd_GLOBAL_SETUP, and save the AEGP_PluginID for later use. The first parameter can be any value, and the second parameter should be the plug-in's match name. AEGP_RegisterWithAEGP(AEGP_GlobalRefcon global_refcon,
AECD Cat Main HUMD	const A_char
AEGP_GetMainHWND	Retrieves After Effects' HWND; useful when displaying your own dialog on Windows. If you don't use After Effects' HWND, your modal dialog will not prevent interaction with the windows behind, and pain will ensue. AEGP_GetMainHWND (
	<pre>void *main_hwnd);</pre>

Table 5 – continued from previous page

Function	Purpose
AEGP_ShowHideAllFloaters	Toggles whether or not floating palettes are displayed. Use this with care; users get twitchy when you unexpectedly change the UI on them.
	AEGP_ShowHideAllFloaters(A_Boolean include_tool_palB);
AEGP_PaintPalGetForeColor	Retrieves the foreground color from the paint palette.
	AEGP_PaintPalGetForeColor(AEGP_ColorVal *fore_colorP);
AEGP_PaintPalGetBackColor	Retrieves the background color from the paint palette.
	AEGP_PaintPalGetBackColor(AEGP_ColorVal *back_colorP);
AEGP_PaintPalSetForeColor	Sets the foreground color in the paint palette.
	<pre>AEGP_PaintPalSetForeColor(const AEGP_ColorVal *fore_colorP);</pre>
AEGP_PaintPalSetBackColor	Sets the background color in the paint palette.
	<pre>AEGP_PaintPalSetBackColor(const AEGP_ColorVal *back_colorP);</pre>
AEGP_CharPalGetFillColor	Retrieves the fill color from the character palette.
	AEGP_CharPalGetFillColor(A_Boolean
AEGP_CharPalGetStrokeColor	Retrieves the stroke color from the character palette.
	AEGP_CharPalGetStrokeColor(A_Boolean
AEGP_CharPalSetFillColor	Sets the fill color in the character palette.
	<pre>AEGP_CharPalSetFillColor(const AEGP_ColorVal *fill_colorP);</pre>
AEGP_CharPalSetStrokeColor	Sets the stroke color in the character palette.
	AEGP_CharPalSetStrokeColor(const AEGP_ColorVal *stroke_colorP);
AEGP_CharPalIsFillColorUIFrontmost	Returns whether or not the fill color is frontmost. If it isn't, the stroke color is frontmost.
	AEGP_CharPalIsFillColorUIFrontmost(A_Boolean *is_fcolor_selectedPB);
AEGP_ConvertFpLongToHSFRatio	Returns an A_Ratio interpretation of the given A_FpLong. Useful for horizontal scale factor interpretation.
	AEGP_ConvertFpLongToHSFRatio(
	A_FpLong numberF, A_Ratio *ratioPR); Continued on payt page

Table 5 – continued from previous page

Function	Purpose
AEGP_ConvertHSFRatioToFpLong	Returns an A_FpLong interpretation of the given A_Ratio. Useful for horizontal scale factor interpretation. AEGP_ConvertHSFRatioToFpLong(A_Ratio ratioR, A_FpLong *numberPF);
AEGP_CauseIdleRoutinesToBeCalled	This routine is safe to call from threads other than the main thread. It is asynchronous and will return before the idle handler is called. The suite functions to get this function pointer are not thread safe; save it off in the main thread for use by the child thread. AEGP_CauseIdleRoutinesToBeCalled(void);
AEGP_GetSuppressInteractiveUI	Returns whether After Effects is running without a user interface. AEGP_GetSuppressInteractiveUI(A_Boolean *ui_is_suppressedPB);
AEGP_WriteToOSConsole	Sends a string to the OS console. AEGP_WriteToOSConsole(const A_char *textZ);
AEGP_WriteToDebugLog	Writes a message to the debug log, or to the OS command line if After Effects was launched with the "debug" option. AEGP_WriteToDebugLog(const A_char *subsystemZ, const A_char *event_typeZ, const A_char *infoZ);
AEGP_GetLastErrorMessage	Retrieves the last error message displayed to the user, and its associated error number. Pass in the size of the character buffer to be returned. AEGP_GetLastErrorMessage(A_long buffer_size, A_char *error_string, A_Err *error_num);
AEGP_IsScriptingAvailable	Returns TRUE if scripting is available to the plug-in. AEGP_IsScriptingAvailable(A_Boolean *outAvailablePB);

Table 5 – continued from previous page

Function	Purpose
AEGP_ExecuteScript	Have After Effects execute a script. The script passed in can be in either UTF-8 or the current application encoding (if platform_encodingB is passed in as TRUE). The two out arguments are optional. The value of the last line of the script is what is passed back in outResultPHO. AEGP_ExecuteScript(AEGP_PluginID inPlugin_id, const A_char *inScriptZ, const A_Boolean platform_encodingB, AEGP_MemHandle *outResultPHO, AEGP_MemHandle *outErrStringPHO);
AEGP_HostIsActivated	Returns TRUE if the user has successfully activated After Effects. AEGP_HostIsActivated(A_Boolean *is_activatedPB);
AEGP_GetPluginPlatformRef	On macOS, returns a CFBundleRef to your Mach-O plug-in, or NULL for a CFM plug-in. Always returns NULL on Windows (you can use an OS-specific entry point to capture your DLLInstance). AEGP_GetPluginPlatformRef(AEGP_PluginID plug_id, void **plat_refPPV);
AEGP_UpdateFontList	Rescans the system font list. AEGP_UpdateFontList();
AEGP_GetPluginPaths	New in CC. Returns a particular path associated with the plug-in: • AEGP_GetPathTypes_PLUGIN - (Not Implemented) The path to the location of the plug-in itself. • AEGP_GetPathTypes_USER_PLUGIN - The suite specific location of user specific plug-ins. • AEGP_GetPathTypes_ALLUSER_PLUGIN - The suite specific location of plug-ins shared by all users. • AEGP_GetPathTypes_APP - The After Effects .exe or .app location. Not plug-in specific. AEGP_GetPluginID
	AEGP_PluginID aegp_plugin_id, AEGP_GetPathTypes path_type AEGP_MemHandle *unicode_pathPH);

64.31 Persistent Data Suite

Plug-ins have read and write access to persistent data in After Effects' preferences. AEGPs may add and manage their own persistent data using the following suite. The data entries are accessed by (section key, value key) pairs. It is recommended that plug-ins use their matchname as their section key, or as a prefix if using multiple section keys.

The available data types are A_long, A_FpLong, strings, and void*. A_FpLongs are stored with 6 decimal places of precision. There is no provision for specifying a different precision. String data supports the full 8-bit space. Only 0x00 is reserved for string ending. This makes them ideal for storing UTF-8 encoded strings, ISO 8859-1, and plain ASCII. Both section keys and value keys are of this type. For data types not represented by the simple data types provided, use data handles containing your custom data. void* unstructured data allows you to store any kind of data. You must pass in a size in bytes along with the data.

When calling any of the functions to retrieve the value of a key, if a given key is not found, the default value is both written to the blob and returned as the value; if no default is provided, a blank value will be written and returned.

Note that this data is stored in the application's preferences, not in the project. As of 6.5, there is no way to store opaque AEGP-generated data in an After Effects project.

After Effects can handle plug-ins which change the preferences during their application; it checks the in-RAM copy of the prefs before acting upon pref-able settings, rather than relying on the saved prefs. It's like we *planned* this, or something!

64.31.1 AEGP_PersistentDateSuite4

Function	Purpose
AEGP_GetApplicationBlob	Obtains the handle to all persistent application data.
	Modifying this will modify the application.
	The AEGP_PersistentType parameter is new in
	CC, and should be set to one of the following:
	 AEGP_PersistentType_MACHINE_SPECIFIC,
	 AEGP_PersistentType_MACHINE_INDEPENDENT,
	 AEGP_PersistentType_MACHINE_INDEPENDENT_RENDE
	 AEGP_PersistentType_MACHINE_INDEPENDENT_OUTPU
	• AEGP_PersistentType_MACHINE_INDEPENDENT_COMPC
	 AEGP_PersistentType_MACHINE_SPECIFIC_TEXT,
	 AEGP_PersistentType_MACHINE_SPECIFIC_PAINT
	AEGP_GetApplicationBlob(
	AEGP_PersistentType blob_type,
	AEGP_PersistentBlobH *blobPH);
AEGP_GetNumSections	Obtains the number of sections in the application blob.
	AEGP_GetNumSections(
	AEGP_PersistentBlobH blobH, A_long *num_sectionPL);
AEGP_GetSectionKeyByIndex	Obtains the key at the given index.
	AEGP_GetSectionKeyByIndex(
	AEGP_PersistentBlobH blobH,
	A_long section_index,
	A_long max_section_size,
	A_char *section_keyZ);
AEGP_DoesKeyExist	Returns whether or not a given key/value pair exists with
	the blob.
	AEGP_DoesKeyExist(
	AEGP_PersistentBlobH blobH,
	<pre>const A_char *section_keyZ,</pre>
	const A_char *value_keyZ,
	A_Boolean *existsPB);
AEGP_GetNumKeys	Retrieves the number of value keys in the section.
	AEGP_GetNumKeys(
	AEGP_PersistentBlobH blobH,
	<pre>const A_char *section_keyZ,</pre>
	A_long *num_keysPL);
AEGP_GetValueKeyByIndex	Retrieves the value of the indexed key.
	AEGP_GetValueKeyByIndex(
	AEGP_PersistentBlobH blobH,
	const A_char *section_keyZ,
	A_long key_index,
	A_long max_key_size,
	A_char *value_keyZ);

Note: For the functions below, if a given key is not found, the default value is both written to the blob and returned

as the value; if no default is provided, a blank value will be written and returned.

Function	Purpose
AEGP_GetDataHandle	Obtains the value associated with the given section's
	key. If using in-memory data structures, watch for en-
	dian issues.
	AEGP_GetDataHandle(
	AEGP_PluginID plugin_id,
	AEGP_PersistentBlobH blobH,
	const A_char *section_keyZ,
	const A_char *value_keyZ,
	AEGP_MemHandle defaultH0, AEGP_MemHandle *valuePH);
AEGP_GetData	Obtains the data located at a given section's value.
1101 <u>-</u> 00 cD a c a	
	AEGP_GetData(
	AEGP_PersistentBlobH blobH,
	const A_char *section_keyZ,
	const A_char *value_keyZ, A_u_long data_sizeLu,
	const void *defaultPV0,
	void *bufPV);
	,,
AEGP_GetString	Obtains the string for a given section key's value (and
	indicates its length in actual_szLu0).
	AEGP_GetString(
	AEGP_PersistentBlobH blobH,
	<pre>const A_char *section_keyZ,</pre>
	<pre>const A_char *value_keyZ,</pre>
	<pre>const A_char *defaultZ0,</pre>
	A_u_long buf_sizeLu,
	char *bufZ,
	A_u_long *actual_szLu0);
AEGP_GetLong	Obtains the A_long associated with a given section
	key's value.
	AEGP_GetLong(
	AEGP_PersistentBlobH blobH,
	<pre>const A_char *section_keyZ,</pre>
	<pre>const A_char *value_keyZ,</pre>
	A_long defaultL,
	A_long *valuePL);
AEGP_GetFpLong	Obtains the A_FpLong associated with a given section
mor_occi prong	key's value.
	AEGP_GetFpLong(
	AEGP_PersistentBlobH blobH, const A_char *section_keyZ,
	const A_char *section_keyZ, const A_char *value_keyZ,
	A_FpLong defaultF,
	A_FpLong
AEGP_GetTime	New in CC. Obtains the A_Time associated with a
	given section key's value.
	AEGP_GetTime(
	AEGP_PersistentBlobH blobH,
	<pre>const A_char *section_keyZ,</pre>
	const A_char *value_keyZ,
	<pre>const A_Time *defaultPT0,</pre>
I.31. Persistent Data Suite	A_Time *valuePT); 29
AEGP_GetARGB	New in CC. Obtains the PF_PixelFloat associated
JEGI _GECANOD	with a given section key's value.
	with a given section key's value.

AEGP Get ARGR (

64.32 Color Management

We've provided a function so AEGPs can obtain information on After Effects' current color management settings.

64.32.1 AEGP_ColorSettingsSuite2

Function	Purpose
AEGP_GetBlendingTables	Retrieves the current opaque
	PF_EffectBlendingTables, for use with AEGP_TransferRect.
	AEGP_GetBlendingTables(PR_RenderContextH render_ →contextH, PF_EffectBlendingTables *blending_
	→tables);
AEGP_DoesViewHaveColorSpaceXform	Returns whether there is a colorspace transform applied to the current item view.
	AEGP_DoesViewHaveColorSpaceXform(AEGP_ItemViewP viewP, A_Boolean *has_xformPB);
AEGP_XformWorkingToViewColorSpace	Changes the view colorspace of the source to be the working colorspace of the destination. Source and destination can be the same.
	AEGP_XformWorkingToViewColorSpace(AEGP_ItemViewP viewP, AEGP_WorldH srcH, AEGP_WorldH dstH);
AEGP_GetNewWorkingSpaceColorProfile	Retrieves the opaque current working space ICC profile. Must be disposed. The "New" in the name does not indicate that you're making up a new profile; rather, it's part of our function naming standard; nything with "New" in the name allocates something which the caller must dispose.
	AEGP_GetNewWorkingSpaceColorProfile(AEGP_PluginID aegp_plugin_id, AEGP_MemHandle *icc_profPH);
AEGP_GetNewColorProfileFromICCProfile	Retrieves a new AEGP_ColorProfileP from After Effects, representing the specified ICC profile. The caller must dispose of the returned AEGP_ColorProfileP using AEGP_DisposeColorProfile().
	AEGP_GetNewColorProfile FromICCProfile(AEGP_PluginID aegp_plugin_id, A_long icc_sizeL, const void *icc_dataPV, AEGP_ColorProfileP *profilePP);
AEGP_GetNewICCProfileFromColorProfile	Retrieves a new ICC profile (stored in an AEGP_MemHandle) representing the specified color profile. Returned AEGP_MemHandle must be disposed by the caller.
	AEGP_GetNewICCProfile FromColorProfile(AEGP_PluginID plugin_id, AEGP_ConstColorProfileP profileP, AEGP_MemHandle *profilePH);
AEGP_GetNewColorProfileDescription 298	Returns a textual description of the specified color profile. Text will be a null-terichapter 64 6 AFGE, Suites must be disposed by the caller.
	AEGP_GetNewColorProfileDescription(

AEGP PluginID

64.33 Render Suites

Since we introduced the AEGP API, we've been asked to provide functions for retrieving rendered frames.

These function suites allows you to do just that.

First, specify what you want rendered in the AEGP_RenderOptionsSuite4 or AEGP_LayerRenderOptionsSuite1.

Then do the rendering with AEGP_RenderSuite4.

64.33. Render Suites 299

64.33.1 AEGP_RenderOptionsSuite4

Function	Purpose
AEGP_NewFromItem	Returns the AEGP_RenderOptionsH associated with a given AEGP_ItemH. If there are no options yet specified, After Effects passes back an AEGP_RenderOptionsH with render time set to 0, time step set to the current frame duration, field render set to PF_Field_FRAME, and the depth set to the highest resolution specified within the item.
	AEGP_NewFromItem(AEGP_PluginID plugin_id, AEGP_ItemH itemH, AEGP_RenderOptionsH *optionsPH);
AEGP_Duplicate	Duplicates an AEGP_RenderOptionsH into copyPH.
	AEGP_Duplicate(AEGP_PluginID plugin_id, AEGP_RenderOptionsH optionsH, AEGP_RenderOptionsH *copyPH);
AEGP_Dispose	Deletes an AEGP_RenderOptionsH.
	AEGP_Dispose(AEGP_RenderOptionsH optionsH);
AEGP_SetTime	Sets the render time of an AEGP_RenderOptionsH.
	AEGP_SetTime(AEGP_RenderOptionsH optionsH, A_Time time);
AEGP_GetTime	Retrieves the render time of the given AEGP_RenderOptionsH.
	AEGP_GetTime(AEGP_RenderOptionsH optionsH, A_Time *timeP);
AEGP_SetTimeStep	Specifies the time step (duration of a frame) for the referenced AEGP_RenderOptionsH.
	AEGP_SetTimeStep(AEGP_RenderOptionsH optionsH, A_Time
AEGP_GetTimeStep	Retrieves the time step (duration of a frame) for the given AEGP_RenderOptionsH.
	AEGP_GetTimeStep(AEGP_RenderOptionsH optionsH, A_Time *timePT);
AEGP_SetFieldRender	Specifies the field settings for the given AEGP_RenderOptionsH.
	AEGP_SetFieldRender(AEGP_RenderOptionsH optionsH, PF_Field field_render);
AEGP_GetFieldRender	Retrieves the field settings for the given
64.33. Render Suites	AEGP_RenderOptionsH. AEGP_GetFieldRender(AEGP_RenderOptionsH optionsH, PF_Field *field_renderP);

64.33.2 AEGP_LayerRenderOptionsSuite1

Note: New in 13.0

Function	Purpose
AEGP_NewFromLayer	Returns the AEGP_LayerRenderOptionsH associated with a given AEGP_LayerH. Render time is set to the layer's current time, time step is set to layer's frame duration, ROI to the layer's nominal bounds, and EffectsToRender to "all". optionsPH must be disposed by calling code.
	AEGP_NewFromLayer(AEGP_PluginID plugin_id, AEGP_LayerH layerH, AEGP_LayerRenderOptionsH *optionsPH);
AEGP_NewFromUpstreamOfEffect	Returns the AEGP_LayerRenderOptionsH from the layer associated with a given AEGP_EffectRefH. Render time is set to the layer's current time, time step is set to layer's frame duration, ROI to the layer's nominal bounds, and EffectsToRender to the index of effectH. optionsPH must be disposed by calling code.
	AEGP_NewFromUpstreamOfEffect(AEGP_PluginID plugin_id, AEGP_EffectRefH effectH, AEGP_LayerRenderOptionsH *optionsPH);
AEGP_Duplicate	Duplicates an AEGP_LayerRenderOptionsH into copyPH.
	AEGP_Duplicate(AEGP_PluginID
AEGP_Dispose	Deletes an AEGP_LayerRenderOptionsH.
	AEGP_Dispose(AEGP_LayerRenderOptionsH optionsH);
AEGP_SetTime	Sets the render time of an AEGP_LayerRenderOptionsH. AEGP_SetTime(AEGP_LayerRenderOptionsH optionsH,
	A_Time time);
AEGP_GetTime	Retrieves the render time of the given AEGP_LayerRenderOptionsH.
	AEGP_GetTime(AEGP_LayerRenderOptionsH optionsH, A_Time
AEGP_SetTimeStep	Specifies the time step (duration of a frame) for the referenced AEGP_LayerRenderOptionsH.
	AEGP_SetTimeStep(AEGP_LayerRenderOptionsH optionsH, A_Time
AEGP_GetTimeStep	Retrieves the time step (duration of a frame) for the given AEGP_LayerRenderOptionsH.
	AEGP_GetTimeStep(AEGP_LayerRenderOptionsH optionsH,
64.33. Render Suites	A_Time *timePT); 303
AEGP_SetWorldType	Specifies the AEGP_WorldType of the output of a given AEGP_LayerRenderOptionsH.

64.33.3 AEGP_RenderSuite4

Function	Purpose
AEGP_RenderAndCheckoutFrame	Retrieves an AEGP_FrameReceiptH (not the actual pixels) for the frame requested. Check in this receipt using AEGP_CheckinFrame to release memory. Create the AEGP_RenderOptionsH using the AEGP_RenderOptionsSuite4. Optionally, the AEGP can pass a function to be called by After Effects if the user cancels the current render, as well as a refcon (constant reference to opaque data) for use during that function. AEGP_RenderAndCheckoutFrame (
	AEGP_RenderOptionsH →optionsH, AEGP_RenderSuiteCheckForCancel cancel_ →functionP0, AEGP_CancelRefcon cancel_ →function_refconP0, AEGP_FrameReceiptH →*receiptPH);
AEGP_RenderAndCheckoutLayerFrame	New in CC 2014. This allows frame checkout of a layer with effects applied at non-render time. This is useful for an operation that requires the frame, for example, when a button is clicked and it is acceptable to wait for a moment while it is rendering. Note: Since it is not asynchronous, it will not solve the general problem where custom UI needs to draw based on the frame. Retrieves an AEGP_FrameReceiptH (not the actual pixels) for the layer frame requested. Check in this receipt using AEGP_CheckinFrame to release memory. Create the AEGP_LayerRenderOptionsH using AEGP_NewFromUpstreamOfEffect(), in AEGP_LayerRenderOptionsSuite1. You can actually use AEGP_NewFromLayer() to get other layer param's layers with their effects applied. However, be careful. If you do it in your effect A, and there's an effect B on the other layer that does the same thing during rendering, you'd create an infinite loop. If you're not doing it for render purposes then it could be okay. Optionally, the AEGP can pass a function to be called by After Effects if the user cancels the current render, as well as a refcon (constant reference to opaque data) for use during that function. AEGP_RenderAndCheckoutLayerFrame(AEGP_LayerRenderOptionsH OptionsH, A_Boolean Plain_layer_frameB, AEGP_RenderSuiteCheckForCancel cancel_ HunctionPO, AEGR_CappelRefcon
64.33. Render Suites	AEGP_CancelRefcon cancel_ →function_refconP0, 305 AEGP_FrameReceiptH
AEGP CheckinFrame	→*receiptPH); Call this function as soon as your AEGP is done access-

64.34 The AEGP_World As We Know It

AEGP_Worlds are the common format used throughout the AEGP APIs to describe frames of pixels.

64.34.1 AEGP_WorldSuite3

Function	Purpose
AEGP_New	Returns an allocated, initialized AEGP_WorldH.
	AEGP_New(AEGP_PluginID plugin_id, AEGP_WorldType type, A_long widthL, A_long heightL, AEGP_WorldH *worldPH);
AEGP_Dispose	Disposes of an AEGP_WorldH. Use this on every world you allocate. AEGP_Dispose(
	AEGP_Dispose(AEGP_WorldH worldH);
AEGP_GetType	Returns the type of a given AEGP_WorldH. AEGP_GetType(AEGP_WorldH worldH, AEGP_WorldType **typeP); AEGP_WorldType will be one of the following:
	AEGP_WorldType will be one of the following: • AEGP_WorldType_8, • AEGP_WorldType_16, • AEGP_WorldType_32
AEGP_GetSize	Returns the width and height of the given AEGP_WorldH.
	AEGP_GetSize(AEGP_WorldH worldH, A_long *widthPL, A_long *heightPL);
AEGP_GetRowBytes	Returns the rowbytes for the given AEGP_WorldH.
	AEGP_GetRowBytes(AEGP_WorldH worldH, A_u_long *row_bytesPL);
AEGP_GetBaseAddr8	Returns the base address of the AEGP_WorldH for use in pixel iteration functions. Will return an error if used on a non-8bpc world.
	AEGP_GetBaseAddr8(AEGP_WorldH worldH, PF_Pixel8 **base_addrP);
AEGP_GetBaseAddr16	Returns the base address of the AEGP_WorldH for use in pixel iteration functions. Will return an error if used on a non-16bpc world.
	<pre>AEGP_GetBaseAddr16(AEGP_WorldH worldH, PF_Pixel16 **base_addrP);</pre>
AEGP_GetBaseAddr32	Returns the base address of the AEGP_WorldH for use in pixel iteration functions. Will return an error if used on a non-32bpc world.
308	AEGP_GetBaseAddr32(AEGP_WorldH worldH PF_PixelFloat **base_addrP); AEGP Suites
AEGP_FillOutPFEffectWorld	Populates and returns a PF_EffectWorld representing the given AEGP_WorldH, for use with numerous pixel

64.35 Track Mattes and Transform Functions

 $Use the \verb|AEGP_CompositeSuite| to copy pixel worlds, operate on track mattes, and apply transfer functions.$

64.35.1 AEGP_CompositeSuite2

Function	Purpose
AEGP_ClearAlphaExceptRect	For the given PF_EffectWorld, sets the alpha to fully transparent except for the specified rectangle.
	AEGP_ClearAlphaExceptRect(A_Rect
AEGP_PrepTrackMatte	Mattes the pixels in a PF_EffectWorld with the PF_Pixel described in src_masks, putting the output into an array of pixels dst_mask. NOTE: Unlike most of the other pixel mangling functions provided by After Effects, this one doesn't take PF_EffectWorld arguments; rather, you can simply pass the data pointer from within the PF_EffectWorld. This can be confusing, but as a bonus, the function pads output appropriately so that num_pix pixels are always output.
	AEGP_PrepTrackMatte(A_long
AEGP_TransferRect	Blends two PF_EffectWorlds using a transfer mode, with an optional mask. Pass NULL for the blend_tablesP0 parameter to perform blending in the current working color space.
	AEGP_TransferRect(PF_Quality quality, PF_ModeFlags m_flags, PF_Field field, const A_Rect *src_rec, const PF_EffectWorld *src_world, const PF_CompositeMode *comp_mode, PF_EffectBlendingTables blend_ →tablesP0, const PF_MaskWorld *mask_world0, A_long dest_x, A_long dest_y, PF_EffectWorld *dst_world);
AEGP_CopyBits_LQ	Copies a rectangle of pixels (pass a NULL rectangle to get all pixels) from one PF_EffectWorld to another, at low quality.
	AEGP_CopyBits_LQ(PF_EffectWorld *src_worldP, A_Rect *src_r, A_Rect *dst_r, PF_EffectWorld *dst_worldP);
AEGP_CopyBits_HQ_Straight	Copies a rectangle of pixels (pass a NULL rectangle to get all pixels) from one PF_EffectWorld to another, at high quality, with a straight alpha channel.
64.35. Track Mattes and Transform Function	AEGP_CopyBits_HQ_Straight(PF_EffectWorld *src, A_Rect *src_r, A_Rect *dst_r, PF_EffectWorld *dst):

PF_EffectWorld *dst);

64.36 Work With Audio

AEGP_SoundDataSuite allows AEGPs to obtain and manipulate the audio associated with compositions and footage items.

Audio-only items may be added to the render queue using AEGP_RenderNewItemSoundData().

64.36.1 AEGP_SoundDateSuite1

Function	Purpose
AEGP_NewSoundData	Creates a new AEGP_SoundDataH, of which the plug-in must dispose.
	AEGP_NewSoundData(const AEGP_SoundDataFormat *formatP, AEGP_SoundDataH *new_ →dataPH);
AEGP_DisposeSoundData	Frees an AEGP_SoundDataH.
	AEGP_DisposeSoundData(AEGP_SoundDataH sound_dataH);
AEGP_GetSoundDataFormat	Obtains information about the format of a given AEGP_SoundDataH.
	AEGP_GetSoundDataFormat(AEGP_SoundDataH
AEGP_LockSoundDataSamples	Locks the AEGP_SoundDataH in memory.
	AEGP_LockSoundDataSamples(
	AEGP_SoundDataH soundH, void **samples);
AEGP_UnlockSoundDataSamples	Unlocks an AEGP_SoundDataH.
	AEGP_UnlockSoundDataSamples(AEGP_SoundDataH soundH);
AEGP_GetNumSamples	Obtains the number of samples in the given AEGP_SoundDataH.
	AEGP_GetNumSamples(AEGP_SoundDataH soundH, A_long *numsamplesPL);

64.37 Audio Settings

Audio render settings are represented using the AEGP_SoundDataFormat.

bytes_per_sampleL is always either 1, 2, or 4, and is ignored if float encoding is specified.

AEGP_SoundEncoding is one of the following:

- AEGP_SoundEncoding_UNSIGNED_PCM
- AEGP_SoundEncoding_SIGNED_PCM
- AEGP_SoundEncoding_FLOAT

64.38 Render Queue Suite

This suite allows AEGPs to add items the to render queue (using default options), and control the basic state of the render queue.

64.38.1 AEGP_RenderQueueSuite1

Function	Purpose
AEGP_AddCompToRenderQueue	Adds a composition to the render queue, using default options.
	AEGP_AddCompToRenderQueue(AEGP_CompH compH, const A_char* pathZ);
AEGP_SetRenderQueueState	Sets the render queue to one of three valid states. It is not possible to go from stopped to paused. AEGP_SetRenderQueueState(AEGP_RenderQueueState state); • AEGP_RenderQueueState_STOPPED • AEGP_RenderQueueState_PAUSED • AEGP_RenderQueueState_RENDERING
AEGP_GetRenderQueueState	Obtains the current render queue state. AEGP_GetRenderQueueState(AEGP_RenderQueueState *stateP);

64.39 Render Queue Item Suite

Manipulate all aspects of render queue items using this suite.

64.39.1 AEGP_RQItemSuite4

Function	Purpose
AEGP_GetNumRQItems	Returns the number of items currently in the render
	queue.
	AEGP_GetNumRQItems(
	A_long *num_itemsPL);
AEGP_GetRQItemByIndex	Returns an AEGP_RQItemRefH referencing the index'd item.
	AEGP_GetRQItemByIndex(A_long
AEGP_GetNextRQItem	Returns the next AEGP_RQItemRefH, for iteration purposes. To get the first AEGP_RQItemRefH, pass RQ_ITEM_INDEX_NONE for the current_rq_itemH.
	AEGP_GetNextRQItem(AEGP_RQItemRefH current_rq_itemH, AEGP_RQItemRefH *next_rq_itemPH);
AEGP_GetNumOutputModulesForRQItem	Returns the number of output modules applied to the given AEGP_RQItemRefH.
	AEGP_GetNumOutputModulesForRQItem(AEGP_RQItemRefH rq_itemH, A_long *num_outmodsPL);
AEGP_GetRenderState	Returns TRUE if the AEGP_RQItemRefH is set to render (once the user clicks the Render button).
	AEGP_GetRenderState(AEGP_RQItemRefH rq_itemH, A_Boolean
AEGP_SetRenderState	Controls whether or not the AEGP_RQItemRefH will render when the user next clicks the Render button. Returns an error if called during rendering. This function will return: • Err_PARAMETER if you try to call while AEGP_RenderQueueState isn't AEGP_RenderQueueState_STOPPED, • Err_RANGE if you pass a status that is illegal in any case, and • Err_PARAMETER if you try to pass a status that doesn't make sense (like trying to queue something for which there's no output path)
	AEGP_SetRenderState(AEGP_RQItemRefH rq_itemH, A_Boolean renderB);
AEGP_GetStartedTime	Returns the time (in seconds, since 1904) that rendering began.
	AEGP_GetStartedTime(AEGP_RQItemRefH rq_itemH, A_Time *started_timePT);
4.39P_Render Quedë Item Suite	Returns the time elapsed since rendering began. AEGP_GetElapsedTime(AEGP_RQItemRefH rq_itemH,

A_Time

*render_timePT);

64.40 Render Queue Monitor Suite

New in CS6. This suite provides all the info a render queue manager needs to figure out what is happening at any point in a render.

64.40.1 AEGP_RenderQueueMonitorSuite1

Function	Purpose
AEGP_RegisterListener	Register a set of plug-in-defined functions to be called
	by the render queue. Use the refcon to pass in data
	that you want to use later on when your plug-in-
	defined functions in AEGP_RQM_FunctionBlock1
	are called later. It may be set it to NULL if you don't
	need it.
	AEGP_RegisterListener(
	- -
	AEGP_PluginID aegp_ ⇔plugin_id,
	AEGP_RQM_Refcon aegp_
	⇒refconP,
	<pre>const AEGP_RQM_FunctionBlock1 *fcn_</pre>
	The AEGP_RQM_FunctionBlock1 is defined as follows:
	<pre>struct _AEGP_RQM_FunctionBlock1 {</pre>
	A_Err (*AEGP_RQM_RenderJobStarted)(
	AEGP_RQM_BasicData *basic_dataP,
	AEGP_RQM_SessionId jobid);
	A_Err (*AEGP_RQM_RenderJobEnded)(
	AEGP_RQM_BasicData *basic_dataP,
	<pre>AEGP_RQM_SessionId jobid);</pre>
	A_Err (*AEGP_RQM_RenderJobItemStarted)
	AEGP_RQM_BasicData *basic_dataP,
	AEGP_RQM_SessionId jobid,
	AEGP_RQM_ItemId itemid);
	A_Err (*AEGP_RQM_RenderJobItemUpdated)(
	AEGP_RQM_BasicData *basic_dataP,
	AEGP_RQM_SessionId jobid,
	AEGP_RQM_ItemId itemid,
	<pre>AEGP_RQM_FrameId frameid);</pre>
	A_Err (*AEGP_RQM_RenderJobItemEnded)(
	⇔dataP,
	AEGP_RQM_SessionId jobid,
	AEGP_RQM_ItemId itemid,
	AEGP_RQM_FinishedStatus fstatus);
	A_Err (*AEGP_RQM_
	<pre>→RenderJobItemReportLog) (</pre>
	AEGP_RQM_BasicData *basic_dataP, AEGP_RQM_SessionId jobid,
	AEGF_RQM_Sessionid jobid, AEGP_RQM_ItemId itemid,
	A_Boolean isError,
	AEGP_MemHandle logbuf);
	AEGP_RQM_FunctionBlock1;
	AEGP_RQM_FinishedStatus will be one of the
	following:
	• AEGP_RQM_FinishedStatus_UNKNOWN,
	• AEGP_RQM_FinishedStatus_SUCCEEDEI
	 AEGP_RQM_FinishedStatus_ABORTED.
10	Chantar 6/1 ALCO Suite
18	 AEGP_RQM_FinishedStatus_ABORTED. Chapter 64. AEGP_Suite AEGP_RQM_FinishedStatus_ERRED The AEGP_RQM_BasicData is defined below.

struct _AEGP_RQM_BasicData {

64.41 Output Module Suite

Every item in the render queue has at least one output module specified.

Use this suite to query and control all aspects of the output modules attached to a given render item.

You may also add and remove output modules.

Factoid: For each frame rendered for a given render item, the list of output modules is traversed. So, for frame 0, output module 0, then 1, then 2 are called.

64.41.1 AEGP_OutputModuleSuite4

Function	Purpose	
AEGP_GetOutputModuleByIndex	Retrieves the indexed output module. NOTE: AEGP_OutputModuleRefH is an opaque data type, and can't be manipulated directly; you must use our accessor functions to modify it.	
	AEGP_GetOutputModuleByIndex(AEGP_RQItemRefH rq_itemH, A_long outmod_indexL, AEGP_OutputModuleRefH *outmodPH);	
AEGP_GetEmbedOptions	Retrieves the embedding setting specified for the referenced AEGP_OutputModuleRefH.	
	AEGP_GetEmbedOptions(AEGP_RQItemRefH rq_itemH, AEGP_OutputModuleRefH outmodH, AEGP_EmbeddingType *embed_ optionsP); AEGP_EmbeddingType will be one of the following: • AEGP_Embedding_NOTHING • AEGP_Embedding_LINK • AEGP_Embedding_LINK_AND_COPY	
AEGP_SetEmbedOptions	Specifies the embedding setting for the referenced AEGP_OutputModuleRefH.	
	AEGP_SetEmbedOptions(AEGP_RQItemRefH rq_itemH, AEGP_OutputModuleRefH outmodH, AEGP_EmbeddingType embed_options);	
AEGP_GetPostRenderAction	Retrieves the post-render action setting for the referenced AEGP_OutputModuleRefH.	
	AEGP_GetPostRenderAction(AEGP_RQItemRefH rq_itemH, AEGP_OutputModuleRefH outmodH, AEGP_PostRenderAction *actionP); AEGP_PostRenderAction will be one of the fol-	
	lowing: • AEGP_PostRenderOptions_IMPORT • AEGP_PostRenderOptions_IMPORT_AND_REPLACE_U • AEGP_PostRenderOptions_SET_PROXY	SAG
AEGP_SetPostRenderAction	Specifies the post-render action setting for the referenced AEGP_OutputModuleRefH.	
	AEGP_SetPostRenderAction(AEGP_RQItemRefH rq_itemH, AEGP_OutputModuleRefH outmodH, AEGP_PostRenderAction action);	
AEGP_GetEnabledOutputs	Retrieves which output types are enabled for the referenced AEGP_OutputModuleRefH.	
	AEGP_GetEnabledOutputs(AEGP_RQItemRefH	
64.41. Output Module Suite	AEGP_OutputTypes *typesP); 321 AEGP_OutputTypes will contain one or both of the following values:	

• AEGP_OutputType_VIDEO

64.42 Working With Effects

These functions provide a way for effects (and AEGPs) to obtain information about the context of an applied effect.

Note: Any time you modify or rely on data from outside the normal render pipeline, you run the risk of dependency problems.

There is no way for After Effects to know that you depend on this external information; consequently, you will not be notified if it changes out from under you.

64.42.1 AEGP_PFInterfaceSuite1

Function	Purpose
AEGP_GetEffectLayer	Obtain the layer handle of the layer to which the effect is applied.
	<pre>AEGP_GetEffectLayer(PF_ProgPtr effect_ref, AEGP_LayerH *layerPH);</pre>
AEGP_GetNewEffectForEffect	Obtain the AEGP_EffectRefH corresponding to the effect. AEGP_GetNewEffectForEffect(AEGP_PluginID aegp_plugin_id, PF_ProgPtr effect_ref, AEGP_EffectRefH *effectPH);
AEGP_ConvertEffectToCompTime	Retreive the composition time corresponding to the effect's layer time. AEGP_ConvertEffectToCompTime(PF_ProgPtr effect_ref, long what_timeL, unsigned long time_scaleLu, A_Time *comp_timePT);
AEGP_GetEffectCamera	Obtain the camera (if any) being used by After Effects to view the effect's layer. AEGP_GetEffectCamera(PF_ProgPtr effect_ref, const A_Time *comp_timePT, AEGP_LayerH camera_layerPH);
AEGP_GetEffectCameraMatrix	Obtain the transform used to move between the layer's coordinate space and that of the containing composition. AEGP_GetEffectCameraMatrix(PF_ProgPtr effect_ref, const A_Time *comp_timePT, A_Matrix4 *camera_matrixP, A_FpLong *dst_to_planePF, A_short *plane_widthPL, A_short *plane_heightPL); NOTE: In cases where the effect's input layer has square pixels, but is in a non-square pixel composition, you must correct for the pixel aspect ratio by premultiplying the matrix by (1/parF, 1, 1).

64.42.2 AEGP_GetEffectCameraMatrix Notes

The model view for the camera matrix is inverse of the matrix obtained from $\texttt{AEGP_GetEffectCameraMatrix}()$.

Also note that our matrix is row-based; OpenGL's is column-based.

64.43 Do This Many Times

Utilizes multiple processors (if available) for your computations.

64.43.1 AEGP_IterateSuite1

Function	Purpose
AEGP_GetNumThreads	Ask After Effects how many threads are currently avail-
	able.
	AEGP_GetNumThreads(
	A_long *num_threadsPL);
AEGP_IterateGeneric	Specify a function for After Effects to manage on mul-
	tiple processors. Can be any function pointer specified
	by fn_func, taking the arguments listed below. See
	Private Data for a description of how refconPV is used.
	AEGP_IterateGeneric(
	A_long iterationsL,
	<pre>void *refconPV,</pre>
	A_Err (*fn_func)
	(void *refconPV,
	A_long thread_indexL,
	A_long i,
	A_long iterationsL));

64.44 File Import Manager Suite

The FIMSuite allows file types handled by AEGPs to appear as part of the After Effects import dialog, and drag-and-drop messaging.

These are not for use by AEIOs! Rather, they are for importing projects which are best represented as After Effects compositions.

64.44.1 AEGP_FIMSuite3

Function	Purpose
AEGP_RegisterImportFlavor	Registers the name of the file type(s) supported by the plug-in. Upon return, imp_refP will be a valid opaque reference, or AE_FIM_ImportFlavorRef_NONE.
	AEGP_RegisterImportFlavor(const char *nameZ, AE_FIM_ImportFlavorRef *imp_refP);
AEGP_RegisterImportFlavorFileTypes	Registers an array of file types and file extensions (the two arrays need not be of equal length) supported by the AEGP.
	AEGP_RegisterImportFlavorFileTypes(AE_FIM_ImportFlavorRef imp_ref, long num_filekindsL, const AEIO_FileKind *kindsAP, long num_fileextsL, const AEIO_FileKind *extsAP);
AEGP_RegisterImportFlavorImportCallbac	Register the AEGP functions which will respond to import of different filetypes.
	AEGP_RegisterImportFlavorImportCallbacks(AE_FIM_ImportFlavorRef ref, AE_FIM_ImportFlags single_ →flag, const AE_FIM_ImportCallbacks *imp_ →cbsP);
AEGP_SetImportedItem	Designates an item as having been imported (possibly replacing an existing item), and sets associated import options.
	AEGP_SetImportedItem(AE_FIM_ImportOptions imp_options, AEGP_ItemH imported_itemH);

Cheating Effect Usage of AEGP Suites

As soon as we showed developers the initial implementation of AEGP suites, they wanted to "cheat" and use them from within effects. This is certainly possible, but please keep in mind that depending on factors outside the effect API (i.e., any information you get from the AEGP APIs) can lead to trouble. If After Effects thinks an effect has all the information it needs to render, it won't (for example) update its parameters based on changes made through an AEGP function. We're actively working on this dependency issue for future versions, but bear it in mind as you write effects which "masquerade" as AEGPs.

Effects can use some AEGP suites to take advantage of camera and lighting information, as well as the AEGP_GetLayerParentComp and AEGP_GetCompBGColor functions, from AEGP_CompSuite11. This should not be interpreted to mean that effects can use any AEGP suite calls. Also, see Effect UI & Events for more information on effects adding keyframes.

AEGP_PFInterfaceSuite is the starting point. The functions in this suite allow you to retrieve the AEGP_LayerH for the layer to which the effect is applied, and the AEGP_EffectRefH for the instance of your effect. AEGP_RegisterWithAEGP from AEGP_UtilitySuite6 allows you to get an AEGP_PluginID, which is needed for many AEGP calls.

65.1 Depending on AEGP Queries

One word: Don't. Effects cannot allow the results of AEGP queries to control what is rendered, without appropriately storing those query results (usually in sequence data), cancelling their own render, and forcing a re-render using the queried information.

This is tricky.

Failure to do so will result in nasty, subtle caching bugs guaranteed to cause hair loss and weight gain.

CHAPTER 66

AEGP Details

66.1 Have A Cookie

In cases where After Effects must preserve state information around the functions your AEGP calls (as when an artisan is rendering a frame, or a keyframer is adding and removing a series of keyframes from the same stream), you'll call begin() and end() functions.

Typically, the begin function will return an opaque identifier, or 'cookie', which you must then pass to the functions being used. The end function will properly dispose of the cookie. See $AEGP_StartAddKeyframes()$ (under $AEGP_KeyframeSuite3$) for an example.

66.2 Modifying Items In The Render Queue

If you call AEGP_AddCompToRenderQueue (from *AEGP_RenderQueueSuite1*), or if the user manually adds or removes a composition from the render queue, all references to render queue items are invalidated. Similarly, adding or removing output modules invalidates any such references for each render queue item.

66.3 Names And Solids

Solids have names in the After Effects UI, but not in their PF_LayerDef *PF_EffectWorld / PF_LayerDef*. Consequently, their names cannot be retrieved by AEGP_GetItemName (in *AEGP_ItemSuite9*) or AEGP_GetLayerName (in *AEGP_LayerSuite8*).

However, you can use the ItemH associated with them to AEGP_GetItemName (from AEGP_ItemSuite9).

66.4 Reporting Errors And Problems

Use AEGP_ItemSuite>AEGP_ReportInfo() to report information to users, and identify your plug-in. AEIO plug-ins use the msg_func pointer contained in the AEIO_BasicData they're passed (with every function) instead.

66.5 Transforms: What Happens First?

After Effects computes rotation based on auto-orientation (towards path, or point of interest), then computes Orientation, then computes X, Y, and Z rotation.

66.6 Accessing Pixels From Effect Layer Parameters

Use AEGP_GetNewStreamValue (in AEGP_StreamSuite5) to get the layer's layer_id, then the new AEGP_GetLayerFromLayerID (in AEGP_LayerSuite8) to get the AEGP_LayerH.

CHAPTER 67

Artisans

Note: If you're considering developing an Artisan, please talk it over with us first.

The Artisan API exposes function hooks necessary for a plug-in to provide rendered output of 3D layers, taking over completely from After Effects (which still handles all rendering of 2D layers). There can be only one Artisan per composition, chosen from within the *Composition Settings* > *Advanced* dialog. Artisans render the 3D environment, asking After Effects for information about each element in the composition. As you might guess, this is a vast and tedious process. This API is not recommended for anyone without a strong need to override After Effects' 3D rendering.

Artisans may share information with effects written to communicate with them, but effects may not initiate this communication. Many of the suites used by Artisans require a rendering context which is generated only after all effects have been applied to the layer.

67.1 Interactive Artisans

These differ from standard artisans in that they handle all layers in a composition (not just those which the user has made 3D), and they will only ever be called for onscreen display, never for rendered final output (the rendering calls "fall through" to the default artisan).

CHAPTER 68

Artisan Data Types

Below are the data types most commonly used in the Artisan API.

68.1 Data Types Used In The Artisan API

Туре	Describes
AEGP_RenderLayerContextH	State information at the time of a render request, sent to an Artisan
	by After Effects.
PR_RenderContextH	A collection of settings defining what is to be rendered, and how.
AEGP_SoundDataH	The audio settings used for a given layer.
AEGP_RenderReceiptH	Used by Artisans when rendering.
AEGP_FrameReceiptH	
AEGP_WorldH	A frame of pixels.
AEGP_RenderOptionsH	The settings associated with a render queue item.

68.2 Horz? Vert?

After Effects' matrix is row based; OpenGL's is column based. This means more work for you. Yay, billable hours!

68.3 Implementation And Design

An Artisan is nearly an application unto itself. Because we realized early in the After Effects 5.0 that there are many ways to approach the problems inherent in 3D rendering; intersections and shading, for example.

We provided an API with which we and third parties (yes, we really do use our own APIs) could implement any 3D rendering scheme desired.

68.4 3D Compositing, Not Modeling

After Effects is *not* a 3D modeling application. Users work in a responsive mode, switching to higher quality only at for proofing or final output. Consider providing at least two quality modes, one for layout and another for final output. Be conscious of render time in low quality mode.

68.5 Registering An Artisan

An Artisan is an AEGP, and has a single entry point. Artisans must also register their own function entry points and have a special callback for this purpose. See AEGP_RegisterArtisan() from AEGP_RegisterSuites5.

This tables shows the functions that Artisans can support as defined by PR_ArtisanEntryPoints: only render_func is required.

68.5.1 Artisan Entry Points

PR_ArtisanEntryPoints	
global_setup_func0	Called only once, right after GP_Main. The global data is common across all instances of the plug-in. If you allocate memory during Global Setup, you must free it during your global_setdown_func.
	PR_GlobalSetupFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_GlobalDataH *global_dataPH);
global_setdown_func0	Dispose of any global data you allocated.
	PR_GlobalSetdownFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_GlobalDataH global_dataH);
global_do_about_func0	Tell the world about yourself! Use in_dataP>msg_func to display your dialog.
	PR_GlobalDoAboutFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_GlobalDataH global_dataH);
setup_instance_func0	Allocate and instantiate any data specific to this instance of your Artisan.
	PR_InstanceSetupFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_InstanceContextH instance_contextH, PR_GlobalDataH global_dataH, PR_InstanceFlags flags, PR_FlatHandle flat_dataH0, PR_InstanceDataH *instance_dataPH);
setdown_instance_func0	Deallocate and free any data specific to this instance of your Artisan.
	PR_InstanceSetdownFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_InstanceContextH instance_contextH, PR_GlobalDataH global_dataH, PR_InstanceDataH instance_dataH);
flatten_instance_func0	Flatten your data in preparation to being written to disk. (making sure it's OS independent, if your Artisan is).
	PR_FlattenInstanceFunc(const PR_InData *in_dataP, PR_GlobalContextH global_contextH, PR_InstanceContextH instance_contextH, PR_GlobalDataH global_dataH, PR_InstanceDataH instance_dataH, PR_FlatHandle *flatH);
do_instance_dialog_func0	If your Artisan has a additional parameters (accessed through its Options dialog), this function will be called
336	to get and set them. Chapter 68. Artisan Data Types PR_DoInstanceDialogFunc(const PR_InData *in_dataP,

PR_GlobalContextH

global_contextH,

68.6 The World Is Your Canvas

AEGP_RenderTexture () supplies the raw pixels of a layer, untransformed, into an arbitrarily-sized buffer.

AEGP_RenderLayer() invokes the entire After Effects render pipeline, including transforms, masking, et cetera, providing the layer as it appears in its composition, in a composition-sized buffer.

If the layer being rendered is 3D, the default (Standard 3D) Artisan is invoked to perform any 3D geometrics.

Your Artisan can use this to render track matte layers, and apply them only in a strictly 2D sense, to the transformed 3D layer.

Before rendering, the Artisans that ship with After Effects apply an inverse transform to get square pixels, then re-apply the transform before display.

For example, if the pixel aspect ratio is 10/11 (DV NTSC), we multiply by 11/10 to get square pixels. We process and composite 3D layers, then re-divide to get back to the original pixel aspect ratio.

The following suite supplies the layers, compositions, texture and destination buffers. This is a vital suite for all artisans.

68.6.1 AEGP_CanvasSuite8

Note: Functions below are for interactive artisans only.

Function	Purpose
AEGP_GetPlatformWindowRef	Retrieves the platform-specific window context into which to draw the given PR_RenderContextH.
	AEGP_GetPlatformWindowRef(const PR_RenderContextH contextH, AEGP_PlatformWindowRef *window_refP);
AEGP_GetViewportScale	Retrieves the source-to-frame downsample factor for the given PR_RenderContextH.
	AEGP_GetViewportScale(const PR_RenderContextH contextH, A_FpLong *scale_xPF, A_FpLong *scale_yPF);
AEGP_GetViewportOrigin	Retrieves to origin of the source, within the frame (necessary to translate between the two), for the given PR_RenderContextH.
	AEGP_GetViewportOrigin(const PR_RenderContextH contextH, A_long *origin_xPL, A_long *origin_yPL);
AEGP_GetViewportRect	Retrieves the bounding rectangle for the area to be drawn, for the given PR_RenderContextH.
	AEGP_GetViewportRect(const PR_RenderContextH contextH, A_LegacyRect *v_rectPR);
AEGP_GetFallowColor	Retrieves the color used for the fallow regions in the given PR_RenderContextH.
	AEGP_GetFallowColor(const PR_RenderContextH contextH, PF_Pixel8 *fallow_ colorP);
AEGP_GetInteractiveCheckerboard	Retrieves whether or not the checkerboard is currently active for the given PR_RenderContextH.
	AEGP_GetInteractiveCheckerboard(const PR_RenderContextH contextH, A_Boolean *cboard_onPB);
AEGP_GetInteractiveCheckerboardColors	Retrieves the colors used in the checkerboard.
	AEGP_GetInteractiveCheckerboardColors(const PR_RenderContextH_contextH,
	PF_Pixel *color1P, PF_Pixel *color2P);
AEGP_GetInteractiveCheckerboardSize	Retrieves the width and height of one checkerboard square.
	AEGP_GetInteractiveCheckerboardSize(const PR_RenderContextH contextH, A_u_long *cbd_widthPLu, A_u_long *cbd_ →heightPLu);
AEGP_GetInteractiveCachedBuffer	Retrieves the cached AEGP_WorldH last used for the
338	PR_RenderContextH. Chapter 68. Artisan Data Types AEGP_GetInteractiveCachedBuffer(const PR_RenderContextH contextH,
	AEGP_WorldH *buffer);

68.7 Convert Between Different Contexts

Convert between render and instance contexts, and manage global data specific to the artisan.

68.7.1 AEGP_ArtisanUtilSuite1

Function	Purpose
AEGP_GetGlobalContextFromInstanceCont	ex Given an instance context, returns a handle to the global context.
	AEGP_GetGlobalContextFromInstanceContext(const PR_InstanceContextH instance_ ⇔contextH, PR_GlobalContextH *global_ ⇔contextPH);
AEGP_GetInstanceContextFromRenderCont	exGiven the render context, returns a handle to the instance context.
	AEGP_GetInstanceContextFromRenderContext(const PR_RenderContextH render_ contextH, PR_InstanceContextH *instac_ ctextPH);
AEGP_GetInstanceContextFromQueryConte	xt Given a query context, returns a handle to the instance context.
	AEGP_GetInstanceContextFromQueryContext(const PR_QueryContextH query_contextH, PR_InstanceContextH *instance_
AEGP_GetGlobalData	Given the global context, returns a handle to global data.
	AEGP_GetGlobalData(const PR_GlobalContextH global_ contextH, PR_GlobalDataH *global_ codataPH);
AEGP_GetInstanceData	Given an instance context, return the associated instance data.
	AEGP_GetInstanceData(const PR_InstanceContextH instance_ contextH, PR_InstanceDataH *instance_ codataPH);
AEGP_GetRenderData	Given a render context, returns the associated render data.
	AEGP_GetRenderData(const PR_RenderContextH render_ contextH, PR_RenderDataH *render_ contextH, PR_AenderDataH *render_

68.8 Smile! Cameras

Obtains the camera geometry, including camera properties (type, lens, depth of field, focal distance, aperture, et cetera).

68.8.1 AEGP_CameraSuite2

Function	Purpose
AEGP_GetCamera	Given a layer handle and time, returns the current cam-
	era layer handle.
	AEGP_GetCamera(
	PR_RenderContextH render_contextH,
	<pre>const A_Time *comp_timeP,</pre>
	AEGP_LayerH *camera_layerPH);
AEGP_GetCameraType	Given a layer, returns the camera type of the layer.
	AEGP_GetCameraType(
	AEGP_LayerH aegp_layerH,
	AEGP_CameraType *camera_typeP;
	The camera type can be the following:
	• AEGP_CameraType_NONE = -1
	• AEGP_CameraType_PERSPECTIVE
	• AEGP_CameraType_ORTHOGRAPHIC
AEGP_GetDefaultCameraDistanceToImagePl	a Given a composition handle, returns the camera distance
	to the image plane.
	AEGP_GetDefaultCamera_
	→DistanceToImagePlane(
	AEGP_CompH compH,
	A_FpLong *dist_to_planePF)
AEGP_GetCameraFilmSize	Retrieves the size (and units used to measure that size)
	of the film used by the designated camera.
	AEGP_GetCameraFilmSize(
	AEGP_LayerH camera_layerH,
	AEGP_FilmSizeUnits *film_size_unitsP,
	A_FpLong *film_sizePF0);
AEGP_SetCameraFilmSize	Sets the size (and unites used to measure that size) of
	the film used by the designated camera.
	AEGP_SetCameraFilmSize)(
	AEGP_LayerH camera_layerH,
	AEGP_FilmSizeUnits film_size_units,
	A_FpLong *film_sizePF0);

68.9 Notes Regarding Camera Behavior

Camera orientation is in composition coordinates, and the rotations are in layer (the camera's layer) coordinates.

68.8. Smile! Cameras 341

If the camera layer has a parent, the position is in a coordinate space relative to the parent.

68.10 Orthographic Camera Matrix

Internally, we use composition width and height to set the matrix described by the OpenGL specification as

```
glOrtho(-width/2, width/2, -height/2, height/2, -1, 100);
```

The orthographic matrix describes the projection. The position of the camera is described by another, scaled matrix. The inverse of the camera position matrix provides the "eye" coordinates.

68.11 Focus On Focal

Remember, focal length affects field of view; focal distance only affects depth of field.

68.12 Film Size

In the real world, film size is measured in millimeters. In After Effects, it's measured in pixels. Multiply by 72 and divide by 25.4 to move from millimeters to pixels.

Field of view is more complex;

= 1/2 field of view

tan() = 1/2 composition height / focal length

focal length = $2 \tan() / \text{composition height}$

68.13 Hit The Lights!

Get and set the type of lights in a composition.

68.13.1 AEGP LightSuite2

Function	Purpose
AEGP_GetLightType	Retrieves the AEGP_LightType of the specified camera layer.
	AEGP_GetLightType(AEGP_LayerH light_layerH, AEGP_LightType *light_typeP); AEGP_LightType will be one of the following: • AEGP_LightType_PARALLEL • AEGP_LightType_SPOT • AEGP_LightType_POINT • AEGP_LightType_AMBIENT
AEGP_SetLightType	Sets the AEGP_LightType for the specified camera layer. AEGP_SetLightType(AEGP_LayerH light_layerH, AEGP_LightType light_type);

68.13.2 Notes On Light Behavior

The formula for parallel lights is found in Foley and Van Dam's "Introduction to Computer Graphics" (ISBN 0-201-60921-5) as is the formula for point lights.

We use the half angle variant proposed by Jim Blinn instead.

Suppose we have a point on a layer and want to shade it with the light.

Let V be the unit vector from the layer point to the eye point. Let L be the unit vector to the light (in the parallel light case this is constant). Let H be (V+L)/2 (normalized). Let N be the unit normal vector to the layer.

The amount of specular reflected light is S * power(H Dot N, shine), where S is the specular coefficient.

68.14 How Should I Draw That?

After Effects relies upon Artisans to draw 3D layer handles. If your Artisan chooses not to respond to this call, the default Artisan will draw 3D layer handles for you. Querying transforms is important for optimization of After Effects' caching.

The coordinate system is positive x to right, positive y down, positive z into the screen. The origin is the upper left corner. Rotations are x then y then z. For matrices the translate is the bottom row, orientations are quaternions (which are applied first), then any x-y-z rotation after that. As a general rule, use orientation or rotation but not both. Also use rotations if you need control over angular velocity.

68.15 Query Transform Functions

These functions give artisans information about the transforms they'll need in order to correctly place layers within a composition and respond appropriately to the various queries After Effects will send to their PR_QueryFunc entry point function.

As that entry point is optional, so is your artisan's response to the queries; however, if you don't, your users may be disappointed that (while doing interactive preview drawing) all the camera and light indicators vanish, until they stop moving! Artisans are complex beasts; contact us if you have any questions.

68.15.1 AEGP_QueryXFormSuite2

Function	Purpose
AEGP_QueryXformGetSrcType	Given a query context, returns trasnsform source currently being modified.
	AEGP_QueryXformGetSrcType(PR_QueryContextH query_contextH,
	AEGP_QueryXformType *src_type);
	The query context will be one of the following:
	• AEGP_Query_Xform_LAYER,
	• AEGP_Query_Xform_WORLD,
	• AEGP_Query_Xform_VIEW,
	AEGP_Query_Xform_SCREEN
AEGP_QueryXformGetDstType	Given a query context, returns the currently requested
	transform destination.
	AEGP_QueryXformGetDstType(
	PR_QueryContextH query_contextH, AEGP_QueryXformType *dst_type);
AEGP_QueryXformGetLayer	Used if the source or destination type is a layer. Given a
	query context, returns the layer handle.
	AEGP_QueryXformGetLayer(
	PR_QueryContextH query_contextH,
	AEGP_LayerH *layerPH);
AEGP_QueryXformGetComp	Given a query context, returns the current composition handle.
	AEGP_QueryXformGetComp(
	PR_QueryContextH query_contextH,
	AEGP_CompH *compPH);
AEGP_QueryXformGetTransformTime	Given a query context, returns the time of the transformation.
	AEGP_QueryXformGetTransformTime(
	PR_QueryContextH query_contextH, A_Time *time);
AEGP_QueryXformGetViewTime	Given a query context, returns the time of the associated
	view.
	AEGP_QueryXformGetViewTime(PR_QueryContextH query_contextH,
	A_Time *time);
AEGP_QueryXformGetCamera	Given a query context, returns the current camera layer handle.
	AEGP_QueryXformGetCamera(
	PR_QueryContextH query_contextH,
	AEGP_LayerH *camera_layerPH);
AEGP_QueryXformGetXform	Given a query context, returns the current matrix transform.
	AEGP_QueryXformGetXform(
	PR_QueryContextH query_contextH, A_Matrix4 *xform);
AEGP_QueryXformSetXform	Given a query context, return the matrix transform you compute in xform.
	AEGP_QueryXformSetXform(
	PR_QueryContextH query_contextH,

68.16 Interactive Drawing Functions

We've added the ability for artisans to provide functions After Effects can use to do basic drawing functions for updating the comp window display during preview, including camera, light, and wireframe preview modeling.

68.16.1 PR InteractiveDrawProcs

Function	Purpose
PR_Draw_MoveToFunc	
	PR_Draw_MoveToFunc(
	short x,
	short y);
PR_Draw_LineToFunc	
	PR_Draw_LineToFunc(
	short x,
	<pre>short y);</pre>
PR_Draw_ForeColorFunc	
	PR_Draw_ForeColorFunc(
	const A_Color *fore_colo
PR_Draw_FrameRectFunc	
	PR_Draw_FrameRectFunc(
	<pre>const A_Rect *rectPR);</pre>
PR_Draw_PaintRectFunc	
	PR_Draw_PaintRectFunc(
	<pre>const A_Rect *rectPR);</pre>

68.17 Notes On Query Time Functions

AEGP_QueryXformGetTransformTime() and AEGP_QueryXformGetViewTime() are both necessary for an artisan to build a representation of the scene to render.

AEGP_QueryXformGetTransformTime() gets the time of the transform, which is then passed to AEGP_GetCompShutterFrameRange() from $AEGP_CompSuite11$.

CHAPTER 69

AEIOs

AEIOs are AEGPs that perform media file import and/or export. AEIOs do everything for a file of a given type that After Effects (or the plug-ins which ship with After Effects) would normally do. On the import side, AEIOs can open existing files, manage file-specific interpretation options, and provide audio and frames from the file to After Effects in AEGP_SoundWorld and PF_EffectWorld format. Additionally, AEIOs can create files interactively, asking users for the settings they'd like instead of reading them from a file. On the export side, AEIOs can create and manage output options for render queue items, create output files and save frames (provided by After Effects as PF_EffectWorlds) into those files.

AEIOs work with uncompressed video with pixels in ARGB order from low to high-byte. Pixels can be 8-bit, 16-bit, or 32-bit float per channel. AEIOs must handle their own compression/decompression of any codecs supported.

69.1 AEIO, or AEGP?

AEIOs provide pixels and audio data to After Effects.

If you're writing an importer/exporter for a file format that represents timeline or project format (referencing file formats supported by After Effects or other installed AEIOs), write an AEGP and add its command to the Import/Export submenu.

69.2 AEIO For Import, Or MediaCore Importer?

After Effects supports MediaCore importer plug-ins. MediaCore is a set of shared libraries that grew out of Premiere Pro; thus the MediaCore APIs are described in the Premiere Pro SDK.

Only MediaCore importer plug-ins support an importer priority system: The highest priority importer gets the first opportunity to import a file, and if the particular imported file isn't supported, the next-highest priority importer will then have the opportunity to try importing it, and so on. MediaCore importers cannot defer file import to an AEIO. So

if your goal is to take over file handling for any file type for which After Effects already provides a plug-in, you need to develop a MediaCore importer plug-in.

On the other hand, only AEIOs can display a setup dialog in the Interpret Footage < Main > More Options dialog.

If the above constraints haven't already answered whether you need to build an AEIO or MediaCore importer, then you'll likely want to build a MediaCore importer, which can be used across the video and audio applications including Premiere Pro, Media Encoder, Prelude, SpeedGrade, and Audition.

69.3 How It Works

From within its entry point function, an AEIO populates a structure of function pointers with the names of the functions it wants called in response to certain events. Many of these function hooks are optional.

69.4 What Would After Effects Do?

For many AEIO hook functions, you can ask After Effects to perform default processing (this capability is noted in each hook's descriptions).

Unless you have compelling reasons to do otherwise, return AEIO_Err_USE_DFLT_CALLBACK from the function, and let After Effects do the work.

This is also a good way to learn the calling sequence before beginning implementation.

69.5 Registering Your AEIO

During your plug-in's entry point function, populate a AEIO_ModuleInfo describing the filetype(s) the AEIO supports, and an AEIO_FunctionBlock structure that points to your file handling functions. For some of these functions, you can rely on After Effects' default behavior by returning AEIO_Err_USE_DFLT_CALLBACK. However, you must still provide a function matching the required signature, that does so. Once you've filled out both these structures, call AEGP_RegisterIO() from AEGP_RegisterSuites5.

In the AEIO_ModuleInfo that you pass in to the register call, you provide the file type and description information that After Effects uses in the Import dialog, for the "Files of type" drop-down on Windows, or the Enable drop-down on MacOS. As of CS6, file extensions cannot be more than three characters long, even though we have a few built-in importers with longer extensions.

350 Chapter 69. AEIOs

69.6 InSpec, OutSpec

On most import-related functions, an $AEIO_InSpecH$ is passed. On most output-related functions, an $AEIO_OutSpecH$ is passed.

What are these mysterious handles? These opaque data handles can be used with *AEGP_IOInSuite5* and *AEGPIOOut-Suite4*, to set or query for information about the import or output.

For example, on an import, you'll use $AEIO_InSpecH$ when calling $AEGP_SetInSpecDimensions$ in $AEGP_IOInSuite$.

And during an export, you'll use AEIO_OutSpecH when calling AEGP_GetOutSpecDimensions in AEGP_IOOutSuite. So use these handles to exchange information with After Effects about the details of the input or output.

352 Chapter 69. AEIOs

Calling Sequence

As with all AEGPs, the entry point function exported in the plug-in's PiPL is called during launch. During this function, the AEIO must provide function pointers to required functions and describe their capabilities, then pass the appropriate structures to *AEGP_RegisterIO()*.

70.1 Import

When users select a file in the file import dialog which is of a type handled by your AEIO, its AEIO_VerifyFileImportable() function will be called; it's called again for each such file the user imports. AEIO_InitInSpecFromFile() will be called for each file; parse the file, and use the various set functions to describe it to After Effects. Also, construct any options data associated with the file, and save that data using AEGP_SetInSpecOptionsHandle().

After Effects then calls the plug-in's *AEIO_GetInSpecInfo()* function, to get descriptive text about the file for display in the project window. As noted in the description of this function, it may be called for folders as well; we recommend that, if there is no valid options data for the file, you do nothing and return no error (that's what our AEIOs do).

AEIO_CountUserData() is then sent; if the AEIO indicates that there is user data present, AEIO_GetUserData() will follow. After Effects will then request that the plug-in draw a frame of video (for the project window thumbnail) by sending AEIO_DrawSparseFrame().

Once the supported file is added to a composition, user interaction will generate calls to $AEIO_DrawSparseFrame()$ and $AEIO_GetSound()$.

When the project is saved, and if there is options data associated with the AEIO_InSpec, After Effects will send *AEIO_FlattenOptions()* during which the AEIO parses the options data, and creates a representation of it that contains no references to external memory. Likewise, the presence of any AEIO_OutSpec options data will result in *AEIO_GetFlatOutputOptions()* being sent.

70.2 Export

If the user adds an item to the render queue and chooses the AEIO's supported output format, <code>AEIO_InitOutputSpec()</code> will be sent. Use the various get functions to obtain information about the output settings, and store any pertinent information using <code>AEGP_SetOutSpecOptionsHandle()</code>, followed by <code>AEIO_GetFlatOutputOptions()</code>. <code>AEIO_GetDepths()</code> is sent so After Effects can determine what output pixel bit depths the AEIO supports. <code>AEIO_GetOutputInfo()</code> is sent so that file name, type and subtype information can be displayed in the output module details.

When the user clicks on the Format Options button, in the render queue, AEIO UserOptionsDialog() is called.

When the user actually clicks on the "Render" button, AEIO_SetOutputFile() will be called, followed by AEIO_GetSizes() (your AEIO is responsible for determining whether the destination has sufficient disk space available).

Before the video frames are sent, AEIO_StartAdding() is sent for the AEIO to open the file handle and write out the file header. If the AEIO supports a video or audio format, AEIO_AddSoundChunk() is sent for each audio chunk, and an AEIO_AddFrame() for each video frame.

If the AEIO supports sequences of still images, *AEIO_OutputFrame()* is called repeatedly. After Effects sends a PF_EffectWorld representation of the frame to be output.

AEIO_WriteLabels() is called (for each frame) to give the plug-in a chance to write out field and alpha interpretation information. AEIO_EndAdding() is sent when there are no more frames (or audio) to be output. Close the output file.

CHAPTER 71

AEIO_ModuleInfo

This is the structure where your AEIO will define its basic properties.

Notice that, in addition to describing the filetypes and extensions supported by your AEIO, you also describe your signature and behavior using the AEIO_ModuleFlags. We love flags.

71.1 AEIO_ModuleInfo Members

Mem-	Purpose
ber	
sig	A long, uniquely identifying your plug-in. Many developers prefer to use a decidedly Mac-ish four
	character code here. Please let us know what sig you're using.
name	Descriptive name for your AEIO plug-in.
flags	Set of AEIO_ModuleFlags.
flags2	Set of AEIO_ModuleFlags2.
max_wio	EThe maximum dimensions supported by your format.
max_he	ght
	eThemesnber of filetypes supported by your AEIO.
num_ext	eThe immerber of file extensions supported by your AEIO.
	phe number of clipboard formats supported by your AEIO.
	kTihectmacOS four character code for files created by your AEIO.
	_eEtte file extension for files created by your AEIO.
read_k	nthis array of 16 AEIO_FileKinds need not be entirely filled out, but the first [num_filetypes
	+ num_extensions + num_clips] ones must be populated, in that order.
num_aux	The treumber of sauxiliary extensions supported by your AEIO.
	Say, for example, that you're writing an AEIO to import information from a 3D program that saves
	scene information into a .123 file, and camera information into a .xyz file.
	The .xyz would be an auxiliary extension; it's not necessary to get the rest of the scene information, but
	it's associated with the .123 files.
aux_ext	The file extension of the auxiliary filetype(s) supported by your AEIO.

71.2 Behavior Flags

AEIOs set these flags (like effect plug-ins use global outflags) in AEIO_ModuleInfo.flags to indicate their behavior to After Effects. Some flags are only relevant to input, and some are only relevant to output.

71.2.1 AEIO_ModuleFlags

Flag	Purpose	l or O?
AEIO_MFlag_INPU	T AEIO is an input module.	In-
		put!
AEIO_MFlag_OUTP	AEIO is an output module (one plug-in can be both).	Out-
AEIO_MFlag_FILE	Each clip imported directly corresponds to a file, somewhere.	Both
AEIO_MFlag_STII	L Supports still images, not video.	Out-
AEIO_MFlag_VIDE	O Supports video images, not stills.	Out- put
AEIO_MFlag_AUDI	O Supports audio.	Out-
AEIO MFlag NO I	IME Time information isn't part of the file format.	In-
	This would be the case with numbered stills, with individual frames imported	put
	based on the composition's time settings.	Put
AEIO MElag INTE	RAC AINEW input sequence necessitates user interaction.	In-
11110_111109_11111	This would be the case for a non-file-based input module.	put
AEIO MElac INTE	RAC AINEN Dutput sequence necessitates user interaction.	Out-
TIDIO_III 149_IIVIL	This would be the case for a non-file-based output module.	put
AFIO MElac CANT	CLThe AEIO's drawing functions cannot accept dimensions smaller than the re-	In-
AE10_MF1ag_CAN1	quested dimensions.	
ARIO MRISA MUCT	_INThraceIOntoust display a dialog box, even if a valid options data handle is avail-	put Out-
AE10_MF1ag_MUS1		
ADTO MD1 CANT	able.	put
AE10_MF1ag_CAN1	_S OTHO ATHORNALIA STHAT all video data be processed, then sound data (instead of	Out-
	interleaving the processing the video and audio).	put
AE10_MF1ag_CAN_	ADD The ANTIO supports antiding non-sequential frames.	Out-
		put
AEIO_MFlag_HOST	_DE The AFIOwants After Effects to display a bit-depth selection dialog.	In-
		put
AEIO_MFlag_HOST	_FRANE_ASTORVanDSIAfter Effects to display a dialog requesting that the user specify	In-
	a starting frame.	put
AEIO_MFlag_NO_C	PTITM6 AEIO does not accept output options.	Out-
AEIO MElag NO P	IXEIThe AEIO's file format doesn't actually store pixels. Currently unused as of	(un-
1111 1 0 <u>_</u> 111 1 0 <u>9</u> _110 <u>_</u> 1	CS6.	used
AFIO MElac SEON	ENCEThe AEION Sill (Mopt the sequence options of its parent if a folder is selected.	In-
		put
AEIO_MFlag_INPU	T_Off The CANSIO has user options associated with each input sequence.	In-
	NOTE: the options information must be flat (not referring to any data contained in external pointers or handles).	put
AEIO_MFlag_HSF_	AWARhe AEIO will provide horizontal scaling factor (pixel aspect ratio) information	In-
	for each new sequence.	put
	This prevents After Effects from guessing.	
AEIO_MFlag_HAS_	LAY ITA6 AEIO supports multiple layers in a single document.	In-
		put
AEIO_MFlag_SCRA	The AEIO has a clipboard parsing component.	In-
		put
AEIO_MFlag_NO_U	I After Effects should display no UI for this module (do not com-	In-
	bine this flag with AEIO_MFlag_HOST_DEPTH_DIALOG or	put
	AEIO_MFlag_HOST_FRAME_START_DIALOG)	
AEIO_MFlag_SEQ_	OP TONA HIO chas sequence options accessible from the More Options button in the	In-
	Interpret Footage dialog. Chapter 71. AEIO Modu	I DIH fo
AEIO_MFlag_HAS_	AUX The file format supported by the AEIO has depth information, normals, or some	Ĭn-
	other non-color information related to each pixel.	put
AEIO_MFlag_HAS	MET AThe Attender and the METAThe ATTENDED ATTE	Out-
	If this flog is set, the embed pop up in the output module dialog will be enabled	put

71.2.2 AEIO_ModuleFlags2

Gotta have dem flags...

Flag	Purpose	l or O?
		Ur
AEIO_MFlag2_AUDIO_OPTI	ON the AEIO has an audio options dialog.	Out-
		put
AEIO_MFlag2_SEND_ADDMA	RATHR AHHOORANTA TO DECEMPE marker data before outputting video or audio	Out-
	(useful for MPEG streams).	put
AEIO_MFlag2_CAN_DO_MAR	ATA6_AEIO supports combined markers; URL flips, chapters, and com-	Out-
	ments.	put
AEIO_MFlag2_CAN_DRAW_F	Lotan Tana AEIO can draw into float (32-bpc) worlds.	In-
		put
AEIO_MFlag2_CAN_DO_AUD	I Suβports 32-bit audio output.	Out-
		put
AEIO_MFlag2_SUPPORTS_I	CSupportsILCCSprofiles.	Both
AEIO_MFlag2_CAN_DO_MAR	AEIO supports combined markers; URL flips, chapters, comments,	Out-
	and cue points.	put
AEIO_MFlag2_SEND_ADDMA	RATHR AND CONTINUES TO ANTOCASED TO THE METERS BEFORE VIDEO during export.	Out-
		put
AEIO_MFlag2_USES_QUICK	TOME MacOS, prior to the host calling AEIO_AddFrame or	Out-
	AEIO_OutputFrame from AEIO_FunctionBlock4, it will lock	put
	the global QuickTime mutex.	

CHAPTER 72

New Kids On The Function Block

During its main entry point function, each AEIO plug-in must fill in an AEIO_FunctionBlock, providing pointers to the functions After Effects will call for different file-related tasks.

The table below shows which functions are needed for input, and which ones are needed for output. For a bare-bones implementation, start with the functions that are noted as "Required" in the right column. You can often invoke "best-case" behavior by having After Effects handle the call for you (by returning AEIO_Err_USE_DFLT_CALLBACK).

For a barebones AEIO for video input only, implement the following functions: AEIO_InitInSpecFromFile or AEIO_InitInSpecInteractive (depending on whether the source is a file or interactively generated), AEIO_DisposeInSpec, AEIO_GetInSpecInfo, AEIO_DrawSparseFrame, AEIO_CloseSourceFiles, and AEIO_InqNextFrameTime (using AEIO_Err_USE_DFLT_CALLBACK is fine).

Starting from the IO sample, it is best to leave the other functions defined too, and fill them in further as needed.

72.1 AEIO_FunctionBlock4

Function	Response	I or O?	Required?
	AFGiven a file path, describe its contents to After Effects in the provided AEIO_InSpecH. Use all appropriate "set" calls from the AEGP_IOInSuite) to do so; if there is image data, set its depth, dimensions, and alpha interpretation. If there is audio, describe its channels and sample rate. The file path is a NULL-terminated UTF-16 string with platform separators. AEIO_ InitInSpecFromFile AEIO_BasicData *basic_dataP, const A_ UTF16Char *file_ pathZ, AEIO_InSpecH inH);	Input	Yes, for file-based media
AEIO_InitInSpecInte	erdsing some form of user interaction (and not a file path provided by After Effects), describe the audio and video your generated AEIO_InSpecH contains. AEIO_ —InitInSpecInteract: AEIO_BasicData —*basic_dataP, AEIO_InSpecH —inH);	Input	Yes, for interactively generated media
AEIO_DisposeInSpec	Free an AEIO_InSpecH. AEIO_DisposeInSpec(AEIO_BasicData _	Input	Yes

Table 1 – continued from previous page

Function	Response	l or 0?	Required?
AEIO_FlattenOptions AEIO_InflateOptions	For the given AEIO_InSpecH, return a flattened version of the data contained in its options handle. Obtain the unflattened options handle using AEGP_GetInSpecOption AEIO_ →FlattenOptions(AEIO_BasicData →*basic_dataP, AEIO_InSpecH →inH, AEIO_Handle →*flat_optionsPH);	Input	No
AETO_INITATEOptions	AEIO_InSpecH, create (using AEGP_SetInSpecOptic an unflattened version of its flattened option data. AEIO_ InflateOptions(AEIO_BasicData *basic_dataP, AEIO_InSpecH inH, AEIO_Handle flat_optionsH);	•	INO
AEIO_SynchInSpec	AEIO_Err_USE_DFLT_Callowed. Inspect the AEIO_InSpecH, update its options if necessary), and indicate whether or not you made changes. AEIO_SynchInSpec(AEIO_BasicData	Діприн АСК	No

Table 1 – continued from previous page

Table 1 – continued from previous page				
Function	Response	I or O?	Required?	
AEIO_GetActiveExter	tAEIO_Err_USE_DFLT_0	A hput ACK	Yes	
	allowed. Populate the pro-			
	vided A_LRect with the			
	active extent of the file's			
	pixels at the given time.			
	AEIO_ →GetActiveExtent(
	AEIO_BasicData			
	→*basic_dataP,			
	AEIO_InSpecH			
	⇒inH,			
	const A_Time _			
	⇔*tr,			
	A_LRect _			
	<pre></pre>			
AEIO_GetInSpecInfo	Provide a few strings in	Input	Yes	
"TTO Gectus hecilito	AEIO_Verbiage to	mput	103	
	describe the file, which			
	will appear in the Project			
	panel. This includes the			
	strings used to describe			
	the file type and subtype			
	(the codec).			
	(the codec).			
	AEIO_GetInSpecInfo(
	AEIO_BasicData _			
	→*basic_dataP,			
	AEIO_InSpecH _ →inH,			
	7.0.17			
	AEIO_verblage _ →*verbiageP);			
	This function gets called			
	OFTEN; every time we			
	refresh the project panel.			
	Keep allocations to a			
	minimum. In the AEIOs			
	that ship with After			
	Effects, we check for a			
	valid optionsH (using			
	AEGP_GetInSpecOption	 nsHandle):		
	if we find one, we use the			
	information from within			
	it. If not, we do nothing.			
	This is important; if your			
	AEIO handles still im-			
	ages, this function will get			
	called for the folder con-			
	taining the stills. Hope-			
	fully, there won't be an			
	optionsH associated with			
	it (unless you're writing a			
	truly bizarre AEIO).			
	r · · · · · · · · · · · · · · · · · · ·	I.	·	

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_DrawSpars	eFrameDraw a frame from the	Input	Yes
	AEIO_InSpecH. The		
	PF_EffectWorld*		
	contains the width and		
	height to use, but make		
	sure you take the re-		
	quired_region0 into		
	account, if it's not NULL.		
	AEIO_		
	→DrawSparseFrame(
	AEIO_BasicData _		
	→dataP,		
	AEIO_InSpecH		
	→ inH,		
	AEIO_Quality		
	const AEIO_		
	⇔RationalScale		
	→*rs0,		
	const A_Time		
	const A_Time _		
	↔ ⊔		
	⇔*duration0,		
	const A_Rect _		
	→*required_		
	→region0, PF_EffectWorld _		
	→ *wP,		
	A_long*		
	originx,		
	A_long*		
	originy,		
	AEIO_		
	<pre>→DrawingFlags _</pre>		
	⇔flagsP);		
	NOTE: return data as lin-		
	ear light (1.0), and After		
	Effects will perform any		
	necessary transformations		
	to bring the footage into		
	the working colorspace.		

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_GetDimensions	AEIO_Err_USE_DFLT_CA allowed. Provide the dimensions (and, if necessary, scaling fac- tor) of the video in the AEIO_InSpecH.	Ш ьр жСК	No
	AEIO_GetDimensions(AEIO_BasicData		
AEIO_GetDuration	AEIO_Err_USE_DFLT_(allowed. Provide the duration of an AEIO_InSpecH, in seconds. AEIO_GetDuration(AEIO_BasicData **basic_dataP, AEIO_InSpecH *inH, A_Time **trP);	Априн аск	No

Table 1 – continued from previous page

Function	Response I or O?	Required?
AEIO_GetTime	AEIO_Err_USE_DFLT_CAnnutACK allowed. Provide the timebase of an	No
	AEIO_InSpecH.	
	AEIO_GetTime(AEIO_BasicData _	
	Here are the values we use internally for common timebases: 29.97 fps: scale = 100; value= 2997; 59.94 fps: scale = 50; value = 2997; 23.976 fps: scale = 125; value = 2997; 30 fps: scale = 1; value = 30; 25 fps: scale = 1; value = 25;	

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_GetSound	AEIO_Err_USE_DFLT_0	A hput ACK	No
	allowed. Provide		
	sound from an		
	AEIO_InSpecH, at		
	the quality described.		
	AEIO_GetSound(
	AEIO_BasicData _		
	→ *basic_		
	→dataP,		
	AEIO_InSpecH _		
	inH,		
	AEIO_SndQuality _		
	→		
	⇔quality,		
	const AEIO_		
	<pre>→InterruptFuncs _</pre>		
	→*Interrupt_ →funcsP0,		
	const A_Time		
	const A_Time _		
	→ *durPT,		
	A_u_long _		
	⇔sampLu,		
	A_u_long _		
	↔ num_		
	⇔samplesLu,		
	void		
	AEIO_SndQuality		
	may be:		
	•		
	AEIO_SndQuality	v APPROX.	
	(this quality is used		
	to draw the audio		
	waveform)		
	•		
	AEIO_SndQuality	y_LO,	
	• AEIO_SndQuality	ү _НІ	

Table 1 – continued from previous page

Function	Response	l or O?	Required?
	maeEIO_Err_USE_DFLT_(Yes
AE10_INQNextFlame1	allowed. Provide the time	Anputack	105
	of the next frame (in		
	the source footage's		
	timebase) within the		
	1		
	AEIO_InSpecH.		
	AEIO_		
	<pre>→InqNextFrameTime(</pre>		
	AEIO_BasicData _		
	→*basic_dataP,		
	AEIO_InSpecH _		
	⇔inH,		
	const A_Time _ →*base_time_tr,		
	AETO TimoDin		
	→time_dir,		
	A_Boolean		
	→*found0,		
	A_Time		
	→*key_time_tr0);		
7770 7 110 1		-0-12-12-1	V
AE10_InitOutputSpe	AEIO_Err_USE_DFLT_(Yes
	allowed. Perform any ini-		
	tialization necessary for a		
	new AEIO_OutSpecH,		
	and indicate whether you		
	made changes.		
	AEIO_		
	→InitOutputSpec(
	AEIO_BasicData _		
	→*basic_dataP,		
	AEIO_OutSpecH _		
	→outH,		
	A_Boolean _		
	<pre>→interacted);</pre>		
	NOTE: The first time		
	your AEIO is used, After		
	Effects caches the last-		
	known-good optionsH in		
	its preferences. When		
	testing this function,		
	delete your preferences		
	often.		

Table 1 – continued from previous page

Function	Response	l or O?	Required?
	-		-
AEIO_GetFlatOutput(-	Output	Yes
	→GetFlatOutputOption AEIO_BasicData →*basic_dataP, AEIO_OutSpecH →outH, AEIO_Handle →*optionsH);		N.
AEIO_DisposeOutput(pAEION_Err_USE_DFLT_0 allowed. Free the memory for the output options passed in. AEIO_ →DisposeOutputOption AEIO_BasicData _ →*basic_dataP, void →*optionsPV);		No
AEIO_UserOptionsDia	IDisplay an output settings dialog (select TIFF output within After Effects to see when this dialog will occur). Store this information in an options handle using AEGP_SetInSpecOption AEIO_ →UserOptionsDialog(AEIO_BasicData →*basic_dataP, AEIO_OutSpecH →outH, PF_EffectWorld →*sample0, A_Boolean →*interacted0);	Output	No

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_GetOutputInfo	Describe (in text) the output options in an AEIO_OutSpecH.		·
	AEIO_GetOutputInfo(AEIO_BasicData _ →*basic_dataP, AEIO_OutSpecH _ →outH, AEIO_Verbiage _ →*verbiage);		
AEIO_OutputInfoChar		Output	No
	AEIO_OutSpecH based on the current settings (using the various Get functions to obtain them).		
	AEIO_ →OutputInfoChanged(AEIO_BasicData _ →*basic_dataP, AEIO_OutSpecH _ →outH);		
AEIO_SetOutputFile	AEIO_Err_USE_DFLT_Callowed. Set the file path for output of an AEIO_OutSpecH. Return AEIO_Err_USE_DEFAUL	•	Yes
	unless you've changed the path. The file path is a NULL-terminated UTF-16 string with platform separators.		
	AEIO_SetOutputFile(AEIO_BasicData _ →*basic_dataP, AEIO_OutSpecH _ →outH, A_UTF16Char _ →*file_pathZ);		

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_StartAdding	Prepare to add frames to the output file. This is a good time to create the ouput file(s) on disk, and to write any header information to such files. This is also your first opportunity to allocate pixel buffers based on valid output spec values.	Output	Yes, for writing formats that support multiple frames
	AEIO_StartAdding(AEIO_BasicData		
AEIO_AddFrame	Add frame(s) to output file. You may pass a pointer to a function you want called if the user interrupts the render. AEIO_AddFrame(Output	Yes, for writing formats that support multiple frames

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_EndAdding	Perform any clean-up associated with adding frames. AEIO_EndAdding(Output	Yes, for writing formats that support multiple frames
	AEIO_BasicData _ →*basic_dataP, AEIO_OutSpecH _ →outH,		
	A_long		
AEIO_OutputFrame	Output a single frame. AEIO_OutputFrame(AEIO_BasicData _	Output	Yes, for writing formats that support a single frame
AEIO_WriteLabels	AEIO_Err_USE_DFLT_Callowed. Set alpha interpretation and field usage information for the AEIO_OutSpecH. Indicate in AEIO_LabelFlags which flags you wrote. AEIO_WriteLabels(Yes
AEIO_GetSizes	AEIO_Err_USE_DFLT_C allowed. Provide infor- mation about file size and remaining free space on output volume. AEIO_GetSizes(AEIO_BasicData	AOutpa ick	Yes

Table 1 – continued from previous page

Function	Response	I from previous page	Required?
AEIO_Flush	Destroy any options or user data associated with the OutSpecH. AEIO_Flush(AEIO_BasicData _ →*basic_dataP, AEIO_OutSpecH _ →outH);		
AEIO_AddSoundChunk	Add the given sound to the output file. AEIO_AddSoundChunk(AEIO_BasicData _	Output	Yes, for writing formats with audio
AEIO_Idle	Optional. Do something with idle time. AEIO_Err_USE_DFLT_(is not supported.) AEIO_Idle(Output CALLBACK	No
AEIO_GetDepths	Set AEIO_OptionsFlags to indicate which pixel and color depths are valid for your output format. See the discussion on Export Bit-Depth. AEIO_GetDepths(Output	Yes

Table 1 – continued from previous page

Function	Response	I or O?	Required?
	AEIO_Err_USE_DFLT_C allowed. Describe the three character extension for the output file. AEIO_ →GetOutputSuffix(AEIO_BasicData →*basic_dataP, AEIO_OutSpecH →outH, A_char →*suffix);		Yes
AEIO_SeqOptionsDlg	Display a footage options dialog, and indicate whether the user made any changes. AEIO_SeqOptionsDlg(AEIO_BasicData	Input	No
AEIO_GetNumAuxChann	Desimerate the auxiliary (beyond red, green, blue and alpha) channels of data contained in an AEIO_InSpecH. AEIO_ →GetNumAuxChannels(AEIO_BasicData →*basic_dataP, AEIO_InSpecH →inH, A_long →*num_channelsPL);	Input	No

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_GetAuxChannelI	-	Input	No
AETO_GetAuxchanner	name, channel, and dimensionality of an auxiliary data channel.	mput	NO
	AEIO_ →GetAuxChannelDesc(AEIO_BasicData _ →*basic_dataP, AEIO_InSpecH →inH, long →chan_indexL, PF_ChannelDesc _ →*descP);		
AEIO_DrawAuxChannel	Draw the auxiliary		
TETO_DTamitationalines	channel(s) from an AEIO_InSpecH.		
	AEIO_ →DrawAuxChannel(AEIO_BasicData → *basic_ →dataP, AEIO_InSpecH → inH, A_long → chan_ →indexL, const AEIO_ →DrawFramePB →*pbP, PF_ChannelChunk → *chunkP);		
AEIO_FreeAuxChannel	Free data associated with an auxiliary channel. AEIO_ →FreeAuxChannel(AEIO_BasicData →*basic_dataP, AEIO_InSpecH →inH, PF_ChannelChunk →*chunkP);	Input	No

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_Num AuxFiles	Enumerate the files	Input	No
	needed to render the	•	
	given AEIO_InSpecH.		
	This function and		
	AEIO_GetNthAuxFileS	pec	
	will be called when the		
	user chooses File >		
	Dependencies >		
	Collect Files		
	Here your AEIO tells AE		
	what the associated files		
	are.		
	AEIO_NumAuxFiles(
	AEIO_BasicData _		
	⇔*basic_dataP,		
	AEIO_InSpecH _		
	⇔seqH,		
	A_long		
	→framePL);		
AEIO_GetNthAuxFileS		Input	No, if no aux files
	nth auxiliary file, for		
	the specified frame.		
	The path is a handle		
	to a NULL-terminated		
	A_UTF16Char string, and		
	must be disposed with		
	AEGP_FreeMemHandle.		
	AEIO_		
	GetNthAuxFileSpec(
	AEIO_BasicData_		
	→*basic_dataP,		
	AEIO_InSpecH _ ⇔seqH,		
	7 1000		
	A_10Ng		
	A_long n,		
	AEGP_MemHandle_		
	<pre>→*pathPH);</pre>		

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_CloseSourceFil	-	Input	Yes
	pending upon closeB) the source files for an AEIO_InSpecH. When the user Collects Files, the AEIO will first be asked to close its source files, then re-open them. AEIO_ CloseSourceFiles(AEIO_BasicData **basic_dataP, AEIO_InSpecH SeqH, A_Boolean CloseB);		
	TRUE for close, FALSE for open.		
AEIO_CountUserData	Enumerate the units of user data associated with the AEIO_InSpecH. AEIO_CountUserData(AEIO_BasicData		
AEIO_SetUserData	Set user data (of the given index and type) for the given AEIO_OutSpecH. AEIO_SetUserData (AEIO_BasicData	Output	No

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_GetUserData	Describe the user data (at the index and of the type given) associated with the AEIO_InSpecH. AEIO_GetUserData (AEIO_BasicData	Input	No
AEIO_AddMarker	Associate a marker of the specified type, at the specified frame, with the AEIO_OutSpecH. You may provide an interrupt function to handle user cancellation of this action. AEIO_AddMarker(AEIO_BasicData	Output	No

Table 1 – continued from previous page

Function	Response	I or O?	Required?
AEIO_VerifyFileImpo	-	Input	No
	portablePB) whether	-	
	or not the plug-in can		
	import the file. Note		
	that After Effects has		
	already done basic ex-		
	tension checking; you		
	may wish to open the file		
	and determine whether		
	or not it's valid. This		
	can be a time-consuming		
	process; most AEIOs that		
	ship with After Effects		
	simply return TRUE, and		
	deal with bad files during		
	AEIO_InitInSpecFror	hFile.	
	The file path is a NULL-		
	terminated UTF-16 string		
	with platform separators.		
	AEIO_		
	→VerifyFileImportabl	e (
	AEIO_BasicData _		
	⇔dataP,		
	AEIO_		
	→ModuleSignature _		
	⇒sig, const A_		
	→UTF16Char		
	→*file_pathZ,		
	A_Boolean		
	⇔ ⊔		
	<pre>→*importablePB);</pre>		
AEIO_UserAudioOptio	n Bignlay and audio ontions	Output	No
1.2.10_00011144100pc14	dialog.	- Carpar	1.0
	AEIO_	100/	
	→UserAudioOptionsDia AEIO_BasicData _	110g (
	→*basic_dataP,		
	AEIO_OutSpecH		
	outH,		
	A_Boolean _		
	→*interacted0);		

Table 1 – continued from previous page

Function	Response	l or O?	Required?
AEIO_AddMarker3	Add a marker, with a flag specifying whether or not this is a composition marker. AEIO_AddMarker3(Output	No No
	→ frame_ →index, AEGP_ →ConstMarkerValP → marker_valP, AEIO_ →RenderMarkerFlag_ → marker_flag, AEIO_ →InterruptFuncs → *inter0);		
AEIO_GetMimeType	Describe the output mime type. This is used for XMP support. AEIO_GetMimeType(AEIO_BasicData	Output	No

72.2 What Goes In

These functions manage an input specification, After Effects' internal representation of data gathered from any source.

Any image or audio data in After Effects (except solids) is obtained from an input specification handle, or AEIO_InSpecH.

72.2.1 AEGP_IOInSuite5

72.2. What Goes In 381

Function	Purpose
AEGP_GetInSpecOptionsHandle	Retrieves the options data (created by your AEIO) for the given AEIO_InSpecH.
	<pre>AEGP_GetInSpecOptionsHandle(AEIO_InSpecH inH, void</pre>
AEGP_SetInSpecOptionsHandle	Sets the options data for the given AEIO_InSpecH. Must be allocated using the <i>Memory Suite</i> .
	<pre>AEGP_SetInSpecOptionsHandle(AEIO_InSpecH inH, void *optionsPV, void **old_optionsPPV);</pre>
AEGP_GetInSpecFilePath	Retrieves the file path for the AEIO_InSpecH. The file path is a handle to a NULL-terminated A_UTF16Char string, and must be disposed with AEGP_FreeMemHandle.
	AEGP_GetInSpecFilePath(AEIO_InSpecH inH, AEGP_MemHandle *file_nameZ);
AEGP_GetInSpecNativeFPS	Retrieves the frame rate of the AEIO_InSpecH.
	<pre>AEGP_GetInSpecNativeFPS(AEIO_InSpecH inH, A_Fixed *native_fpsP);</pre>
AEGP_SetInSpecNativeFPS	Sets the frame rate of the AEIO_InSpecH.
	AEGP_SetInSpecNativeFPS(AEIO_InSpecH inH, A_Fixed native_fpsP);
AEGP_GetInSpecDepth	Retrieves the bit depth of the image data in the AEIO_InSpecH.
	AEGP_GetInSpecDepth(AEIO_InSpecH inH, A_short *depthPS);
AEGP_SetInSpecDepth	Indicates to After Effects the bit depth of the image data in the AEIO_InSpecH.
	AEGP_SetInSpecDepth(AEIO_InSpecH inH, A_short depthS);
AEGP_GetInSpecSize	Retrieves the size (in bytes) of the data referenced by the AEIO_InSpecH.
	AEGP_GetInSpecSize(AEIO_InSpecH inH, AEIO_FileSize *sizePLLu);

Table 2 – continued from previous page

Function	Purpose
AEGP_SetInSpecSize	Indicates to After Effects the size (in bytes) of the data referenced by the AEIO_InSpecH.
	AEGP_SetInSpecSize(AEIO_InSpecH inH, AEIO_FileSize sizeL);
AEGP_GetInSpecInterlaceLabel	Retrieves field information for the AEIO_InSpecH.
	<pre>AEGP_GetInSpecInterlaceLabel(AEIO_InSpecH inH, FIEL_Label *interlaceP);</pre>
AEGP_SetInSpecInterlaceLabel	Specifies field information for the AEIO_InSpecH.
	AEGP_SetInSpecInterlaceLabel(AEIO_InSpecH inH, const FIEL_Label *interlaceP);
AEGP_GetInSpecAlphaLabel	Retrieves alpha channel interpretation information for the AEIO_InSpecH.
	AEGP_GetInSpecAlphaLabel(AEIO_InSpecH inH, AEIO_AlphaLabel *alphaP);
AEGP_SetInSpecAlphaLabel	Sets alpha channel interpretation information for the AEIO_InSpecH.
	AEGP_SetInSpecAlphaLabel(AEIO_InSpecH inH, const AEIO_AlphaLabel* alphaP);
AEGP_GetInSpecDuration	Retrieves the duration of the AEIO_InSpecH.
	AEGP_GetInSpecDuration(AEIO_InSpecH inH, A_Time *durationP);
AEGP_SetInSpecDuration	Sets the duration of the AEIO_InSpecH. NOTE: As of 5.5, this must be called, even for frame-based file formats. If you don't set the A_Time. scale to something other than zero, your file(s) will not import. This will be fixed in future versions.
	AEGP_SetInSpecDuration(AEIO_InSpecH inH, const A_Time *durationP);
AEGP_GetInSpecDimensions	Retrieves the width and height of the image data in the AEIO_InSpecH.
	AEGP_GetInSpecDimensions(AEIO_InSpecH inH, A_long *widthPL0, A_long *heightPL0);

72.2. What Goes In 383

Table 2 – continued from previous page

Table 2 – continued from previous page Function Purpose	
Purpose PSS and the little of	
Indicates to After Effects the width and height of the image data in the AEIO_InSpecH.	
AEGP_SetInSpecDimensions(AEIO_InSpecH inH, A_long widthL, A_long heightL);	
Retrieves the width, height, bounding rect, and scaling factor applied to an AEIO_InSpecH.	
AEGP_InSpecGetRationalDimensions(AEIO_InSpecH inH, const AEIO_RationalScale *rs0, A_long *width0, A_long *height0, A_Rect *r0);	
Retrieves the horizontal scaling factor applied to an AEIO_InSpecH.	
AEGP_GetInSpecHSF(AEIO_InSpecH inH, A_Ratio *hsf);	
Sets the horizontal scaling factor of an AEIO_InSpecH.	
<pre>AEGP_SetInSpecHSF(AEIO_InSpecH inH, const A_Ratio *hsf);</pre>	
Obtains the sampling rate (in samples per second) for the audio data referenced by the AEIO_InSpecH.	
AEGP_GetInSpecSoundRate(AEIO_InSpecH inH, A_FpLong *ratePF);	
Sets the sampling rate (in samples per second) for the audio data referenced by the AEIO_InSpecH.	
AEGP_SetInSpecSoundRate(AEIO_InSpecH inH, A_FpLong rateF);	
Obtains the encoding method (signed PCM, unsigned PCM, or floating point) from an AEIO_InSpecH.	
AEGP_GetInSpecSoundEncoding(AEIO_InSpecH inH, AEIO_SndEncoding *encodingP);	
Sets the encoding method of an AEIO_InSpecH.	
AEGP_SetInSpecSoundEncoding(
AEIO_InSpecH inH, AEIO_SndEncoding encoding);	

Table 2 – continued from previous page

Function	Purpose
AEGP_GetInSpecSoundSampleSize	Retrieves the bytes-per-sample (1,2, or 4) from an AEIO_InSpecH.
	AEGP_GetInSpecSoundSampleSize(AEIO_InSpecH inH, AEIO_SndSampleSize *bytes_per_smpP);
AEGP_SetInSpecSoundSampleSize	Set the bytes per sample of an AEIO_InSpecH. AEGP_SetInSpecSoundSampleSize(AEIO_InSpecH inH, AEIO_SndSampleSize bytes_per_sample);
AEGP_GetInSpecSoundChannels	Determines whether the audio in the AEIO_SndChannels is mono or stereo. AEGP_GetInSpecSoundChannels(AEIO_InSpecH inH, AEIO_SndChannels *num_channelsP);
AEGP_SetInSpecSoundChannels	Sets the audio in an AEIO_SndChannels to mono or stereo. AEGP_SetInSpecSoundChannels(AEIO_InSpecH inH, AEIO_SndChannels num_channels);
AEGP_AddAuxExtMap	If your file format has auxiliary files which you want to prevent users from opening directly, pass it's extension, file type and creator to this function to keep it from appearing in input dialogs. AEGP_AddAuxExtMap(const A_char *extension, A_long file_type, A_long creator);

72.2. What Goes In 385

Table 2 – continued from previous page

Function Table 2 – continued	Purpose
AEGP_SetInSpecEmbeddedColorProfile	In case of RGB data, if there is an embedded icc profile, build an AEGP_ColorProfile out of this icc profile using AEGP_GetNewColorProfileFromICCProfile from AEGP_ColorSettingsSuite2 and set the profile description set to NULL. In case of non-RGB data, if there is an embedded non-RGB icc profile or you know the color space the data is in, set the color profile set to NULL, and provide the description as a NULL-terminated unicode string. Doing this disables color management UI that allows user to affect profile choice in the application UI. If you are unpacking non-RGB data directly into working space (to get working space use AEGP_GetNewWorkingSpaceColorProfile), you are done. If you are unpacking non-RGB data into specific RGB color space, you must pass the profile describing this space to AEGP_SetInSpecAssignedColorProfile below. Otherwise, your RGB data will be incorrectly interpreted as being in working space. Either color profile or profile description should be NULL in this function. You cannot use both. AEGP_SetInSpecEmbeddedColorProfile(AEIO_InSpecH inH, AEGP_ConstColorProfileP color_
	<pre>→profileP0, const A_UTF16Char *profile_ →descP0);</pre>
AEGP_SetInSpecAssignedColorProfile	Assign a valid RGB color profile to the footage. AEGP_SetInSpecAssignedColorProfile(AEIO_InSpecH inH, AEGP_ConstColorProfileP color_ →profileP);
AEGP_GetInSpecNativeStartTime	New in CC. Retrieves the native start time of the footage. AEGP_GetInSpecNativeStartTime(AEIO_InSpecH inH, A_Time *startTimeP);
AEGP_SetInSpecNativeStartTime	New in CC. Assign a native start time to the footage. AEGP_SetInSpecNativeStartTime(AEIO_InSpecH inH, const A_Time *startTimeP);

Table 2 – continued from previous page

Function	Purpose
AEGP_ClearInSpecNativeStartTime	New in CC. Clear the native start time of the footage. Setting the native start time to 0 using AEGP_SetInSpecNativeStartTime doesn't do this. It still means there is a special native start time provided. AEGP_ClearInSpecNativeStartTime(AEIO_InSpecH inH);
AEGP_GetInSpecNativeDisplayDropFrame	New in CC. Retrieve the drop-frame setting of the footage. AEGP_GetInSpecNativeDisplayDropFrame(AEIO_InSpecH inH, A_Boolean *displayDropFrameBP);
AEGP_SetInSpecNativeDisplayDropFrame	New in CC. Assign the drop-frame setting of the footage. AEGP_SetInSpecNativeDisplayDropFrame(AEIO_InSpecH inH, A_Boolean displayDropFrameB);

72.3 What Goes Out

These functions manage all interactions with an output specification in After Effects' render queue.

72.3.1 AEGPIOOutSuite4

Function	Purpose
AEGP_GetOutSpecOptionsHandle	Retrieves the Options for the AEIO_OutSpecH.
	AEGP_GetOutSpecOptionsHandle(
	AEIO_OutSpecH outH,
	<pre>void **optionsPPV);</pre>
AEGP_SetOutSpecOptionsHandle	Sets the Options for the AEIO_OutSpecH.
	AEGP_SetOutSpecOptionsHandle(
	AEIO_OutSpecH outH,
	<pre>void *optionsPV,</pre>
	<pre>void **old_optionsPPV);</pre>

Continued on next page

72.3. What Goes Out 387

Table 3 – continued from previous page

Function	Purpose
AEGP_GetOutSpecFilePath	Obtains the path for the AEIO_OutSpecH. The file path is a handle to a NULL-terminated A_UTF16Char string, and must be disposed with AEGP_FreeMemHandle. If file_rsrvdPB returns TRUE, the plug-in should not overwrite it (After Effects has already created an empty file); doing so can cause network renders to fail. AEGP_GetOutSpecFilePath(AEIO_OutSpecH outH, AEGP_MemHandle *unicode_pathPH, A_Boolean *file_rsrvdPB);
AEGP_GetOutSpecFPS	Obtains the frames per second of the AEIO_OutSpecH. AEGP_GetOutSpecFPS(AEIO_OutSpecH outH, A_Fixed *native_fpsP);
AEGP_SetOutSpecNativeFPS	Sets the frames per second of the AEIO_OutSpecH. AEGP_SetOutSpecNativeFPS(AEIO_OutSpecH outH, A_Fixed native_fpsP);
AEGP_GetOutSpecDepth	Obtains the pixel bit depth of the AEIO_OutSpecH. AEGP_GetOutSpecDepth(AEIO_OutSpecH outH, A_short *depthPS);
AEGP_SetOutSpecDepth	Sets the pixel bit depth of the AEIO_OutSpecH. AEGP_SetOutSpecDepth(AEIO_OutSpecH outH, A_short depthPS);
AEGP_GetOutSpecInterlaceLabel	Obtains field information for the AEIO_OutSpecH. AEGP_GetOutSpecInterlaceLabel(AEIO_OutSpecH outH, FIEL_Label *interlaceP);
AEGP_SetOutSpecInterlaceLabel	Set the field information for the AEIO_OutSpecH. AEGP_SetOutSpecInterlaceLabel(AEIO_OutSpecH outH, const FIEL_Label *interlaceP);
AEGP_GetOutSpecAlphaLabel	Obtains alpha interpretation information for the AEIO_OutSpecH. AEGP_GetOutSpecAlphaLabel(AEIO_OutSpecH outH, AEIO_AlphaLabel *alphaP);

Table 3 – continued from previous page

Function	Purpose
AEGP_SetOutSpecAlphaLabel	Sets the alpha interpretation for the AEIO_OutSpecH.
	AEGP_SetOutSpecAlphaLabel(AEIO_OutSpecH outH, const AEIO_AlphaLabel *alphaP);
AEGP_GetOutSpecDuration	Obtains the duration of the AEIO_OutSpecH.
	<pre>AEGP_GetOutSpecDuration(AEIO_OutSpecH outH, A_Time *durationP);</pre>
AEGP_SetOutSpecDuration	Sets the duration of the AEIO_OutSpecH.
	<pre>AEGP_SetOutSpecDuration(AEIO_OutSpecH outH, const A_Time *durationP);</pre>
AEGP_GetOutSpecDimensions	Obtains the dimensions of the AEIO_OutSpecH.
	AEGP_GetOutSpecDimensions(AEIO_OutSpecH outH, A_long *widthPL0, A_long *heightPL0);
AEGP_GetOutSpecHSF	Obtains the horizontal scaling factor of the AEIO_OutSpecH.
	AEGP_GetOutSpecHSF(AEIO_OutSpecH outH, A_Ratio *hsf);
AEGP_SetOutSpecHSF	Sets the horizontal scaling factor of the AEIO_OutSpecH.
	<pre>AEGP_SetOutSpecHSF(AEIO_OutSpecH outH, const A_Ratio *hsf);</pre>
AEGP_GetOutSpecSoundRate	Obtains the sampling rate for the AEIO_OutSpecH.
	AEGP_GetOutSpecSoundRate(AEIO_OutSpecH outH, A_FpLong *ratePF);
AEGP_SetOutSpecSoundRate	Sets the sampling rate for the AEIO_OutSpecH.
	AEGP_SetOutSpecSoundRate(AEIO_OutSpecH outH, A_FpLong rateF);
AEGP_GetOutSpecSoundEncoding	Obtains the sound encoding format of the AEIO_OutSpecH.
	AEGP_GetOutSpecSoundEncoding(AEIO_OutSpecH outH, AEIO_SndEncoding *encodingP);
	Continued on next next

72.3. What Goes Out 389

Table 3 – continued from previous page

Function	Purpose
AEGP_SetOutSpecSoundEncoding	Sets the sound encoding format of the AEIO_OutSpecH. AEGP_SetOutSpecSoundEncoding(AEIO_OutSpecH outH, AEIO_SndEncoding encoding);
AEGP_GetOutSpecSoundSampleSize	Obtains the bytes-per-sample of the AEIO_OutSpecH. AEGP_GetOutSpecSoundSampleSize(AEIO_OutSpecH outH, AEIO_SndSampleSize *bpsP);
AEGP_SetOutSpecSoundSampleSize	Sets the bytes-per-sample of the AEIO_OutSpecH. AEGP_SetOutSpecSoundSampleSize(AEIO_OutSpecH outH, AEIO_SndSampleSize bpsP);
AEGP_GetOutSpecSoundChannels	Obtains the number of sounds channels in the AEIO_OutSpecH. AEGP_GetOutSpecSoundChannels(AEIO_OutSpecH outH, AEIO_SndChannels *channelsP);
AEGP_SetOutSpecSoundChannels	Sets the number of sounds channels in the AEIO_OutSpecH. AEGP_SetOutSpecSoundChannels(AEIO_OutSpecH outH, AEIO_SndChannels channels);
AEGP_GetOutSpecIsStill	Determines whether the AEIO_OutSpecH is a still. AEGP_GetOutSpecIsStill(AEIO_OutSpecH outH, A_Boolean *is_stillPB);
AEGP_GetOutSpecPosterTime	Obtains the time of the AEIO_OutSpecH's poster frame. AEGP_GetOutSpecPosterTime(AEIO_OutSpecH outH, A_Time *poster_timeP);
AEGP_GetOutSpecStartFrame	Obtains the time of the first frame in the AEIO_OutSpecH. AEGP_GetOutSpecStartFrame(AEIO_OutSpecH outH, A_long *start_frameP);
AEGP_GetOutSpecPullDown	Obtains the pulldown phase of the AEIO_OutSpecH. AEGP_GetOutSpecPullDown(AEIO_OutSpecH outH, AEIO_Pulldown *pulldownP);

Table 3 – continued from previous page

Function	Purpose		
AEGP_GetOutSpecIsMissing	Passes back TRUE if there is no AEIO_OutSpecH.		
	AEGP_GetOutSpecIsMissing(AEIO_OutSpecH outH, A_Boolean *missingPB);		
AEGP_GetOutSpecShouldEmbedICCProfile	Returns TRUE if the AEIO should embed a color profile in the output.		
	AEGP_GetOutSpecShouldEmbedICCProfile(AEIO_OutSpecH outH, A_Boolean *embedPB);		
AEGP_GetNewOutSpecColorProfile	Returns an (opaque) ICC color profile for embedding in the AEIO's output. Must be disposed with AEGP_DisposeColorProfile.		
	AEGP_GetNewOutSpecColorProfile(AEGP_PluginID		
AEGP_GetOutSpecOutputModule	Returns the AEGP_RQItemRefH and AEGP_OutputModuleRefH associated with the given AEIO_OutSpecH. Fails if the render queue item is not found, or if AEIO_OutSpecH is not a confirmed outH and is a copy, i.e. if the Output Module settings dialog is open and the user hasn't hit OK.		
	AEGP_GetOutSpecOutputModule(AEIO_OutSpecH outH, AEGP_RQItemRefH *rq_itemP, AEGP_OutputModuleRefH *om_refP);		

72.3. What Goes Out 391

Implementation Details

73.1 Export Bit-Depth

In the Output Module Settings, the user can choose a Depth based on the options the AEIO declares support for in AEIO_GetDepths() from AEIO_FunctionBlock4.

If a plug-in supports higher bit-depth exports, it should be able to handle these higher bit-depth PF_EffectWorlds passed in AEIO_AddFrame() or AEIO_OutputFrame(), even when the export setting is not set to the same depth.

The frame delivered to the AEIO, and the final output will not necessarily be the same depth.

You may get frames passed in the project bit-depth instead of the final output if After Effects thinks that will be higher quality.

73.2 User Data vs. Options

It's possible to use either user data allocations or options handles to store metadata about a file.

We use user data for information that's to be embedded in the file (presuming the file format supports such information); marker data, field labels, etc.

We use option handles for information about the file; output settings, dimensions, details of compression settings used.

Premiere Pro & Other Hosts

Adobe Premiere Pro and Adobe Premiere Elements both support the After Effects effect API as described in chapters 2, 3, and 5.

They offer a thorough host implementation, some the key omissions being 3D-related calls (auxiliary channel information, cameras and lights), 16-bit and SmartFX support, and other utility functions provided by After Effects' AEGP API.

Both Premiere Pro and Premiere Elements set PF_InData>appl_id to 'PrMr'.

In this chapter, we will describe the AE API support in Premiere Pro, but generally the same support exists in corresponding versions of Premiere Elements.

If you need to distinguish between Premiere Pro and Premiere Elements, you may use the Premiere-specific App Info Suite, available from the Premiere Pro SDK headers.

Application Versions	PF_InData> ver- sion.major	PF_InData> ver- sion.minor
Premiere Pro CC through Premiere Pro CC 2019	13	4
Premiere Pro CS6	13	2
Premiere Pro CS5.5	13	1
Premiere Pro CS5, Premiere Elements 9	13	0
Premiere Pro CS4, Premiere Elements 8	12	5
Premiere Pro CS3, Premiere Elements 4 and 7	12	4
Premiere Pro 2.0, Premiere Elements 3	12	3
Premiere Pro 1.5, Premiere Elements 2	12	2
Premiere Pro 1.0, Premiere Elements 1	12	1

Note that the versioning used by Premiere Pro and Premiere Elements does not mean that they support the same API features After Effects did at the same version. It is simply meant to distinguish from one version to the next.

Plug-in Installation

Use the common plug-in folder as described here: Where Installers Should Put Plug-ins.

If you try to install an effect plug-in only to the Premiere Pro plug-ins directory, you will be surprised to find that your effect is not rendered when you export to disk through Adobe Media Encoder, an entirely separate application.

Oh, and you'll also miss out on project interchange and copy / paste between Premiere Pro and After Effects.

Basic Host Differences

We've tried to provide robust compatibility for After Effects effect plug-ins in Premiere Pro.

There are underlying differences in the render pipeline that lead to differences, and we realize the API implementation may not be perfect.

Below is an overview of some differences the plug-in will encounter when running in Premiere Pro.

76.1 Time Values

Premiere Pro uses slightly different time values in PF_InData. For example in CS4:

Rendering in NTSC, time_scale is 60000, time_step is 1001, field gives field order (in After Effects, for field rendering, scale is 2997, step is 50, or for progressive rendering, scale is 2997, step is 100).

Rendering in PAL, time_scale is 50, time_step is 1, field gives field order (in After Effects, for field rendering, scale is 3200, step is 64, or for progressive rendering, scale is 3200, step is 128.

It's the ratio of time-related values that produces the time value, not specifically the time_scale value. It's possible Premiere Pro will use different time_scales in the future, so please don't hard code. Just be aware that it does not necessarily use the exact same values as After Effects.

76.2 Rendering Frames

Premiere is optimized for responsive editing. When scrubbing in the timeline, and changing effect parameters, Premiere will immediately request a low-quality render for immediate display, followed by a high-quality render. So the effect may receive two requests for the same effective time, one at a low resolution, low bit-depth, followed by one at full-resolution, full bit-depth. The resolution requested for each render with take into account the Playback and

Paused Resolution set in the Source and Program Monitors: The first request will be at the Playback Resolution, and the second request will be at the Paused Resolution.

Premiere will also perform speculative rendering, to render a set of frames ahead in the timeline, so that if/when the editor starts playback, the initial frames will be ready. This means that when repositioning the time needle, or when changing effect parameters, Premiere will ask the effect to render a set of frames ahead of the current time. If the frames have previously been rendered and cached, the effect will not see these render requests because the cached frames will be used.

When rendering frames in Premiere-native pixel formats, Premiere will send PF_Cmd_RENDER once for each field, rather than for each frame. The PF_InData->field will indicate which field is being rendered, the PF_LayerDef->height will be half of the frame height, and the PF_LayerDef->rowbytes will be double the normal value.

76.3 Render Order

Premiere Pro was built to provide real-time playback of footage with effects wherever possible. The render scheduling is much more aggressive and multithreaded rendering is a basic requirement. This is quite different than After Effects, where users are building layers upon layers of effects and more willing to wait for a RAM preview.

Multithreaded rendering in Premiere applies to AE effects too. When rendering an AE effect, the request from Premiere passes through a critical section which is used for all commands, except those relating to arbitrary data. The critical section prevents two threads from calling the same instance of the effect at the same time. However, Premiere creates multiple instances of the effect, which can be called concurrently from separate threads.

Therefore, an effect should not expect to receive render requests in order of increasing time. Also, effects should not depend on static, non-constant variables.

76.4 Frame Dimensions

Differences between source footage and the project/composition are handled differently.

For example, in CS4, when importing an NTSC clip in a PAL sequence, PF_InData>width, height are (598, 480) and PF_InData->pixel_aspect_ratio is (768, 702).

In AE, width, height are (720, 480) and pixel_aspect_ratio is (10, 11).

76.5 PF_InData

Premiere Pro handles field rendering differently than After Effects. While field rendering, PF_InData>field gives the current field being rendered, ignoring whether or not PF_OutFlag_PIX_INDEPENDENT flag was set.

In Premiere Pro, effects receive the quality setting of the monitor window in *PF_InData>quality*. This differs from After Effects, where the source layer's quality setting is provided here.

76.6 Parameter UI

Premiere Pro does not honor the *PF_ParamFlag_START_COLLAPSED* flag. Parameters are always initialized with their twirlies collapsed, and cannot be automatically twirled open by parameter supervision.

Premiere Pro supports the macro PF_ADD_FLOAT_EXPONENTIAL_SLIDER(), which lets you define an exponent. Although this macro is newly added for the CC 2015 release 2 SDK, Premiere Pro has used this for some time in the Fast Color Corrector, in the Input Grey Level parameter. The exponent is used so that although the range is from 0.10 to 10, 1.0 is about in the middle of the slider. The exponent we used was 2.5. Typical values would be from 0.01 to 100.

Starting in CC 2015, effects will not be sent PF_Cmd_UPDATE_PARAMS_UI or PF_Event_DRAW when the time needle is moved and there are no keyframes, unless the effect sets PF_OutFlag_NON_PARAM_VARY. Effects such as those that draw histograms in the Effect Controls panel will need to be aware of this optimization.

76.7 Missing Suites

Many suites supported by After Effects are not implemented in the Premiere Pro host. In several cases, even if a suite is missing in Premiere Pro, an equivalent macro function is available. Here are a few examples:

After Effects suite call	Premiere Pro equivalent function		
WorldTransformSuite1()->copy()	PF_COPY()		
WorldTransformSuite1()->convolve()	in_data->utils->convolve()		
FillMatteSuite2()->fill()	PF_FILL()		
<pre>PF_PixelDataSuite1->get_pixel_data8()</pre>	PF_GET_PIXEL_DATA8()		

The sample projects demonstrate alternate ways of handling a missing suite, by checking for the host application and version. The Portable sample project demonstrates both host application and version checking.

76.8 A Special Suite for AE Effects Running in Premiere Pro

No AEGP calls are supported by Premiere Pro. However, there are some interesting parallels in the header PrSDKAE-Support.h. For example, you can use the Utility Suite in that header to get the frame rate or field type of the source footage, or to get the speed applied to the clip.

Note that other suites from the Premiere Pro SDK cannot be used in AE effects.

76.6. Parameter UI 401

			. 7	7
CHA	PT	ΕB	<i>\</i>	

Multithreading

You may have noticed this flag: $PF_OutFlag2_PPRO_DO_NOT_CLONE_SEQUENCE_DATA_FOR_RENDER$. We advise against setting this flag, as it has been found to cause parameter UI problems.

Bigger Differences

As long as an effect only supports the basic ARGB_8u pixel format supported by After Effects, Premiere Pro will try to imitate the After Effects hosting behavior and hide various differences because of the different render pipeline architecture. But if an effect wants to support additional pixel formats, such as 32-bit RGB, be prepared to handle further divergent behavior.

78.1 Pixel Formats

Premiere Pro provides function suites for declaring support for pixel formats other than the 8-bit RGB format used by After Effects - ARGB_8u. These pixel formats include the Premiere Pro native 8-bit RGB format - BGRA_8u, as well as YUV, 32-bit formats, and more. For a more detailed discussion of the various pixel formats, see the Premiere Pro SDK Guide, chapter 3, in the section "Pixel Formats and Colorspaces".

Use the PF Pixel Format Suite (defined in PrAESDKSupport.h) to register for *PF_EffectWorld / PF_LayerDef* in other pixel formats. Use the Premiere Pixel Format Suite (defined in the aptly-named PrSDKPixelFormatSuite.h) to get black and white values in those pixel formats.

After Effects functions such as PF_BLEND() have not been enhanced to work with pixel formats beyond 8-bit RGB.

78.2 32-Bit Float Support

Premiere Pro does not support After Effects 16-bit rendering or SmartFX. For 32-bit rendering in Premiere Pro, you'll need to declare support for one of the 32-bit pixel formats (see previous section), and then implement 32-bit rendering for PF_Cmd_RENDER. You can support multiple render depths this way. See the SDK Noise sample project for an example.

Depending on the clip(s) to which an effect is applied, 32-bit processing is not always necessary to preserve the quality of the source input. But there are settings to force 32-bit rendering, to give effects processing finer granularity and more

headroom, if desired. Go to Settings>Sequence Settings> Video Previews>Maximum Bit Depth, to control previewing from the timeline. For export to file, use Export Settings> Video> Basic Settings> Render at Maximum Depth.

78.3 PF_CHECKOUT_PARAM and Pixel Formats

Before CS6, PF_CHECKOUT_PARAM() only returned 8-bit ARGB buffers, regardless of the pixel format currently being used for rendering. Starting in CS6, an effect can opt in to get frames in the same format as the render request, whether it is 32-bit float, YUV, etc.

Plug-ins may request this behavior, but existing plug-ins will continue working receiving 8-bit ARGB frames. The call is EffectWantsCheckedOutFramesToMatch RenderPixelFormat(), in the PF Utility Suite, defined in PrSDKAE-Support.h. The call should be made on PF_Cmd_GLOBAL_SETUP, the same selector where an effect would already advertise support beyond 8-bit RGB using AddSupportedPixelFormat().

Plug-Ins... Reloaded

On it's first launch, Premiere Pro loads all the plug-ins, reads the PiPL, and sends PF_Cmd_GLOBAL_SETUP to determine the plug-ins' capabilities. To save time on future application launches, it saves some of these capabilities in what we call the plug-in cache (the registry on Windows, a Property List file on macOS). The next time the application is launched, the cached information is used wherever possible, rather than loading the plug-ins.

When debugging, you can always force a reload of all the plug-ins by holding down the Shift key when launching Premiere Pro.

If your effect needs to be reloaded each time, there is a way to disable this caching. The plug-in can use the PF Cache On Load Suite in AE_CacheOnLoadSuite.h (from the Premiere Pro SDK headers) to call PF_SetNoCacheOnLoad() during PF_Cmd_GLOBAL_SETUP. For the second parameter of that function, pass a non-zero value if you want your effect to show up in the UI. Pass zero if loading failed, but you still want Premiere Pro to attempt to load it again on the next relaunch.

Effects Presets

Premiere Pro uses a different preset scheme than After Effects.

From the Premiere Pro SDK Guide:

Effect presets appear in the Presets bin in the Effects panel, and can be applied just like Effects with specific parameter settings and keyframes. Effect presets can be created as follows:

- 1) Apply a filter to a clip
- 2) Set the parameters of the filter, adding keyframes if desired
- 3) Right-click on the filter name in the Effect Controls panel, and select "Save Preset..."
- 4) Create preset bins if desired by right-clicking in the Effects panel and choosing "New Presets Bin"
- 5) Organize the presets in the preset folders
- 6) Select the bins and/or presets you wish to export, right-click, and choose "Export Preset"

Presets should be installed in the Plug-ins directory. Once they are installed in that directory, they will be read-only, and the user will not be able to move them to a different folder or change their names. User-created presets will be modifiable.

On Windows Vista, these are in the user's hidden AppData folder (e.g. C:Users[user name]AppDataRoamingAdobePremiere Pro[version]Effect Presets and Custom Items.prfpset).

On macOS, they are in the user folder, at ~/Library/ Application Support/Adobe/Premiere Pro/[version]/Effect Presets and Custom Items.prfpset.

Custom ECW UI Over A Standard Data Type

While this is logged as bug #1235407, there is a simple workaround: Create two separate parameters, and have the custom UI control the slider param using parameter supervision.

Premiere Elements

Premiere Elements (but not Premiere Pro) displays visual icons for each effect. You will need to provide icons for your effects, or else an empty black icon will be shown for your effects, or even worse behavior in Premiere Elements 8.

The icons are 60x45 PNG files, and are placed here:

 $[Program\ Files] Adobe Adobe\ Premiere\ Elements\ [version] Plug-in Common Effect Previews$

The filename should be the match name of the effect, which you specify in the *PiPL Resources*, prefixed with "AE." So if the match name was "MatchName", then the filename should be "AE.MatchName.png"

Unsupported Features

Premiere Pro is currently known to not support the following features of the After Effects API:

(If you would like a feature with a "-" bullet, please email Premiere Pro API Engineering with the feature request. Numbers preceded by an 'F' are feature request numbers, and the others are bug numbers)

- F7233 extent_hint support
- F7835 Multiple PiPLs in a single plug-in
- F7836 AEGP support
- F7517 Audio support if a plug-in sets PF_OutFlag_I_USE_AUDIO in PF_Cmd_GLOBAL_SETUP, it will not be loaded at all
- F9355 Support PF_ParamFlag_COLLAPSE_TWIRLY
- PF World Transform Suite
- PF AE Channel Suite
- AE's implementation of high bit color depth support
- SmartFX
- 3D support
- PF_SUBPIXEL_SAMPLE(), PF_GET_PIXEL_DATA16()

83.1 But... Why'd You LOAD It If You Can't RUN It?!

Premiere Pro attempts to load AEGP plug-ins. To detect this and avoid any problem behavior, your command hook function can access a suite which is only provided by After Effects; AEGP_CanvasSuite is a fine candidate.

If the suite isn't present, return an error. The plug-in will be placed on Premiere Pro's "don't load these" list.

Other Hosts

For third-party hosts, the Adobe policy remains:

"Adobe neither supports nor recommends the creation of Adobe-compatible third-party hosts. While it may be possible to create a partially functional host by reverse engineering from the plug-in API specification, we do not recommend it and will not support you in doing so."

84.1 Reality Sandwich

We realize that, for developers like you, one good way to grow your market is to ensure that your plug-ins work in as many hosts as possible.

Our SmartFX API has created quite a bit of distance between the After Effects API and the implementations available in the rest of the plug-in hosting world.

We will do what we can to help the other hosts support newer features. If you encounter problems in third party hosts, please refer them to us if they need assistance.