
Windows Subsystem for Linux Guide Documentation

Release

Kenneth Reitz

Aug 30, 2017

Contents:

1	Background on WSL (Windows Subsystem for Linux)	3
1.1	What is WSL?	3
1.2	It's Beta Software	3
2	Installing WSL (Bash on Ubuntu on Windows)	5
2.1	Step 1: Enable Developer Mode	5
2.2	Step 2: Install WSL	5
2.3	Step 3: Create a Unix Account	5
2.4	Step 4: Enjoy!	5
3	Updating WSL	7
3.1	Updating Packages in WSL	7
3.2	Updating the Ubuntu OS	7
4	Common Gotchas	9
4.1	VIM Arrow Keys Don't Work	9
4.2	Sudo 'Unable to Resolve Host' Warning	9
4.3	Connecting to the Linux subsystem via SSH	9
5	GUI Applications	11
5.1	Step 1: Installing an X Server	11
5.2	Step 2: Set DISPLAY Environment Variable	11
6	Fun Packages to Install	13
6.1	Changing Your Shell	13
7	Indices and tables	15

Greetings, Earthling! Welcome to The Hitchhiker's Guide to the Windows Subsystem for Linux (WSL).

This is a living, breathing guide. If you'd like to contribute, [fork us on GitHub!](#)

This guide is also available in [Chinese](#).

This handcrafted guide exists to provide both novice and expert Windows and Linux developers a best practice handbook to the installation, configuration, and usage of WSL (Bash on Ubuntu on Windows) on a daily basis.

Background on WSL (Windows Subsystem for Linux)

What is WSL?

WSL is a full Ubuntu operating system that you can install on your Windows 10 machine.

It's Beta Software

Please keep in mind that this is beta software. This means that any part of it is subject to change, as feedback is collected and improvements are made based on community feedback.

In fact, if you have any issues you run into you, you can [open a GitHub issue](#) with Microsoft to let them know about it!

Microsoft's [Creator's Update](#) includes some improvements to the WSL that are not included in the regular release of Windows yet. The biggest one being that you can launch Windows programs from WSL.

Installing WSL (Bash on Ubuntu on Windows)

This document provides step-by-step instructions for installing WSL on your Windows machine.

Step 1: Enable Developer Mode

The first thing you need to do is enable developer mode on your Windows machine.

Go to **Settings -> Update and Security -> For developers**, and click “Developer mode”.

Step 2: Install WSL

Next, you need to install WSL.

Go to the Start Menu and search for “turn windows features on or off”. Select that, then check the “Windows Subsystem for Linux (Beta)” checkbox.

Hit OK. Restart your computer.

Step 3: Create a Unix Account

Next, we need to activate WSL from the command-line. Open up a Command Prompt and run the following command:

```
> bash
```

This will setup your Linux environment on Windows! If you see a blank screen at any point during this process, hit enter, and you’ll be prompted to create a new username for your Linux account.

Step 4: Enjoy!

Updating Packages in WSL

Because WSL uses a standard Ubuntu installation, upgrading your packages should look very familiar:

```
$ sudo apt-get update
$ sudo apt-get upgrade
```

Updating the Ubuntu OS

You can also upgrade to the latest version of Ubuntu with the following command (caution, this will take quite some time)!::

```
$ sudo -S apt-mark hold procps strace sudo
$ sudo -S env RELEASE_UPGRADER_NO_SCREEN=1 do-release-upgrade
```

And, it works, just as expected!

VIM Arrow Keys Don't Work

You may notice that by default, VIM's arrow keys don't work on your computer. To fix this, add the following to your `~/.vimrc`:

```
$ cat ~/.vimrc
set term=builtin_ansi
```

Sudo 'Unable to Resolve Host' Warning

You may notice that every time you run `sudo something`, your system complains that it cannot resolve its own hostname, but then continues on anyway. To fix this annoyance, you need to add your system's hostname to `/etc/hosts`:

```
$ cat /etc/hosts
127.0.0.1 localhost
127.0.0.1 nova
...
```

Here, my machine is called 'nova'.

Connecting to the Linux subsystem via SSH

In order to be able to ssh into your Linux subsystem instance follow the steps outlined by Master Azazel in this [thread](#):

1. `sudo apt-get remove openssh-server`
2. `sudo apt-get install openssh-server`
3. `sudo nano /etc/ssh/sshd_config` and disallow root login by setting `PermitRootLogin no`

4. Then add a line beneath it that says: `AllowUsers yourusername` and make sure `PasswordAuthentication` is set to `yes` if you want to login using a password.
5. Disable privilege separation by adding/modifying: `UsePrivilegeSeparation no`
6. `sudo service ssh --full-restart`
7. Connect to your Linux subsystem from Windows using a ssh client like PuTTY.

Step 1: Installing an X Server

In order to run GUI applications in WSL, you need to first install an X Server on your Windows machine. I recommend installing [Xming](#).

Step 2: Set DISPLAY Environment Variable

Next, you have to tell your WSL environment to use the X Server by setting the `DISPLAY` environment variable.

I added the following to my `~/ .bashrc`:

```
export DISPLAY=:0
```


CHAPTER 6

Fun Packages to Install

Changing Your Shell

CHAPTER 7

Indices and tables

- `genindex`
- `modindex`
- `search`