
xtensor-r

Feb 22, 2019

INSTALLATION

1	Enabling R arrays in your C++ libraries	3
2	Licensing	5
2.1	Installation	5
2.2	Basic Usage	6
2.3	Arrays and tensors	7
2.4	R Peculiarities	7
2.5	API reference	8
2.6	Releasing xtensor-r	11

R bindings for the `xtensor` C++ multi-dimensional array library.

What are `xtensor` and `xtensor-r`?

- `xtensor` is a C++ library for multi-dimensional arrays enabling numpy-style broadcasting and lazy computing.
- `xtensor-r` enables inplace use of R arrays with all the benefits from `xtensor`
 - C++ universal functions and broadcasting
 - STL - compliant APIs.

The [numpy to xtensor cheat sheet](#) from the `xtensor` documentation shows how numpy APIs translate to C++ with `xtensor`.

The Python bindings for `xtensor` are based on the [Rcpp](#) C++ library, which enables seamless interoperability between C++ and Python.

Enabling R arrays in your C++ libraries

Instead of exposing new types to R, `xtensor-r` enables the use of R data structures from C++ using R's C API.

In addition to the basic accessors and iterators of `xtensor` containers, it also enables using R arrays with `xtensor`'s expression system.

Besides `xtensor-r` provides an API to create *Universal functions* from simple scalar functions from your C++ code.

`xtensor` and `xtensor-r` require a modern C++ compiler supporting C++14. The following C++ compilers are supported:

- On Windows platforms, Visual C++ 2015 Update 2, or more recent
- On Unix platforms, gcc 4.9 or a recent version of Clang

We use a shared copyright model that enables all contributors to maintain the copyright on their contributions. This software is licensed under the BSD-3-Clause license. See the LICENSE file for details.

2.1 Installation

`xtensor-r` is a header-only C++ library. We maintain the conda package for `xtensor-r` and its dependencies.

Besides the `xtensor-r` headers, all these methods place the `cmake` project configuration file in the right location so that third-party projects can use `cmake`'s `find_package` to locate `xtensor-r` headers.

2.1.1 Using the conda package

A package for `xtensor-r` is available on the conda package manager.

```
conda install -c conda-forge xtensor-r
```

2.1.2 From source with cmake

You can also install `xtensor-r` from source with `cmake`. On Unix platforms, from the source directory:

```
mkdir build
cd build
cmake -DCMAKE_INSTALL_PREFIX=/path/to/prefix ..
make install
```

On Windows platforms, from the source directory:

```
mkdir build
cd build
cmake -G "NMake Makefiles" -DCMAKE_INSTALL_PREFIX=/path/to/prefix ..
nmake
nmake install
```

2.1.3 Using the R package

We also provide a R package for xtensor, which has been packaged for both conda and CRAN (Comprehensive R Archive Network). The repository for the R package is <https://github.com/QuantStack/Xtensor.R>.

To install the conda package:

```
conda install r-xtensor -c conda-forge
```

To install the R package from CRAN

```
install.packages("xtensor")
```

2.2 Basic Usage

2.2.1 Example : Use an algorithm of the C++ library on a R array inplace

C++ code

```
#include <numeric> // Standard library import for std::accumulate
#define STRICT_R_HEADERS // Otherwise a PI macro is defined in R
#include "xtensor/xmath.hpp" // xtensor import for the C++ universal_
→functions
#include "xtensor-r/rarray.hpp" // R bindings
#include <Rcpp.h>

using namespace Rcpp;

// [[Rcpp::plugins(cpp14)]]
// [[Rcpp::export]]
double sum_of_sines(xt::rarray<double>& m)
{
    auto sines = xt::sin(m); // sines does not actually hold values.
    return std::accumulate(sines.cbegin(), sines.cend(), 0.0);
}
```

R code:

```
v <- matrix(0:14, nrow=3, ncol=5)
s <- sum_of_sines(v)
s
```

Outputs

```
1.2853996391883833
```

Note that R places some restriction on what C++ types are usable. We've noted the differences in *R Peculiarities*.

2.3 Arrays and tensors

`xtensor-r` provides two container types wrapping R arrays: `rarray` and `rtensor`. They are the counterparts to `xarray` and `xtensor` containers.

2.3.1 rarray

Like `xarray`, `rarray` has a dynamic shape. This means that you can reshape the R array on the C++ side and see this change reflected on the R side. `rarray` doesn't make a copy of the shape, but reads it each time it is needed. Therefore, if a reference on a `rarray` is kept in the C++ code and the corresponding R array is then reshaped in the R code, this modification will reflect in the `rarray`.

2.3.2 rtensor

Like `xtensor`, `rtensor` has a static stack-allocated shape. This means that the shape of the R array is copied into the shape of the `rtensor` upon creation. As a consequence, reshapes are not reflected across languages. However, this drawback is offset by a more effective computation of shape and broadcast.

2.4 R Peculiarities

R supports only a subset of types available in C++. The types which are natively supported with `xtensor-R` are `int` (32 bit), `double`, `complex`, `byte`. Using other types (such as a C++ `float`) in a `rarray` or `rtensor` will fail to compile.

Below is a mapping from R to `xtensor`:

R type	xtensor type
Integer Vector	<code>rarray<int></code> or <code>rarray<int32_t></code>
Real Vector	<code>rarray<double></code>
Complex Vector	<code>rarray<std::complex<double>></code>
Raw Vector	<code>rarray<Rbyte></code> or <code>rarray<uint8_t></code>
Logical Vector	Not supported at the moment

Note that, for illustration purposes, `rarray` was used above. The `rtensor` container works just as well.

2.4.1 R's NA and NaN values

R encodes missing values (NAs) as special values of the underlying type.

`Xtensor-r` supports R's missing values with the `rarray_optional` and `rtensor_optional` counterparts to `rarray` and `rtensor` which enable operations with missing values with the `xoptional` API.

2.4.2 R defining PI as macro

Ancient versions of S used to define a `PI` macro. This macro collides with `xtensor`, as `xtensor` is using `PI` as a variable name in the numeric constants.

If you're encountering this issue, either reorder your headers so that the `xmath` header of `xtensor` is included before `Rcpp / xtensor-r` or use the following define before including `xtensor-r` and `Rcpp`:

```
#define STRICT_R_HEADERS
```

This prevents the `PI` macro definition.

2.5 API reference

2.5.1 Containers

`rarray`

```
template <class T>
```

```
class rarray : public xt::rcontainer<rarray<T>>, public xcontainer_semantic<rarray<T>>
```

Multidimensional container providing the `xtensor` container semantics to an R array.

`rarray` is similar to the `xarray` container in that it has a dynamic dimensionality. Reshapes of a `rarray` container are reflected in the underlying R array.

See *rtensor*

Template Parameters

- `T`: The type of the element stored in the `rarray`.

Constructors

```
rarray (const shape_type &shape)
```

Allocates an uninitialized `rarray` with the specified shape.

Parameters

- `shape`: the shape of the `rarray`

```
rarray (const shape_type &shape, const_reference value)
```

Allocates a `rarray` with the specified shape.

Elements are initialized to the specified value.

Parameters

- `shape`: the shape of the `rarray`
- `value`: the value of the elements

```
rarray (const value_type &t)
```

Allocates a `rarray` with nested initializer lists.

```
template <class S>
```

`rarray<T> from_shape (S &&shape)`
 Allocates and returns an rarray with the specified shape.

Parameters

- `shape`: the shape of the rarray

Copy semantic

`rarray (const self_type &rhs)`
 The copy constructor.

auto `operator= (const self_type &rhs)`
 The assignment operator.

Extended copy semantic

`template <class E>`
`rarray (const xexpression<E> &e)`
 The extended copy constructor.

`template <class E>`
 auto `operator= (const xexpression<E> &e)`
 The extended assignment operator.

rtensor

`template <class T, std::size_t N>`
`class rtensor : public xt::rcontainer<rtensor<T, N>>, public xcontainer_semantic<rtensor<T, N>>`
 Multidimensional container providing the xtensor container semantics wrapping an R array.

`rtensor` is similar to the `xtensor` container in that it has a static dimensionality.

Unlike the `rarray` container, `rtensor` cannot be reshaped with a different number of dimensions and reshapes are not reflected on the R side. However, `rtensor` has benefits compared to `rarray` in terms of performances. `rtensor` shapes are stack-allocated which makes iteration upon `rtensor` faster than with `pyarray`.

See [rarray](#)

Template Parameters

- `T`: The type of the element stored in the rarray.

Constructors

`rtensor ()`
 Allocates an uninitialized `rtensor`.

`rtensor (nested_initializer_list_t<T, N> t)`
 Allocates a `rtensor` with a nested initializer list.

`rtensor (const shape_type &shape)`
 Allocates an uninitialized `rtensor` with the specified shape and layout.

Parameters

- `shape`: the shape of the rtensor
- `l`: the `layout_type` of the rtensor

rtensor (**const** `shape_type &shape`, `const_reference value`)

Allocates a rtensor with the specified shape and layout.

Elements are initialized to the specified value.

Parameters

- `shape`: the shape of the rtensor
- `value`: the value of the elements
- `l`: the `layout_type` of the rtensor

Copy semantic

rtensor (**const** `self_type &rhs`)

The copy constructor.

auto **operator=** (**const** `self_type &rhs`)

The assignment operator.

Extended copy semantic

template <**class** E>

rtensor (**const** `xexpression<E> &e`)

The extended copy constructor.

template <**class** E>

auto **operator=** (**const** `xexpression<E> &e`)

The extended assignment operator.

roptional

template <**class** RC>

class `rcontainer_optional` : **public** `xoptional_assembly_base<rcontainer_optional<RC>>`, **public** `xcontainer_semantic`

Multidimensional container of optional values providing the xtensor container semantics to an R array.

`rcontainer_optional` is not meant to be used directly, but through the aliases `rarray_optional<T>` and `rtensor_optional<T, N>`.

Depending on the value type, optional values are reference proxies on R's `NA_INTEGER`, `NA_LOGICAL`, `NA_REAL`, `NA_STRING`, or `R_NilValue`.

Besides support for optionality, `rarray_optional` and `rtensor_optional` are similar to the `rarray` and `rtensor` respectively, with respect to dynamic and static dimensionality.

Template Parameters

- T: The type of the element stored in the rarray.

2.5.2 Numpy-style universal functions

rvectorize

```
template <class R, class... Args>
rvectorizer<R (*)(Args...), R, Args...> xt::rvectorize
    R (*)(Args...) Create numpy-style universal function from scalar function.
```

2.6 Releasing xtensor-r

2.6.1 Releasing a new version

From the master branch of xtensor-r

- Make sure that you are in sync with the master branch of the upstream remote.
- In file `xtensor_r_config.hpp`, set the macros for `XTENSOR_R_VERSION_MAJOR`, `XTENSOR_R_VERSION_MINOR` and `XTENSOR_R_VERSION_PATCH` to the desired values.
- Update the readme file w.r.t. dependencies on xtensor and pybind11.
- Stage the changes (`git add`), commit the changes (`git commit`) and add a tag of the form `Major.minor.patch`. It is important to not add any other content to the tag name.
- Push the new commit and tag to the main repository. (`git push`, and `git push --tags`)

2.6.2 Updating the conda-forge recipe

xtensor-r has been packaged for the conda package manager. Once the new tag has been pushed on GitHub, edit the conda-forge recipe for xtensor in the following fashion:

- Update the version number to the new `Major.minor.patch`.
- Set the build number to 0.
- Update the hash of the source tarball.
- Check for the versions of the dependencies.
- Optionally, rerender the conda-forge feedstock.

X

`xt::rarray` (*C++ class*), 8
`xt::rarray::from_shape` (*C++ function*), 8
`xt::rarray::operator=` (*C++ function*), 9
`xt::rarray::rarray` (*C++ function*), 8, 9
`xt::rcontainer_optional` (*C++ class*), 10
`xt::rtensor` (*C++ class*), 9
`xt::rtensor::operator=` (*C++ function*), 10
`xt::rtensor::rtensor` (*C++ function*), 9, 10
`xt::rvectorize` (*C++ function*), 11