
xsimd

Dec 25, 2018

INSTALLATION

1	Licensing	3
1.1	Installation	3
1.2	Basic usage	4
1.3	Writing vectorized code	5
1.4	Instruction set macros	8
1.5	Wrapper types	9
1.6	Data transfer	43
1.7	Mathematical functions	48
1.8	Aligned memory allocator	60

C++ wrappers for SIMD intrinsics.

SIMD (Single Instruction, Multiple Data) is a feature of microprocessors that has been available for many years. SIMD instructions perform a single operation on a batch of values at once, and thus provide a way to significantly accelerate code execution. However, these instructions differ between microprocessor vendors and compilers.

xsimd provides a unified means for using these features for library authors. Namely, it enables manipulation of batches of numbers with the same arithmetic operators as for single values. It also provides accelerated implementation of common mathematical functions operating on batches.

You can find out more about this implementation of C++ wrappers for SIMD intrinsics at the [The C++ Scientist](#). The mathematical functions are a lightweight implementation of the algorithms also used in [boost.SIMD](#).

xsimd requires a C++14 compliant compiler. The following C++ compilers are supported:

Compiler	Version
Microsoft Visual Studio	MSVC 2015 update 2 and above
g++	4.9 and above
clang	3.7 and above

The following SIMD instruction set extensions are supported:

Architecture	Instruction set extensions
x86	SSE2, SSE3, SSSE3, SSE4.1, SSE4.2, AVX, FMA3, AVX2
x86	AVX512 (gcc7 and higher)
x86 AMD	same as above + SSE4A, FMA4, XOP
ARM	ARMv7, ARMv8

We use a shared copyright model that enables all contributors to maintain the copyright on their contributions. This software is licensed under the BSD-3-Clause license. See the LICENSE file for details.

1.1 Installation

Although `xsimd` is a header-only library, we provide standardized means to install it, with package managers or with `cmake`.

Besides the `xsimd` headers, all these methods place the `cmake` project configuration file in the right location so that third-party projects can use `cmake`'s `find_package` to locate `xsimd` headers.

1.1.1 Using the conda package

A package for `xsimd` is available on the conda package manager.

```
conda install -c conda-forge xsimd
```

1.1.2 Using the Spack package

A package for `xsimd` is available on the Spack package manager.

```
spack install xsimd
spack load xsimd
```

1.1.3 From source with cmake

You can also install `xsimd` from source with `cmake`. On Unix platforms, from the source directory:

```
mkdir build
cd build
cmake -DCMAKE_INSTALL_PREFIX=/path/to/prefix ..
make install
```

On Windows platforms, from the source directory:

```
mkdir build
cd build
cmake -G "NMake Makefiles" -DCMAKE_INSTALL_PREFIX=/path/to/prefix ..
nmake
nmake install
```

1.2 Basic usage

1.2.1 Explicit use of an instruction set extension

Here is an example that computes the mean of two sets of 4 double floating point values, assuming AVX extension is supported:

```
#include <iostream>
#include "xsimd/xsimd.hpp"

namespace xs = xsimd;

int main(int argc, char* argv[])
{
    xs::batch<double, 4> a(1.5, 2.5, 3.5, 4.5);
    xs::batch<double, 4> b(2.5, 3.5, 4.5, 5.5);
    auto mean = (a + b) / 2;
    std::cout << mean << std::endl;
    return 0;
}
```

This example outputs:

```
(2.0, 3.0, 4.0, 5.0)
```

1.2.2 Auto detection of the instruction set extension to be used

The same computation operating on vectors and using the most performant instruction set available:

```
#include <cstddef>
#include <vector>
#include "xsimd/xsimd.hpp"

namespace xs = xsimd;
using vector_type = std::vector<double, xsimd::aligned_allocator<double, XSIMD_
↳DEFAULT_ALIGNMENT>>;
```

(continues on next page)

(continued from previous page)

```

void mean(const vector_type& a, const vector_type& b, vector_type& res)
{
    std::size_t size = a.size();
    constexpr std::size_t simd_size = xsimd::simd_type<double>::size;
    std::size_t vec_size = size - size % simd_size;

    for(std::size_t i = 0; i < vec_size; i += simd_size)
    {
        auto ba = xs::load_aligned(&a[i]);
        auto bb = xs::load_aligned(&b[i]);
        auto bres = (ba + bb) / 2;
        bres.store_aligned(&res[i]);
    }
    for(std::size_t i = vec_size; i < size; ++i)
    {
        res[i] = (a[i] + b[i]) / 2;
    }
}

```

1.3 Writing vectorized code

Assume that we have a simple function that computes the mean of two vectors, something like:

```

#include <cstddef>
#include <vector>

void mean(const std::vector<double>& a, const std::vector<double>& b, std::vector
↳<double>& res)
{
    std::size_t size = res.size();
    for(std::size_t i = 0; i < size; ++i)
    {
        res[i] = (a[i] + b[i]) / 2;
    }
}

```

How can we use *xsimd* to take advantage of vectorization ?

1.3.1 Explicit use of an instruction set

xsimd provides the template class `batch<T, N>` where `N` is the number of scalar values of type `T` involved in SIMD instructions. If you know which instruction set is available on your machine, you can directly use the corresponding specialization of `batch`. For instance, assuming the AVX instruction set is available, the previous code can be vectorized the following way:

```

#include <cstddef>
#include <vector>
#include "xsimd/xsimd.hpp"

void mean(const std::vector<double>& a, const std::vector<double>& b, std::vector
↳<double>& res)
{

```

(continues on next page)

```

using b_type = xsimd::batch<double, 4>;
std::size_t inc = b_type::size;
std::size_t size = res.size();
// size for which the vectorization is possible
std::size_t vec_size = size - size % inc;
for(std::size_t i = 0; i < vec_size; i +=inc)
{
    b_type avec(&a[i]);
    b_type bvec(&b[i]);
    b_type rvec = (avec + bvec) / 2;
    rvec.store_unaligned(&res[i]);
}
// Remaining part that cannot be vectorize
for(std::size_t i = vec_size; i < size; ++i)
{
    res[i] = (a[i] + b[i]) / 2;
}
}

```

However, if you want to write code that is portable, you cannot rely on the use of `batch<double, 4>`. Indeed this won't compile on a CPU where only SSE2 instruction set is available for instance. To solve this, *xsimd* provides an auto-detection mechanism so you can use the most performant SIMD instruction set available on your hardware.

1.3.2 Auto detecting the instruction set

Using the auto detection mechanism does not require a lot of change:

```

#include <cstddef>
#include <vector>
#include "xsimd/xsimd.hpp"

void mean(const std::vector<double>& a, const std::vector<double>& b, std::vector
-><double>& res)
{
    using b_type = xsimd::simd_type<double>;
    std::size_t inc = b_type::size;
    std::size_t size = res.size();
    // size for which the vectorization is possible
    std::size_t vec_size = size - size % inc;
    for(std::size_t i = 0; i < vec_size; i += inc)
    {
        b_type avec = xsimd::load_unaligned(&a[i]);
        b_type bvec = xsimd::load_unaligned(&b[i]);
        b_type rvec = (avec + bvec) / 2;
        xsimd::store_unaligned(&res[i], rvec);
        // or rvec.store_unaligned(&res[i]);
    }
    // Remaining part that cannot be vectorize
    for(std::size_t i = vec_size; i < size; ++i)
    {
        res[i] = (a[i] + b[i]) / 2;
    }
}

```

1.3.3 Aligned vs unaligned memory

In the previous example, you may have noticed the `load_unaligned/store_unaligned` functions. These are meant for loading values from contiguous dynamically allocated memory into SIMD registers and reciprocally. When dealing with memory transfer operations, some instructions sets required the memory to be aligned by a given amount, others can handle both aligned and unaligned modes. In that latter case, operating on aligned memory is always faster than operating on unaligned memory.

`xsimd` provides an aligned memory allocator which follows the standard requirements, so it can be used with STL containers. Let's change the previous code so it can take advantage of this allocator:

```
#include <cstdint>
#include <vector>
#include "xsimd/xsimd.hpp"

using vector_type = std::vector<double, XSIMD_DEFAULT_ALLOCATOR(double)>;
void mean(const vector_type& a, const vector_type& b, vector_type& res)
{
    using b_type = xsimd::simd_type<double>;
    std::size_t inc = b_type::size;
    std::size_t size = res.size();
    // size for which the vectorization is possible
    std::size_t vec_size = size - size % inc;
    for(std::size_t i = 0; i < vec_size; i += inc)
    {
        b_type avec = xsimd::load_aligned(&a[i]);
        b_type bvec = xsimd::load_aligned(&b[i]);
        b_type rvec = (avec + bvec) / 2;
        xsimd::store_unaligned(&res[i], rvec);
        // or rvec.store_unaligned(&res[i]);
    }
    // Remaining part that cannot be vectorize
    for(std::size_t i = vec_size; i < size; ++i)
    {
        res[i] = (a[i] + b[i]) / 2;
    }
}
```

1.3.4 Memory alignment and tag dispatching

You may need to write code that can operate on any type of vectors or arrays, not only the STL ones. In that case, you cannot make assumption on the memory alignment of the container. `xsimd` provides a tag dispatching mechanism that allows you to easily write such a generic code:

```
#include <cstdint>
#include <vector>
#include "xsimd/xsimd.hpp"

template <class C, class Tag>
void mean(const C& a, const C& b, C& res)
{
    using b_type = xsimd::simd_type<double>;
    std::size_t inc = b_type::size;
    std::size_t size = res.size();
    // size for which the vectorization is possible
    std::size_t vec_size = size - size % inc;
```

(continues on next page)

```

for(std::size_t i = 0; i < vec_size; i += inc)
{
    b_type avec = xsimd::load_simd(&a[i], Tag());
    b_type bvec = xsimd::load_simd(&b[i], Tag());
    b_type rvec = (avec + bvec) / 2;
    xsimd::store_simd(&res[i], rvec, Tag());
}
// Remaining part that cannot be vectorize
for(std::size_t i = vec_size; i < size; ++i)
{
    res[i] = (a[i] + b[i]) / 2;
}
}

```

Here, the Tag template parameter can be `xsimd::aligned_mode` or `xsimd::unaligned_mode`. Assuming the existence of a `get_alignment_tag` metafunction in the code, the previous code can be invoked this way:

```
mean<get_alignment_tag<decltype(a)>>(a, b, res);
```

1.4 Instruction set macros

`xsimd` defines different macros depending on the symbols defined by the compiler options.

1.4.1 x86 architecture

If one of the following symbols is detected, `XSIMD_X86_INSTR_SET` is set to the corresponding version and `XSIMD_X86_INSTR_SET_AVAILABLE` is defined.

Symbol	Version
<code>__SSE__</code>	<code>XSIMD_X86_SSE_VERSION</code>
<code>__M_IX86_FP >= 1</code>	<code>XSIMD_X86_SSE_VERSION</code>
<code>__SSE2__</code>	<code>XSIMD_X86_SSE2_VERSION</code>
<code>__M_X64</code>	<code>XSIMD_X86_SSE2_VERSION</code>
<code>__M_IX86_FP >= 2</code>	<code>XSIMD_X86_SSE2_VERSION</code>
<code>__SSE3__</code>	<code>XSIMD_X86_SSE3_VERSION</code>
<code>__SSSE3__</code>	<code>XSIMD_X86_SSSE3_VERSION</code>
<code>__SSE4_1__</code>	<code>XSIMD_X86_SSE4_1_VERSION</code>
<code>__SSE4_2__</code>	<code>XSIMD_X86_SSE4_2_VERSION</code>
<code>__AVX__</code>	<code>XSIMD_X86_AVX_VERSION</code>
<code>__FMA__</code>	<code>XSIMD_X86_FMA3_VERSION</code>
<code>__AVX2__</code>	<code>XSIMD_X86_AVX2_VERSION</code>
<code>__AVX512__</code>	<code>XSIMD_X86_AVX512_VERSION</code>
<code>__KNCNI__</code>	<code>XSIMD_X86_AVX512_VERSION</code>
<code>__AVX512F__</code>	<code>XSIMD_X86_AVX512_VERSION</code>

1.4.2 x86_AMD architecture

If one of the following symbols is detected, `XSIMD_X86_AMD_INSTR_SET` is set to the corresponding version and `XSIMD_X86_AMD_SET_AVAILABLE` is defined.

Symbol	Version
<code>__SSE4A__</code>	<code>XSIMD_X86_AMD_SSE4A_VERSION</code>
<code>__FMA__</code>	<code>XSIMD_X86_AMD_FMA4_VERSION</code>
<code>__XOP__</code>	<code>XSIMD_X86_AMD_XOP_VERSION</code>

If one of the previous symbol is defined, other x86 instruction sets not specific to AMD should be available too; thus `XSIMD_X86_INSTR_SET` and `XSIMD_X86_INSTR_SET_AVAILABLE` should be defined. In that case, `XSIMD_X86_AMD_INSTR_SET` is set to the maximum of `XSIMD_X86_INSTR_SET` and the current value of `XSIMD_X86_AMD_INSTR_SET`.

1.4.3 PPC architecture

If one of the following symbols is detected, `XSIMD_PPC_INSTR_SET` is set to the corresponding version and `XSIMD_PPC_INSTR_AVAILABLE` is defined.

Symbol	Version
<code>__ALTIVEC__</code>	<code>XSIMD_PPC_VMX_VERSION</code>
<code>__VEC__</code>	<code>XSIMD_PPC_VMX_VERSION</code>
<code>__VSX__</code>	<code>XSIMD_PPC_VSX_VERSION</code>
<code>__VECTOR4DOUBLE__</code>	<code>XSIMD_PPC_QPX_VERSION</code>

1.4.4 ARM architecture

If one of the following condition is detected, `XSIMD_ARM_INSTR_SET` is set to the corresponding version and `XSIMD_ARM_INSTR_AVAILABLE` is defined.

Symbol	Version
<code>__ARM_ARCH == 7</code>	<code>XSIMD_ARM7_NEON_VERSION</code>
<code>__ARM_ARCH == 8 && ! __aarch64__</code>	<code>XSIMD_ARM8_32_NEON_VERSION</code>
<code>__ARM_ARCH == 8 && __aarch64__</code>	<code>XSIMD_ARM8_64_NEON_VERSION</code>

1.4.5 Generic instruction set

If `XSIMD*_INSTR_SET_AVAILABLE` has been defined as explained above, `XSIMD_INSTR_SET` is set to `XSIMD*_INSTR_SET` and `XSIMD_INSTR_SET_AVAILABLE` is defined.

1.5 Wrapper types

1.5.1 `simd_batch_bool`

```
template <class X>
```

```
class simd_batch_bool
```

Base class for batch of boolean values.

The `simd_batch_bool` class is the base class for all classes representing a batch of boolean values. Batch of boolean values is meant for operations that may involve batches of integer or floating point values. Thus, the boolean values are stored as integer or floating point values, and each type of batch has its dedicated type of boolean batch.

See *simd_batch*

Template Parameters

- X: The derived type

Subclassed by *xsimd::simd_complex_batch_bool< X >*

Bitwise computed assignment

X &operator&= (const X &rhs)

Assigns the bitwise and of *rhs* and *this*.

Return a reference to *this*.

Parameters

- *rhs*: the batch involved in the operation.

X &operator|= (const X &rhs)

Assigns the bitwise or of *rhs* and *this*.

Return a reference to *this*.

Parameters

- *rhs*: the batch involved in the operation.

X &operator^= (const X &rhs)

Assigns the bitwise xor of *rhs* and *this*.

Return a reference to *this*.

Parameters

- *rhs*: the batch involved in the operation.

Static downcast functions

X &operator () ()

Returns a reference to the actual derived type of the *simd_batch_bool*.

const X &operator () () const

Returns a constant reference to the actual derived type of the *simd_batch_bool*.

Bitwise operators

template <class X>

X xsimd::operator& (const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)

Computes the bitwise and of batches *lhs* and *rhs*.

Return the result of the bitwise and.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

```
template <class X>
```

```
X xsimd::operator| (const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)
```

Computes the bitwise or of batches lhs and rhs.

Return the result of the bitwise or.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

```
template <class X>
```

```
X xsimd::operator^ (const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)
```

Computes the bitwise xor of batches lhs and rhs.

Return the result of the bitwise xor.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

```
template <class X>
```

```
X xsimd::operator~ (const simd_batch_bool<X> &rhs)
```

Computes the bitwise not of batch rhs.

Return the result of the bitwise not.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- rhs: batch involved in the operation.

```
template <class X>
```

```
X xsimd::bitwise_andnot (const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)
```

Computes the bitwise and not of batches lhs and rhs.

Return the result of the bitwise and not.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

Logical operators

template <class X>

X xsimd::operator&&(const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)

Computes the logical and of batches lhs and rhs.

Return the result of the logical and.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

template <class X>

X xsimd::operator&&(const simd_batch_bool<X> &lhs, bool rhs)

Computes the logical and of the batch lhs and the scalar rhs.

Equivalent to the logical and of two boolean batches, where all the values of the second one are initialized to rhs.

Return the result of the logical and.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: batch involved in the operation.
- rhs: boolean involved in the operation.

template <class X>

X xsimd::operator&&(bool lhs, const simd_batch_bool<X> &rhs)

Computes the logical and of the scalar lhs and the batch rhs.

Equivalent to the logical and of two boolean batches, where all the values of the first one are initialized to lhs.

Return the result of the logical and.

Template Parameters

- X: the actual type of boolean batch.

Parameters

- lhs: boolean involved in the operation.
- rhs: batch involved in the operation.

template <class X>

X xsimd::operator|| (const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)

Computes the logical or of batches lhs and rhs.

Return the result of the logical or.

Template Parameters

- *X*: the actual type of boolean batch.

Parameters

- *lhs*: batch involved in the operation.
- *rhs*: batch involved in the operation.

```
template <class X>
```

```
X xsimd::operator|| (const simd_batch_bool<X> &lhs, bool rhs)
```

Computes the logical or of the batch *lhs* and the scalar *rhs*.

Equivalent to the logical or of two boolean batches, where all the values of the second one are initialized to *rhs*.

Return the result of the logical or.

Template Parameters

- *X*: the actual type of boolean batch.

Parameters

- *lhs*: batch involved in the operation.
- *rhs*: boolean involved in the operation.

```
template <class X>
```

```
X xsimd::operator|| (bool lhs, const simd_batch_bool<X> &rhs)
```

Computes the logical or of the scalar *lhs* and the batch *rhs*.

Equivalent to the logical or of two boolean batches, where all the values of the first one are initialized to *lhs*.

Return the result of the logical or.

Template Parameters

- *X*: the actual type of boolean batch.

Parameters

- *lhs*: boolean involved in the operation.
- *rhs*: batch involved in the operation.

Comparison operators

```
template <class X>
```

```
X xsimd::operator==( const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)
```

Element-wise equality of batches *lhs* and *rhs*.

Return the result of the equality comparison.

Parameters

- *lhs*: batch involved in the comparison.
- *rhs*: batch involved in the comparison.

```
template <class X>
```

```
X xsimd::operator!=( const simd_batch_bool<X> &lhs, const simd_batch_bool<X> &rhs)
```

Element-wise inequality of batches *lhs* and *rhs*.

Return the result of the inequality comparison.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

Reducers

template <class X>

bool xsimd: **all** (const *simd_batch_bool*<X> &rhs)

Returns true if all the boolean values in the batch are true, false otherwise.

Return a boolean scalar.

Parameters

- rhs: the batch to reduce.

template <class X>

bool xsimd: **any** (const *simd_batch_bool*<X> &rhs)

Return true if any of the boolean values in the batch is true, false otherwise.

Return a boolean scalar.

Parameters

- rhs: the batch to reduce.

1.5.2 simd_batch

template <class X>

class simd_batch

Base class for batch of integer or floating point values.

The *simd_batch* class is the base class for all classes representing a batch of integer or floating point values. Each type of batch (i.e. a class inheriting from *simd_batch*) has its dedicated type of boolean batch (i.e. a class inheriting from *simd_batch_bool*) for logical operations.

See *simd_batch_bool*

Template Parameters

- X: The derived type

Static downcast functions

X &operator () ()

Returns a reference to the actual derived type of the *simd_batch_bool*.

const X &operator () () const

Returns a constant reference to the actual derived type of the *simd_batch_bool*.

Arithmetic computed assignment

`X &operator+=(const X &rhs)`

Adds the batch `rhs` to `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch to add.

`X &operator+=(const value_type &rhs)`

Adds the scalar `rhs` to each value contained in `this`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar to add.

`X &operator-=(const X &rhs)`

Subtracts the batch `rhs` to `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch to subtract.

`X &operator-=(const value_type &rhs)`

Subtracts the scalar `rhs` to each value contained in `this`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar to subtract.

`X &operator*=(const X &rhs)`

Multiplies `this` with the batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the multiplication.

`X &operator*=(const value_type &rhs)`

Multiplies each scalar contained in `this` with the scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar involved in the multiplication.

`X &operator/=(const X &rhs)`

Divides `this` by the batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the division.

`X &operator/= (const value_type &rhs)`

Divides each scalar contained in `this` by the scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar involved in the division.

Bitwise computed assignment

`X &operator&= (const X &rhs)`

Assigns the bitwise and of `rhs` and `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the operation.

`X &operator|= (const X &rhs)`

Assigns the bitwise or of `rhs` and `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the operation.

`X &operator^= (const X &rhs)`

Assigns the bitwise xor of `rhs` and `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the operation.

Increment and decrement operators

`X &operator++ ()`

Pre-increment operator.

Return a reference to `this`.

`X &operator++ (int)`

Post-increment operator.

Return a reference to `this`.

`X &operator-- ()`
Pre-decrement operator.

Return a reference to `this`.

`X &operator-- (int)`
Post-decrement operator.

Return a reference to `this`.

Arithmetic operators

`template <class X>`
`X xsimd::operator- (const simd_batch<X> &rhs)`
Computes the opposite of the batch `rhs`.

Return the opposite of `rhs`.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `rhs`: batch involved in the operation.

`template <class X>`
`X xsimd::operator+ (const simd_batch<X> &rhs)`
No-op on `rhs`.

Return `rhs`.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `rhs`: batch involved in the operation.

`template <class X>`
`X xsimd::operator+ (const simd_batch<X> &lhs, const simd_batch<X> &rhs)`
Computes the sum of the batches `lhs` and `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the addition.
- `rhs`: batch involved in the addition.

`template <class X>`

```
X xsimd::operator+ (const simd_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the sum of the batch `lhs` and the scalar `rhs`.

Equivalent to the sum of two batches where all the values of the second one are initialized to `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the addition.
- `rhs`: scalar involved in the addition.

```
template <class X>
```

```
X xsimd::operator+ (const typename simd_batch<X>::value_type &lhs, const simd_batch<X>
                    &rhs)
```

Computes the sum of the scalar `lhs` and the batch `rhs`.

Equivalent to the sum of two batches where all the values of the first one are initialized to `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: scalar involved in the addition.
- `rhs`: batch involved in the addition.

```
template <class X>
```

```
X xsimd::operator- (const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Computes the difference of the batches `lhs` and `rhs`.

Return the result of the difference.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the difference.
- `rhs`: batch involved in the difference.

```
template <class X>
```

```
X xsimd::operator- (const simd_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the difference of the batch `lhs` and the scalar `rhs`.

Equivalent to the difference of two batches where all the values of the second one are initialized to `rhs`.

Return the result of the difference.

Template Parameters

- `X`: the actual type of batch.

Parameters

- lhs: batch involved in the difference.
- rhs: scalar involved in the difference.

```
template <class X>
X xsimd::operator- (const typename simd_batch<X>::value_type &lhs, const simd_batch<X>
                    &rhs)
```

Computes the difference of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the difference.
- rhs: batch involved in the difference.

```
template <class X>
X xsimd::operator* (const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Computes the product of the batches lhs and rhs.

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the product.
- rhs: batch involved in the product.

```
template <class X>
X xsimd::operator* (const simd_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the product of the batch lhs and the scalar rhs.

Equivalent to the product of two batches where all the values of the second one are initialized to rhs.

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the product.
- rhs: scalar involved in the product.

```
template <class X>
X xsimd::operator* (const typename simd_batch<X>::value_type &lhs, const simd_batch<X>
                    &rhs)
```

Computes the product of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the product.
- rhs: batch involved in the product.

```
template <class X>
```

```
X xsimd::operator/ (const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Computes the division of the batch lhs by the batch rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: batch involved in the division.

```
template <class X>
```

```
X xsimd::operator/ (const simd_batch<X> &lhs, const typename  
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the division of the batch lhs by the scalar rhs.

Equivalent to the division of two batches where all the values of the second one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: scalar involved in the division.

```
template <class X>
```

```
X xsimd::operator/ (const typename simd_batch<X>::value_type &lhs, const simd_batch<X>  
                    &rhs)
```

Computes the division of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the division.
- rhs: batch involved in the division.

```
template <class X>
```

```
X xsimd::operator% (const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Computes the integer modulo of the batch lhs by the batch rhs.

Return the result of the modulo.

Parameters

- lhs: batch involved in the modulo.
- rhs: batch involved in the modulo.

```
template <class X>
X xsimd::operator% (const simd_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the integer modulo of the batch lhs by the scalar rhs.

Equivalent to the modulo of two batches where all the values of the second one are initialized to rhs.

Return the result of the modulo.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the modulo.
- rhs: scalar involved in the modulo.

```
template <class X>
X xsimd::operator% (const typename simd_batch<X>::value_type &lhs, const simd_batch<X>
                    &rhs)
```

Computes the integer modulo of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the modulo.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the modulo.
- rhs: batch involved in the modulo.

Comparison operators

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator==(const simd_batch<X> &lhs, const
                                                         simd_batch<X> &rhs)
```

Element-wise equality comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator!=(const simd_batch<X> &lhs, const
                                                         simd_batch<X> &rhs)
```

Element-wise inequality comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator<(const simd_batch<X> &lhs, const
                                                    simd_batch<X> &rhs)
```

Element-wise lesser than comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator<=(const simd_batch<X> &lhs, const
                                                       simd_batch<X> &rhs)
```

Element-wise lesser or equal to comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator>(const simd_batch<X> &lhs, const
                                                       simd_batch<X> &rhs)
```

Element-wise greater than comparison of batches lhs and rhs.

Return a boolean batch.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator>=(const simd_batch<X> &lhs, const
                                                       simd_batch<X> &rhs)
```

Element-wise greater or equal comparison of batches lhs and rhs.

Return a boolean batch.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

Bitwise operators

template <class X>

X xsimd::operator& (const simd_batch<X> &lhs, const simd_batch<X> &rhs)

Computes the bitwise and of the batches lhs and rhs.

Return the result of the bitwise and.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

template <class X>

X xsimd::operator| (const simd_batch<X> &lhs, const simd_batch<X> &rhs)

Computes the bitwise or of the batches lhs and rhs.

Return the result of the bitwise or.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

template <class X>

X xsimd::operator^ (const simd_batch<X> &lhs, const simd_batch<X> &rhs)

Computes the bitwise xor of the batches lhs and rhs.

Return the result of the bitwise xor.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

template <class X>

X xsimd::operator~ (const simd_batch<X> &rhs)

Computes the bitwise not of the batches lhs and rhs.

Return the result of the bitwise not.

Parameters

- rhs: batch involved in the operation.

template <class X>

X xsimd::bitwise_andnot (const simd_batch<X> &lhs, const simd_batch<X> &rhs)

Computes the bitwise andnot of the batches lhs and rhs.

Return the result of the bitwise andnot.

Parameters

- lhs: batch involved in the operation.
- rhs: batch involved in the operation.

Reducers

template <class X>

`simd_batch_traits<X>::value_type xsimd::hadd(const simd_batch<X> &rhs)`

Adds all the scalars of the batch rhs.

Return the result of the reduction.

Parameters

- rhs: batch involved in the reduction

template <class X>

`X xsimd::haddp(const simd_batch<X> *row)`

Parallel horizontal addition: adds the scalars of each batch in the array pointed by `row` and store them in a returned batch.

Return the result of the reduction.

Parameters

- row: an array of N batches

Miscellaneous

template <class X>

`X xsimd::select(const typename simd_batch_traits<X>::batch_bool_type &cond, const simd_batch<X> &a, const simd_batch<X> &b)`

Ternary operator for batches: selects values from the batches a or b depending on the boolean values in cond.

Equivalent to

```
for(std::size_t i = 0; i < N; ++i)
    res[i] = cond[i] ? a[i] : b[i];
```

Return the result of the selection.

Parameters

- cond: batch condition.
- a: batch values for truthy condition.
- b: batch value for falsy condition.

Other operators

template <class X>

`simd_batch_traits<X>::batch_bool_type xsimd::operator!(const simd_batch<X> &rhs)`

Element-wise not of rhs.

Return boolean batch.

Template Parameters

- X: the actual type of batch.

Parameters

- rhs: batch involved in the logical not operation.

```
template <class X>
std::ostream &xsimd::operator<<(std::ostream &out, const simd_batch<X> &rhs)
    Insert the batch rhs into the stream out.
```

Return the output stream.

Template Parameters

- X: the actual type of batch.

Parameters

- out: the output stream.
- rhs: the batch to output.

1.5.3 batch_bool

```
template <class T, std::size_t N>
class batch_bool : public xsimd::simd_batch_bool<batch_bool<T, N>>, public xsimd::simd_batch_bool<batch_bool<T, N>, N>
    Batch of boolean values.
```

The *batch_bool* class represents a batch of boolean values, that can be used in operations involving batches of integer or floating point values. The boolean values are stored as integer or floating point values, depending on the type of batch they are dedicated to.

Template Parameters

- T: The value type used for encoding boolean.
- N: The number of scalar in the batch.

Public Functions

```
batch_bool ()
    Builds an uninitialized batch of boolean values.
```

```
batch_bool (bool b)
    Initializes all the values of the batch to b.
```

```
xsimd::batch_bool::batch_bool (bool b0, ..., bool bn)
    Initializes a batch of booleans with the specified boolean values.
```

```
batch_bool (const simd_data &rhs)
    Initializes a batch of boolean with the specified SIMD value.
```

```
batch_bool &operator= (const simd_data &rhs)
    Assigns the specified SIMD value.
```

```
operator simd_data () const
    Converts this to a SIMD value.
```

1.5.4 batch

```
template <class T, std::size_t N>
class batch : public xsimd::simd_batch<batch<T, N>>, public xsimd::simd_batch<batch<T, N>>
```

Public Functions

```
batch ()
```

Builds an uninitialized batch.

```
batch (T f)
```

Initializes all the values of the batch to `b`.

```
xsimd::batch::batch (T f0, ..., T f3)
```

Initializes a batch with the specified scalar values.

```
batch (const T *src, aligned_mode)
```

Initializes a batch to the `N` contiguous values pointed by `src`; `src` is not required to be aligned.

```
batch (const T *src, unaligned_mode)
```

Initializes a batch to the values pointed by `src`; `src` must be aligned.

```
batch (const simd_data &rhs)
```

Initializes a batch with the specified SIMD value.

```
batch &operator= (const simd_data &rhs)
```

Assigns the specified SIMD value to the batch.

```
operator simd_data () const
```

Converts `this` to a SIMD value.

```
batch &load_aligned (const T *src)
```

Loads the `N` contiguous values pointed by `src` into the batch.

`src` must be aligned.

```
batch &load_unaligned (const T *src)
```

Loads the `N` contiguous values pointed by `src` into the batch.

`src` is not required to be aligned.

```
void store_aligned (T *dst) const
```

Stores the `N` values of the batch into a contiguous array pointed by `dst`.

`dst` must be aligned.

```
void store_unaligned (T *dst) const
```

Stores the `N` values of the batch into a contiguous array pointed by `dst`.

`dst` is not required to be aligned.

```
T operator[] (std::size_t i) const
```

Return the `i`-th scalar in the batch.

1.5.5 `simd_complex_batch_bool`

```
template <class X>
class simd_complex_batch_bool : public xsimd::simd_batch_bool<X>
```

Base class for complex batch of boolean values.

The `simd_complex_batch_bool` class is the base class for all classes representing a complex batch of boolean values. Complex batch of boolean values is meant for operations that may involve batches of complex vnmubers. Thus, the boolean values are stored as floating point values, and each type of batch of complex has its dedicated type of boolean batch.

See [`simd_complex_batch`](#)

Template Parameters

- `X`: The derived type

Public Functions

```
simd_complex_batch_bool (bool b)
    Initializes all the values of the batch to b.
```

```
simd_complex_batch_bool (const real_batch &b)
    Initializes the values of the batch with those of the real batch b.
```

A real batch contains scalars whose type is the `value_type` of the complex number type.

1.5.6 `simd_complex_batch`

```
template <class X>
class simd_complex_batch
```

Base class for batch complex numbers.

The `simd_complex_batch` class is the base class for all classes representing a batch of complex numbers. Each type of batch (i.e. a class inheriting from `simd_complex_batch`) has its dedicated type of boolean batch (i.e. a class inheriting from `simd_complex_batch_bool`) for logical operations.

Internally, a batch of complex numbers holds two batches of real numbers, one for the real part and one for the imaginary part.

See [`simd_complex_batch_bool`](#)

Template Parameters

- `X`: The derived type

Subclassed by `xsimd::batch< std::complex< double >, 2 >`, `xsimd::batch< std::complex< double >, 4 >`, `xsimd::batch< std::complex< double >, 8 >`, `xsimd::batch< std::complex< float >, 16 >`, `xsimd::batch< std::complex< float >, 8 >`

Static downcast functions

```
X &operator () ()
```

Returns a reference to the actual derived type of the `simd_batch_bool`.

const X &operator () () const

Returns a constant reference to the actual derived type of the *simd_batch_bool*.

Arithmetic computed assignment

X &operator+= (const X &rhs)

Adds the batch *rhs* to *this*.

Return a reference to *this*.

Parameters

- *rhs*: the batch to add.

X &operator+= (const value_type &rhs)

Adds the scalar *rhs* to each value contained in *this*.

Return a reference to *this*.

Parameters

- *rhs*: the scalar to add.

X &operator+= (const real_batch &rhs)

Adds the real batch *rhs* to *this*.

Return a reference to *this*.

Parameters

- *rhs*: the real batch to add.

X &operator+= (const real_value_type &rhs)

Adds the real scalar *rhs* to each value contained in *this*.

Return a reference to *this*.

Parameters

- *rhs*: the real scalar to add.

X &operator-= (const X &rhs)

Subtracts the batch *rhs* to *this*.

Return a reference to *this*.

Parameters

- *rhs*: the batch to subtract.

X &operator-= (const value_type &rhs)

Subtracts the scalar *rhs* to each value contained in *this*.

Return a reference to *this*.

Parameters

- *rhs*: the scalar to subtract.

`X &operator--(const real_batch &rhs)`

Subtracts the real batch `rhs` to `this`.

Return a reference to `this`.

Parameters

- `rhs`: the batch to subtract.

`X &operator--(const real_value_type &rhs)`

Subtracts the real scalar `rhs` to each value contained in `this`.

Return a reference to `this`.

Parameters

- `rhs`: the real scalar to subtract.

`X &operator*=(const X &rhs)`

Multiplies `this` with the batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the multiplication.

`X &operator*=(const value_type &rhs)`

Multiplies each scalar contained in `this` with the scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar involved in the multiplication.

`X &operator*=(const real_batch &rhs)`

Multiplies `this` with the real batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the real batch involved in the multiplication.

`X &operator*=(const real_value_type &rhs)`

Multiplies each scalar contained in `this` with the real scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the real scalar involved in the multiplication.

`X &operator/=(const X &rhs)`

Divides `this` by the batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the batch involved in the division.

`X &operator/= (const value_type &rhs)`

Divides each scalar contained in `this` by the scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the scalar involved in the division.

`X &operator/= (const real_batch &rhs)`

Divides `this` by the real batch `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the real batch involved in the division.

`X &operator/= (const real_value_type &rhs)`

Divides each scalar contained in `this` by the real scalar `rhs`.

Return a reference to `this`.

Parameters

- `rhs`: the real scalar involved in the division.

Load and store methods

template <class T>

`X &load_aligned (const T *real_src, const T *imag_src)`

Loads the `N` contiguous values pointed by `real_src` into the batch holding the real values, and `N` contiguous values pointed by `imag_src` into the batch holding the imaginary values.

`real_src` and `imag_src` must be aligned.

template <class T>

`X &load_unaligned (const T *real_src, const T *imag_src)`

Loads the `N` contiguous values pointed by `real_src` into the batch holding the real values, and `N` contiguous values pointed by `imag_src` into the batch holding the imaginary values.

`real_src` and `imag_src` are not required to be aligned.

template <class T>

void `store_aligned (T *real_dst, T *imag_dst) const`

Stores the `N` values of the batch holding the real values into a contiguous array pointed by `real_dst`., and the `N` values of the batch holding the imaginary values into a contiguous array pointer by `imag_dst`.

`real_dst` and `imag_dst` must be aligned.

template <class T>

void `store_unaligned (T *real_dst, T *imag_dst) const`

Stores the `N` values of the batch holding the real values into a contiguous array pointed by `real_dst`., and the `N` values of the batch holding the imaginary values into a contiguous array pointer by `imag_dst`.

`real_dst` and `imag_dst` are not required to be aligned.

```
template <class T>
std::enable_if<detail::is_complex<T>::value, X&>::type load_aligned (const T *src)
    Loads the N contiguous values pointed by src into the batch.
```

`src` must be aligned.

```
template <class T>
std::enable_if<detail::is_complex<T>::value, X&>::type load_unaligned (const T *src)
    Loads the N contiguous values pointed by src into the batch.
```

`src` is not required to be aligned.

```
template <class T>
void store_aligned (T *dst) const
    Stores the N values of the batch into a contiguous array pointed by dst.
```

`dst` must be aligned.

```
template <class T>
void store_unaligned (T *dst) const
    Stores the N values of the batch into a contiguous array pointed by dst.
```

`dst` is not required to be aligned.

Public Functions

```
simd_complex_batch (const value_type &v)
    Initializes all the values of the batch to the complex value v.
```

```
simd_complex_batch (const real_value_type &v)
    Initializes all the values of the batch to the real value v.
```

```
simd_complex_batch (const real_batch &re)
    Initializes the values of the batch with those of the real batch re.
    Imaginary parts are set to 0.
```

```
simd_complex_batch (const real_batch &re, const real_batch &im)
    Initializes the batch with two real batch, one for the real part and one for the imaginary part.
```

```
auto real ()
    Returns a batch for the real part.
```

```
auto imag ()
    Returns a batch for the imaginary part.
```

```
auto real () const
    Returns a const batch for the real part.
```

```
auto imag () const
    Returns a const batch for the imaginary part.
```

Arithmetic operators

```
template <class X>
X xsimd::operator- (const simd_complex_batch<X> &rhs)
    Computes the opposite of the batch rhs.
```

Return the opposite of `rhs`.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `rhs`: batch involved in the operation.

```
template <class X>
```

```
X xsimd::operator+ (const simd_complex_batch<X> &lhs, const simd_complex_batch<X> &rhs)
```

Computes the sum of the batches `lhs` and `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the addition.
- `rhs`: batch involved in the addition.

```
template <class X>
```

```
X xsimd::operator+ (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the sum of the batch `lhs` and the scalar `rhs`.

Equivalent to the sum of two batches where all the values of the second one are initialized to `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the addition.
- `rhs`: scalar involved in the addition.

```
template <class X>
```

```
X xsimd::operator+ (const typename simd_batch_traits<X>::value_type &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the sum of the scalar `lhs` and the batch `rhs`.

Equivalent to the sum of two batches where all the values of the first one are initialized to `rhs`.

Return the result of the addition.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: scalar involved in the addition.
- `rhs`: batch involved in the addition.

```
template <class X>
```

```
X xsimd::operator+ (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::real_batch &rhs)
    Computes the sum of the batches lhs and rhs.
```

Return the result of the addition.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the addition.
- rhs: real batch involved in the addition.

```
template <class X>
X xsimd::operator+ (const typename simd_batch_traits<X>::real_batch &lhs, const
                    simd_complex_batch<X> &rhs)
    Computes the sum of the batches lhs and rhs.
```

Return the result of the addition.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real batch involved in the addition.
- rhs: batch involved in the addition.

```
template <class X>
X xsimd::operator+ (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::real_value_type &rhs)
    Computes the sum of the batch lhs and the real scalar rhs.
```

Equivalent to the sum of two batches where all the values of the second one are initialized to rhs.

Return the result of the addition.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the addition.
- rhs: real scalar involved in the addition.

```
template <class X>
X xsimd::operator+ (const typename simd_batch_traits<X>::real_value_type &lhs, const
                    simd_complex_batch<X> &rhs)
    Computes the sum of the real scalar lhs and the batch rhs.
```

Equivalent to the sum of two batches where all the values of the first one are initialized to rhs.

Return the result of the addition.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real scalar involved in the addition.
- rhs: batch involved in the addition.

```
template <class X>
```

```
X xsimd::operator- (const simd_complex_batch<X> &lhs, const simd_complex_batch<X> &rhs)
```

Computes the difference of the batches lhs and rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the difference.
- rhs: batch involved in the difference.

```
template <class X>
```

```
X xsimd::operator- (const simd_complex_batch<X> &lhs, const typename  
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the difference of the batch lhs and the scalar rhs.

Equivalent to the difference of two batches where all the values of the second one are initialized to rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the difference.
- rhs: scalar involved in the difference.

```
template <class X>
```

```
X xsimd::operator- (const typename simd_batch_traits<X>::value_type &lhs, const  
                    simd_complex_batch<X> &rhs)
```

Computes the difference of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the difference.
- rhs: batch involved in the difference.

```
template <class X>
```

```
X xsimd::operator- (const simd_complex_batch<X> &lhs, const typename  
                    simd_batch_traits<X>::real_batch &rhs)
```

Computes the difference of the batches lhs and rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the difference.
- rhs: real batch involved in the difference.

```
template <class X>
X xsimd::operator-(const typename simd_batch_traits<X>::real_batch &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the difference of the batches lhs and rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real batch involved in the difference.
- rhs: batch involved in the difference.

```
template <class X>
X xsimd::operator-(const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::real_value_type &rhs)
```

Computes the difference of the batch lhs and the real scalar rhs.

Equivalent to the difference of two batches where all the values of the second one are initialized to rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the difference.
- rhs: real scalar involved in the difference.

```
template <class X>
X xsimd::operator-(const typename simd_batch_traits<X>::real_value_type &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the difference of the real scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the difference.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real scalar involved in the difference.
- rhs: batch involved in the difference.

```
template <class X>
X xsimd::operator*(const simd_complex_batch<X> &lhs, const simd_complex_batch<X> &rhs)
```

Computes the product of the batches lhs and rhs.

Return the result of the product.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the product.
- `rhs`: batch involved in the product.

```
template <class X>
X xsimd::operator* (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the product of the batch `lhs` and the scalar `rhs`.

Equivalent to the product of two batches where all the values of the second one are initialized to `rhs`.

Return the result of the product.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the product.
- `rhs`: scalar involved in the product.

```
template <class X>
X xsimd::operator* (const typename simd_batch_traits<X>::value_type &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the product of the scalar `lhs` and the batch `rhs`.

Equivalent to the difference of two batches where all the values of the first one are initialized to `rhs`.

Return the result of the product.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: scalar involved in the product.
- `rhs`: batch involved in the product.

```
template <class X>
X xsimd::operator* (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::real_batch &rhs)
```

Computes the product of the batches `lhs` and `rhs`.

Return the result of the product.

Template Parameters

- `X`: the actual type of batch.

Parameters

- `lhs`: batch involved in the product.
- `rhs`: real batch involved in the product.

```
template <class X>
X xsimd::operator*(const typename simd_batch_traits<X>::real_batch &lhs, const
                  simd_complex_batch<X> &rhs)
    Computes the product of the batches lhs and rhs.
```

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real batch involved in the product.
- rhs: batch involved in the product.

```
template <class X>
X xsimd::operator*(const simd_complex_batch<X> &lhs, const typename
                  simd_batch_traits<X>::real_value_type &rhs)
    Computes the product of the batch lhs and the real scalar rhs.
```

Equivalent to the product of two batches where all the values of the second one are initialized to rhs.

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the product.
- rhs: real scalar involved in the product.

```
template <class X>
X xsimd::operator*(const typename simd_batch_traits<X>::real_value_type &lhs, const
                  simd_complex_batch<X> &rhs)
    Computes the product of the real scalar lhs and the batch rhs.
```

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the product.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real scalar involved in the product.
- rhs: batch involved in the product.

```
template <class X>
X xsimd::operator/(const simd_complex_batch<X> &lhs, const simd_complex_batch<X> &rhs)
    Computes the division of the batch lhs by the batch rhs.
```

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: batch involved in the division.

```
template <class X>
X xsimd::operator/ (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::value_type &rhs)
```

Computes the division of the batch lhs by the scalar rhs.

Equivalent to the division of two batches where all the values of the second one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: scalar involved in the division.

```
template <class X>
X xsimd::operator/ (const typename simd_batch_traits<X>::value_type &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the division of the scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: scalar involved in the division.
- rhs: batch involved in the division.

```
template <class X>
X xsimd::operator/ (const simd_complex_batch<X> &lhs, const typename
                    simd_batch_traits<X>::real_batch &rhs)
```

Computes the division of the batch lhs by the batch rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: real batch involved in the division.

```
template <class X>
X xsimd::operator/ (const typename simd_batch_traits<X>::real_batch &lhs, const
                    simd_complex_batch<X> &rhs)
```

Computes the division of the batch lhs by the batch rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real batch involved in the division.
- rhs: batch involved in the division.

```
template <class X>
X xsimd::operator/ (const simd_complex_batch<X> &lhs, const typename
    simd_batch_traits<X>::real_value_type &rhs)
```

Computes the division of the batch lhs by the real scalar rhs.

Equivalent to the division of two batches where all the values of the second one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: batch involved in the division.
- rhs: real scalar involved in the division.

```
template <class X>
X xsimd::operator/ (const typename simd_batch_traits<X>::real_value_type &lhs, const
    simd_complex_batch<X> &rhs)
```

Computes the division of the real scalar lhs and the batch rhs.

Equivalent to the difference of two batches where all the values of the first one are initialized to rhs.

Return the result of the division.

Template Parameters

- X: the actual type of batch.

Parameters

- lhs: real scalar involved in the division.
- rhs: batch involved in the division.

Comparison operators

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::operator==(const simd_complex_batch<X> &lhs,
    const simd_complex_batch<X> &rhs)
```

Element-wise equality comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

```
template <class X>
```

```
simd_batch_traits<X>::batch_bool_type xsimd::operator!=(const simd_complex_batch<X> &lhs,
                                                         const simd_complex_batch<X> &rhs)
```

Element-wise inequality comparison of batches lhs and rhs.

Return a boolean batch.

Parameters

- lhs: batch involved in the comparison.
- rhs: batch involved in the comparison.

Reducers

```
template <class X>
```

```
simd_batch_traits<X>::value_type xsimd::hadd(const simd_complex_batch<X> &rhs)
```

Adds all the scalars of the batch rhs.

Return the result of the reduction.

Parameters

- rhs: batch involved in the reduction

Miscellaneous

```
template <class X>
```

```
X xsimd::select(const typename simd_batch_traits<X>::batch_bool_type &cond, const
                simd_complex_batch<X> &a, const simd_complex_batch<X> &b)
```

Ternary operator for batches: selects values from the batches a or b depending on the boolean values in cond.

Equivalent to

```
for(std::size_t i = 0; i < N; ++i)
    res[i] = cond[i] ? a[i] : b[i];
```

Return the result of the selection.

Parameters

- cond: batch condition.
- a: batch values for truthy condition.
- b: batch value for falsy condition.

Other operators

```
template <class X>
```

```
std::ostream &xsimd::operator<<(std::ostream &out, const simd_complex_batch<X> &rhs)
```

Insert the batch rhs into the stream out.

Return the output stream.

Template Parameters

- X: the actual type of batch.

Parameters

- `out`: the output stream.
- `rhs`: the batch to output.

1.5.7 Available wrappers

The `batch` and `batch_bool` generic template classes are not implemented by default, only full specializations of these templates are available depending on the instruction set macros defined according to the instruction sets provided by the compiler.

Fallback implementation

You may optionally enable a fallback implementation, which translates `batch` and `batch_bool` variants that do not exist in hardware into scalar loops. This is done by setting the `XSIMD_ENABLE_FALLBACK` preprocessor flag before including any `xsimd` header.

This scalar fallback enables you to test the correctness of your computations without having matching hardware available, but you should be aware that it is only intended for use in validation scenarios. It has generally speaking not been tuned for performance, and its run-time characteristics may vary enormously from one compiler to another. Enabling it in performance-conscious production code is therefore strongly discouraged.

x86 architecture

Depending on the value of `XSIMD_X86_INSTR_SET`, the following wrappers are available:

- `XSIMD_X86_INSTR_SET >= XSIMD_X86_SSE2_VERSION`

<code>batch</code>	<code>batch_bool</code>
<code>batch<int8_t, 16></code>	<code>batch_bool<int8_t, 16></code>
<code>batch<uint8_t, 16></code>	<code>batch_bool<uint8_t, 16></code>
<code>batch<int16_t, 9></code>	<code>batch_bool<int16_t, 8></code>
<code>batch<uint16_t, 8></code>	<code>batch_bool<uint16_t, 8></code>
<code>batch<int32_t, 4></code>	<code>batch_bool<int32_t, 4></code>
<code>batch<uint32_t, 4></code>	<code>batch_bool<uint32_t, 4></code>
<code>batch<int64_t, 2></code>	<code>batch_bool<int64_t, 2></code>
<code>batch<uint64_t, 2></code>	<code>batch_bool<uint64_t, 2></code>
<code>batch<float, 4></code>	<code>batch_bool<float, 4></code>
<code>batch<double, 2></code>	<code>batch_bool<double, 2></code>
<code>batch<std::complex<float>, 4></code>	<code>batch_bool<std::complex<float>, 4></code>
<code>batch<std::complex<double>, 2></code>	<code>batch_bool<std::complex<double>, 2></code>

- `XSIMD_X86_INSTR_SET >= XSIMD_X86_AVX_VERSION`

In addition to the wrappers defined above, the following wrappers are available:

batch	batch_bool
batch<int8_t, 32>	batch_bool<int8_t, 32>
batch<uint8_t, 32>	batch_bool<uint8_t, 32>
batch<int16_t, 16>	batch_bool<int16_t, 16>
batch<uint16_t, 16>	batch_bool<uint16_t, 16>
batch<int32_t, 8>	batch_bool<int32_t, 8>
batch<uint32_t, 8>	batch_bool<uint32_t, 8>
batch<int64_t, 4>	batch_bool<int64_t, 4>
batch<uint64_t, 4>	batch_bool<uint64_t, 4>
batch<float, 8>	batch_bool<float, 8>
batch<double, 4>	batch_bool<double, 4>
batch<std::complex<float>, 8>	batch_bool<std::complex<float>, 8>
batch<std::complex<double>, 4>	batch_bool<std::complex<double>, 4>

- XSIMD_X86_INSTR_SET >= XSIMD_X86_AVX512_VERSION

In addition to the wrappers defined above, the following wrappers are available:

batch	batch_bool
batch<int8_t, 64>	batch_bool<int8_t, 64>
batch<uint8_t, 64>	batch_bool<uint8_t, 64>
batch<int16_t, 32>	batch_bool<int16_t, 32>
batch<uint16_t, 32>	batch_bool<uint16_t, 32>
batch<int32_t, 16>	batch_bool<int32_t, 16>
batch<uint32_t, 16>	batch_bool<uint32_t, 16>
batch<int64_t, 8>	batch_bool<int64_t, 8>
batch<uint64_t, 8>	batch_bool<uint64_t, 8>
batch<float, 16>	batch_bool<float, 16>
batch<double, 8>	batch_bool<double, 8>
batch<std::complex<float>, 16>	batch_bool<std::complex<float>, 16>
batch<std::complex<double>, 8>	batch_bool<std::complex<double>, 8>

ARM architecture

Depending on the value of XSIMD_ARM_INSTR_SET, the following wrappers are available:

- XSIMD_ARM_INSTR_SET >= XSIMD_ARM7_NEON_VERSION

batch	batch_bool
batch<int8_t, 16>	batch_bool<int8_t, 16>
batch<uint8_t, 16>	batch_bool<uint8_t, 16>
batch<int16_t, 8>	batch_bool<int16_t, 8>
batch<uint16_t, 8>	batch_bool<uint16_t, 8>
batch<int32_t, 4>	batch_bool<int32_t, 4>
batch<uint32_t, 4>	batch_bool<uint32_t, 4>
batch<int64_t, 2>	batch_bool<int64_t, 2>
batch<uint64_t, 2>	batch_bool<uint64_t, 2>
batch<float, 4>	batch_bool<float, 4>
batch<std::complex<float>, 4>	batch_bool<std::complex<float>, 4>

- XSIMD_ARM_INSTR_SET >= XSIMD_ARM8_64_NEON_VERSION

In addition to the wrappers defined above, the following wrappers are available:

batch	batch_bool
batch<double, 2>	batch_bool<double, 2>
batch<std::complex<double>, 2>	batch_bool<std::complex<double>, 2>

Warning: Support for `std::complex` on ARM is still experimental. You may experience accuracy errors with `std::complex<float>`.

XTL complex support

If the preprocessor token `XSIMD_ENABLE_XTL_COMPLEX` is defined, `xsimd` provides batches for `xtl::xcomplex`, similar to those for `std::complex`. This requires `xtl` to be installed.

1.6 Data transfer

1.6.1 Data transfer instructions

```
template <class T1, class T2 = T1>
simd_return_type<T1, T2> xsimd::set_simd(const T1 &value)
    Returns a batch with all values initialized to value.
```

Return the batch wrapping the highest available instruction set.

Parameters

- `value`: the scalar used to initialize the batch.

```
template <class T1, class T2 = T1>
simd_return_type<T1, T2> xsimd::load_aligned(const T1 *src)
    Loads the memory array pointed to by src into a batch and returns it.
    src is required to be aligned.
```

Return the batch wrapping the highest available instruction set.

Parameters

- `src`: the pointer to the memory array to load.

```
template <class T1, class T2 = T1>
void xsimd::load_aligned(const T1 *src, simd_type<T2> &dst)
    Loads the memory array pointed to by src into the batch dst.
    src is required to be aligned.
```

Parameters

- `src`: the pointer to the memory array to load.
- `dst`: the destination batch.

```
template <class T1, class T2>
```

`simd_return_type<T1, T2> xsimd::load_aligned(const T1 *real_src, const T1 *imag_src)`
Loads the memory arrays pointed to by `real_src` and `imag_src` into a batch of complex numbers and returns it.

`real_src` and `imag_src` are required to be aligned.

Return the batch of complex wrapping the highest available instruction set.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.

template <class T1, class T2>

`void xsimd::load_aligned(const T1 *real_src, const T1 *imag_src, simd_type<T2> &dst)`

Loads the memory arrays pointed to by `real_src` and `imag_src` into the batch `dst`.

`real_src` and `imag_src` are required to be aligned.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.
- `dst`: the destination batch.

template <class T1, class T2 = T1>

`simd_return_type<T1, T2> xsimd::load_unaligned(const T1 *src)`

Loads the memory array pointed to by `src` into a batch and returns it.

`src` is not required to be aligned.

Return the batch wrapping the highest available instruction set.

Parameters

- `src`: the pointer to the memory array to load.

template <class T1, class T2 = T1>

`void xsimd::load_unaligned(const T1 *src, simd_type<T2> &dst)`

Loads the memory array pointed to by `src` into the batch `dst`.

`src` is not required to be aligned.

Parameters

- `src`: the pointer to the memory array to load.
- `dst`: the destination batch.

template <class T1, class T2>

`simd_return_type<T1, T2> xsimd::load_unaligned(const T1 *real_src, const T1 *imag_src)`

Loads the memory arrays pointed to by `real_src` and `imag_src` into a batch of complex numbers and returns it.

`real_src` and `imag_src` are not required to be aligned.

Return the batch of complex wrapping the highest available instruction set.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.

template <class T1, class T2>

void xsimd::load_unaligned(const T1 *real_src, const T1 *imag_src, simd_type<T2> &dst)
 Loads the memory arrays pointed to by *real_src* and *imag_src* into the batch *dst*.

real_src and *imag_src* are not required to be aligned.

Parameters

- *real_src*: the pointer to the memory array containing the real part.
- *imag_src*: the pointer to the memory array containing the imaginary part.
- *dst*: the destination batch.

template <class T1, class T2 = T1>

void xsimd::store_aligned(T1 *dst, const simd_type<T2> &src)
 Stores the batch *src* into the memory array pointed to by *dst*.

dst is required to be aligned.

Parameters

- *dst*: the pointer to the memory array.
- *src*: the batch to store.

template <class T1, class T2 = T1>

void xsimd::store_unaligned(T1 *dst, const simd_type<T2> &src)
 Stores the batch *src* into the memory array pointed to by *dst*.

dst is not required to be aligned.

Parameters

- *dst*: the pointer to the memory array.
- *src*: the batch to store.

template <class T1, class T2>

void xsimd::store_aligned(T1 *real_dst, T1 *imag_dst, const simd_type<T2> &src)
 Stores the batch of complex numbers *src* into the memory arrays pointed to by *real_dst* and *imag_dst*.

real_dst and *imag_dst* are required to be aligned.

Parameters

- *real_dst*: the pointer to the memory array of the real part.
- *imag_dst*: the pointer to the memory array of the imaginary part.
- *src*: the batch to store.

template <class T1, class T2>

void xsimd::store_unaligned(T1 *real_dst, T1 *imag_dst, const simd_type<T2> &src)
 Stores the batch of complex numbers *src* into the memory arrays pointed to by *real_dst* and *imag_dst*.

real_dst and *imag_dst* are not required to be aligned.

Parameters

- *real_dst*: the pointer to the memory array of the real part.
- *imag_dst*: the pointer to the memory array of the imaginary part.
- *src*: the batch to store.

1.6.2 Generic load and store

```
template <class T1, class T2 = T1>
simd_return_type<T1, T2> xsimd::load_simd(const T1 *src, aligned_mode)
```

Loads the memory array pointed to by `src` into a batch and returns it.

`src` is required to be aligned.

Return the batch wrapping the highest available instruction set.

Parameters

- `src`: the pointer to the memory array to load.

```
template <class T1, class T2 = T1>
void xsimd::load_simd(const T1 *src, simd_type<T2> &dst, aligned_mode)
```

Loads the memory array pointed to by `src` into the batch `dst`.

`src` is required to be aligned.

Parameters

- `src`: the pointer to the memory array to load.
- `dst`: the destination batch.

```
template <class T1, class T2>
simd_return_type<T1, T2> xsimd::load_simd(const T1 *real_src, const T1 *imag_src,
                                         aligned_mode)
```

Loads the memory arrays pointed to by `real_src` and `imag_src` into a batch of complex numbers and returns it.

`real_src` and `imag_src` are required to be aligned.

Return the batch of complex wrapping the highest available instruction set.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.

```
template <class T1, class T2>
void xsimd::load_simd(const T1 *real_src, const T1 *imag_src, simd_type<T2> &dst,
                    aligned_mode)
```

Loads the memory arrays pointed to by `real_src` and `imag_src` into the batch `dst`.

`real_src` and `imag_src` are required to be aligned.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.
- `dst`: the destination batch.

```
template <class T1, class T2 = T1>
simd_return_type<T1, T2> xsimd::load_simd(const T1 *src, unaligned_mode)
```

Loads the memory array pointed to by `src` into a batch and returns it.

`src` is not required to be aligned.

Return the batch wrapping the highest available instruction set.

Parameters

- `src`: the pointer to the memory array to load.

```
template <class T1, class T2 = T1>
void xsimd::load_simd(const T1 *src, simd_type<T2> &dst, unaligned_mode)
    Loads the memory array pointed to by src into the batch dst.

src is not required to be aligned.
```

Parameters

- `src`: the pointer to the memory array to load.
- `dst`: the destination batch.

```
template <class T1, class T2>
simd_return_type<T1, T2> xsimd::load_simd(const T1 *real_src, const T1 *imag_src, un-
    aligned_mode)
    Loads the memory arrays pointed to by real_src and imag_src into a batch of complex numbers and
    returns it.

real_src and imag_src are not required to be aligned.
```

Return the batch of complex wrapping the highest available instruction set.

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.

```
template <class T1, class T2>
void xsimd::load_simd(const T1 *real_src, const T1 *imag_src, simd_type<T2> &dst, un-
    aligned_mode)
    Loads the memory arrays pointed to by real_src and imag_src into the batch dst.

real_src and imag_src are not required to be aligned.
```

Parameters

- `real_src`: the pointer to the memory array containing the real part.
- `imag_src`: the pointer to the memory array containing the imaginary part.
- `dst`: the destination batch.

```
template <class T1, class T2 = T1>
void xsimd::store_simd(T1 *dst, const simd_type<T2> &src, aligned_mode)
    Stores the batch src into the memory array pointed to by dst.

dst is required to be aligned.
```

Parameters

- `dst`: the pointer to the memory array.
- `src`: the batch to store.

```
template <class T1, class T2 = T1>
void xsimd::store_simd(T1 *dst, const simd_type<T2> &src, unaligned_mode)
    Stores the batch src into the memory array pointed to by dst.

dst is not required to be aligned.
```

Parameters

- `dst`: the pointer to the memory array.
- `src`: the batch to store.

```
template <class T1, class T2>
```

```
void xsimd::store_simd(T1 *real_dst, T1 *imag_dst, const simd_type<T2> &src, aligned_mode)
```

Stores the batch of complex numbers `src` into the memory arrays pointed to by `real_dst` and `imag_dst`.

`real_dst` and `imag_dst` are required to be aligned.

Parameters

- `real_dst`: the pointer to the memory array of the real part.
- `imag_dst`: the pointer to the memory array of the imaginary part.
- `src`: the batch to store.

```
template <class T1, class T2>
```

```
void xsimd::store_simd(T1 *real_dst, T1 *imag_dst, const simd_type<T2> &src, unaligned_mode)
```

Stores the batch of complex numbers `src` into the memory arrays pointed to by `real_dst` and `imag_dst`.

`real_dst` and `imag_dst` are not required to be aligned.

Parameters

- `real_dst`: the pointer to the memory array of the real part.
- `imag_dst`: the pointer to the memory array of the imaginary part.
- `src`: the batch to store.

1.7 Mathematical functions

1.7.1 Basic functions

```
template <class X>
```

```
X xsimd::abs(const simd_batch<X> &rhs)
```

Computes the absolute values of each scalar in the batch `rhs`.

Return the absolute values of `rhs`.

Parameters

- `rhs`: batch of integer or floating point values.

```
template <class X>
```

```
X xsimd::fabs(const simd_batch<X> &rhs)
```

Computes the absolute values of each scalar in the batch `rhs`.

Return the absolute values of `rhs`.

Parameters

- `rhs`: batch floating point values.

```
template <class T, std::size_t N>
```

```
batch<T, N> xsimd::fmod(const batch<T, N> &x, const batch<T, N> &y)
```

Computes the floating-point remainder of the division operation x/y .

The floating-point remainder of the division operation x/y calculated by this function is exactly the value $x - n*y$, where n is x/y with its fractional part truncated. The returned value has the same sign as x and is less than y in magnitude.

Return the floating-point remainder of the division.

Parameters

- x : batch of floating point values.
- y : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::remainder(const batch<T, N> &x, const batch<T, N> &y)
```

Computes the IEEE remainder of the floating point division operation x/y .

The IEEE floating-point remainder of the division operation x/y calculated by this function is exactly the value $x - n*y$, where the value n is the integral value nearest the exact value x/y . When $|n-x/y| = 0.5$, the value n is chosen to be even. In contrast to `fmod`, the returned value is not guaranteed to have the same sign as x . If the returned value is 0, it will have the same sign as x .

Return the IEEE remainder remainder of the floating point division.

Parameters

- x : batch of floating point values.
- y : batch of floating point values.

```
template <class X>
X xsimd::fma(const simd_batch<X> &x, const simd_batch<X> &y, const simd_batch<X> &z)
```

Computes $(x*y) + z$ in a single instruction when possible.

Return the result of the fused multiply-add operation.

Parameters

- x : a batch of integer or floating point values.
- y : a batch of integer or floating point values.
- z : a batch of integer or floating point values.

```
template <class X>
X xsimd::fms(const simd_batch<X> &x, const simd_batch<X> &y, const simd_batch<X> &z)
```

Computes $(x*y) - z$ in a single instruction when possible.

Return the result of the fused multiply-sub operation.

Parameters

- x : a batch of integer or floating point values.
- y : a batch of integer or floating point values.
- z : a batch of integer or floating point values.

```
template <class X>
X xsimd::fnma(const simd_batch<X> &x, const simd_batch<X> &y, const simd_batch<X> &z)
```

Computes $-(x*y) + z$ in a single instruction when possible.

Return the result of the fused negated multiply-add operation.

Parameters

- x : a batch of integer or floating point values.
- y : a batch of integer or floating point values.

- z : a batch of integer or floating point values.

```
template <class X>
```

```
X xsimd::fnms(const simd_batch<X> &x, const simd_batch<X> &y, const simd_batch<X> &z)
```

Computes $-(x*y) - z$ in a single instruction when possible.

Return the result of the fused negated multiply-sub operation.

Parameters

- x : a batch of integer or floating point values.
- y : a batch of integer or floating point values.
- z : a batch of integer or floating point values.

```
template <class X>
```

```
X xsimd::min(const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Returns the smaller values of the batches lhs and rhs .

Return a batch of the smaller values.

Parameters

- lhs : a batch of integer or floating point values.
- rhs : a batch of integer or floating point values.

```
template <class X>
```

```
X xsimd::max(const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Returns the larger values of the batches lhs and rhs .

Return a batch of the larger values.

Parameters

- lhs : a batch of integer or floating point values.
- rhs : a batch of integer or floating point values.

```
template <class X>
```

```
X xsimd::fmin(const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Returns the smaller values of the batches lhs and rhs .

Return a batch of the smaller values.

Parameters

- lhs : a batch of floating point values.
- rhs : a batch of floating point values.

```
template <class X>
```

```
X xsimd::fmax(const simd_batch<X> &lhs, const simd_batch<X> &rhs)
```

Returns the larger values of the batches lhs and rhs .

Return a batch of the larger values.

Parameters

- lhs : a batch of floating point values.

- rhs: a batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::fdim(const batch<T, N> &x, const batch<T, N> &y)
    Computes the positive difference between x and y, that is,  $\max(0, x-y)$ .
```

Return the positive difference.

Parameters

- x: batch of floating point values.
- y: batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::clip(const batch<T, N> &x, const batch<T, N> &lo, const batch<T, N> &hi)
    Clips the values of the batch x between those of the batches lo and hi.
```

Return the result of the clipping.

Parameters

- x: batch of floating point values.
- lo: batch of floating point values.
- hi: batch of floating point values.

<i>abs</i>	absolute value
<i>fabs</i>	absolute value
<i>fmod</i>	remainder of the floating point division operation
<i>remainder</i>	signed remainder of the division operation
<i>fma</i>	fused multiply-add operation
<i>fms</i>	fused multiply-sub operation
<i>fma</i>	fused negated multiply-add operation
<i>fms</i>	fused negated multiply-sub operation
<i>min</i>	smaller of two batches
<i>max</i>	larger of two batches
<i>fmin</i>	smaller of two batches of floating point values
<i>fmax</i>	larger of two batches of floating point values
<i>fdim</i>	positive difference
<i>clip</i>	clipping operation

1.7.2 Exponential functions

```
template <class T, std::size_t N>
batch<T, N> xsimd::exp(const batch<T, N> &x)
    Computes the natural exponential of the batch x.
```

Return the natural exponential of x.

Parameters

- x: batch of floating point values.

```
template <class T, std::size_t N>
```

batch<T, N> xsimd::exp2(const *batch*<T, N> &x)

Computes the base 2 exponential of the batch *x*.

Return the base 2 exponential of *x*.

Parameters

- *x*: batch of floating point values.

Warning: doxygenfunction: Unable to resolve multiple matches for function “exp10” with arguments () in doxygen xml output for project “xsimd” from directory: ../xml. Potential matches:

```
- template <class T, std::size_t *N*>
  batch<T, N> xsimd::exp10(const batch<T, N>&)
- template <class T>
  T xsimd::exp10(const T&)
```

Warning: doxygenfunction: Unable to resolve multiple matches for function “expm1” with arguments () in doxygen xml output for project “xsimd” from directory: ../xml. Potential matches:

```
- template <class T, std::size_t *N*>
  batch<T, N> xsimd::expm1(const batch<T, N>&)
- template <class T>
  std::complex<T> xsimd::expm1(const std::complex<T>&)
```

template <class T, std::size_t N>

batch<T, N> xsimd::log(const *batch*<T, N> &x)

Computes the natural logarithm of the batch *x*.

Return the natural logarithm of *x*.

Parameters

- *x*: batch of floating point values.

Warning: doxygenfunction: Unable to resolve multiple matches for function “log2” with arguments () in doxygen xml output for project “xsimd” from directory: ../xml. Potential matches:

```
- template <class T, std::size_t *N*>
  batch<T, N> xsimd::log2(const batch<T, N>&)
- template <class T>
  std::complex<T> xsimd::log2(const std::complex<T>&)
```

template <class T, std::size_t N>

batch<T, N> xsimd::log10(const *batch*<T, N> &x)

Computes the base 10 logarithm of the batch *x*.

Return the base 10 logarithm of *x*.

Parameters

- *x*: batch of floating point values.

Warning: doxygenfunction: Unable to resolve multiple matches for function “log1p” with arguments () in doxygen xml output for project “xsimd” from directory: ../xml. Potential matches:

```
- template <class T, std::size_t *N*>
  batch<T, N> xsimd::log1p(const batch<T, N>&)
- template <class T>
  std::complex<T> xsimd::log1p(const std::complex<T>&)
```

<i>exp</i>	natural exponential function
<i>exp2</i>	base 2 exponential function
<i>exp10</i>	base 10 exponential function
<i>expm1</i>	natural exponential function, minus one
<i>log</i>	natural logarithm function
<i>log2</i>	base 2 logarithm function
<i>log10</i>	base 10 logarithm function
<i>log1p</i>	natural logarithm of one plus function

1.7.3 Power functions

Warning: doxygenfunction: Unable to resolve multiple matches for function “pow” with arguments () in doxygen xml output for project “xsimd” from directory: ../xml. Potential matches:

```
- template <class T, std::size_t *N*>
  batch<T, N> xsimd::pow(const batch<T, N>&, const batch<T, N>&)
- template <class T0, class T1>
  auto xsimd::pow(const T0&, const T1&)
- template <class T0, class T1>
  auto xsimd::pow(const T0&, const std::complex<T1>&)
- template <class T0, class T1>
  std::enable_if<!std::is_integral<T1>::value, std::complex<T0>>::type
  xsimd::pow(const std::complex<T0>&, const T1&)
- template <class T0, class T1>
  std::enable_if<std::is_integral<T1>::value, T0>::type xsimd::pow(const T0&, const
  T1&)
- template <class T0, class T1>
  std::enable_if<std::is_integral<T1>::value, std::complex<T0>>::type
  xsimd::pow(const std::complex<T0>&, const T1&)
- template <class T0, std::size_t *N*, class T1>
  std::enable_if<std::is_integral<T1>::value, batch<T0, N>>::type xsimd::pow(const
  batch<T0, N>&, const T1&)
```

template <class X>

X xsimd::sqrt(const simd_batch<X> &rhs)

Computes the square root of the batch rhs.

Return the square root of rhs.

Parameters

- rhs: batch of floating point values.

template <class T, std::size_t N>

`batch<T, N> xsimd::cbrt (const batch<T, N> &x)`

Computes the cubic root of the batch `x`.

Return the cubic root of `x`.

Parameters

- `x`: batch of floating point values.

`template <class T, std::size_t N>`

`batch<T, N> xsimd::hypot (const batch<T, N> &x, const batch<T, N> &y)`

Computes the square root of the sum of the squares of the batches `x`, and `y`.

Return the square root of the sum of the squares of `x` and `y`.

Parameters

- `x`: batch of floating point values.
- `y`: batch of floating point values.

<i>pow</i>	power function
<i>sqrt</i>	square root function
<i>cbrt</i>	cubic root function
<i>hypot</i>	hypotenuse function

1.7.4 Trigonometric functions

`template <class T, std::size_t N>`

`batch<T, N> xsimd::sin (const batch<T, N> &x)`

Computes the sine of the batch `x`.

Return the sine of `x`.

Parameters

- `x`: batch of floating point values.

`template <class T, std::size_t N>`

`batch<T, N> xsimd::cos (const batch<T, N> &x)`

Computes the cosine of the batch `x`.

Return the cosine of `x`.

Parameters

- `x`: batch of floating point values.

`template <class T, std::size_t N>`

`void xsimd::sincos (const batch<T, N> &x, batch<T, N> &si, batch<T, N> &co)`

Computes the sine and the cosine of the batch `x`.

This method is faster than calling sine and cosine independently.

Parameters

- `x`: batch of floating point values.

- `si`: the sine of `x`.
- `co`: the cosine of `x`.

template <class T, std::size_t N>
batch<T, N> xsimd::tan(const *batch*<T, N> &x)
 Computes the tangent of the batch `x`.

Return the tangent of `x`.

Parameters

- `x`: batch of floating point values.

template <class T, std::size_t N>
batch<T, N> xsimd::asin(const *batch*<T, N> &x)
 Computes the arc sine of the batch `x`.

Return the arc sine of `x`.

Parameters

- `x`: batch of floating point values.

template <class T, std::size_t N>
batch<T, N> xsimd::acos(const *batch*<T, N> &x)
 Computes the arc cosine of the batch `x`.

Return the arc cosine of `x`.

Parameters

- `x`: batch of floating point values.

template <class T, std::size_t N>
batch<T, N> xsimd::atan(const *batch*<T, N> &x)
 Computes the arc tangent of the batch `x`.

Return the arc tangent of `x`.

Parameters

- `x`: batch of floating point values.

template <class T, std::size_t N>
batch<T, N> xsimd::atan2(const *batch*<T, N> &y, const *batch*<T, N> &x)
 Computes the arc tangent of the batch `x/y`, using the signs of the arguments to determine the correct quadrant.

Return the arc tangent of `x/y`.

Parameters

- `x`: batch of floating point values.
- `y`: batch of floating point values.

<i>sin</i>	sine function
<i>cos</i>	cosine function
<i>sincos</i>	sine and cosine function
<i>tan</i>	tangent function
<i>asin</i>	arc sine function
<i>acos</i>	arc cosine function
<i>atan</i>	arc tangent function
<i>atan2</i>	arc tangent function, determining quadrants

1.7.5 Hyperbolic functions

template <class T, std::size_t N>

batch<T, N> xsimd::sinh(const *batch*<T, N> &x)

Computes the hyperbolic sine of the batch *x*.

Return the hyperbolic sine of *x*.

Parameters

- *x*: batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::cosh(const *batch*<T, N> &x)

Computes the hyperbolic cosine of the batch *x*.

Return the hyperbolic cosine of *x*.

Parameters

- *x*: batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::tanh(const *batch*<T, N> &x)

Computes the hyperbolic tangent of the batch *x*.

Return the hyperbolic tangent of *x*.

Parameters

- *x*: batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::asinh(const *batch*<T, N> &x)

Computes the inverse hyperbolic sine of the batch *x*.

Return the inverse hyperbolic sine of *x*.

Parameters

- *x*: batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::acosh(const *batch*<T, N> &x)

Computes the inverse hyperbolic cosine of the batch *x*.

Return the inverse hyperbolic cosine of *x*.

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::atanh(const batch<T, N> &x)
    Computes the inverse hyperbolic tangent of the batch  $x$ .
```

Return the inverse hyperbolic tangent of x .

Parameters

- x : batch of floating point values.

<i>sinh</i>	hyperbolic sine function
<i>cosh</i>	hyperbolic cosine function
<i>tanh</i>	hyperbolic tangent function
<i>asinh</i>	inverse hyperbolic sine function
<i>acosh</i>	inverse hyperbolic cosine function
<i>atanh</i>	inverse hyperbolic tangent function

1.7.6 Error and gamma functions

```
template <class T, std::size_t N>
batch<T, N> xsimd::erf(const batch<T, N> &x)
    Computes the error function of the batch  $x$ .
```

Return the error function of x .

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::erfc(const batch<T, N> &x)
    Computes the complementary error function of the batch  $x$ .
```

Return the error function of x .

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::tgamma(const batch<T, N> &x)
    Computes the gamma function of the batch  $x$ .
```

Return the gamma function of x .

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::lgamma(const batch<T, N> &x)
    Computes the natural logarithm of the gamma function of the batch  $x$ .
```

Return the natural logarithm of the gamma function of x .

Parameters

- x : batch of floating point values.

<i>erf</i>	error function
<i>erfc</i>	complementary error function
<i>gamma</i>	gamma function
<i>lgamma</i>	natural logarithm of the gamma function

1.7.7 Nearest integer floating point operations

template <class T, std::size_t N>

batch<T, N> xsimd::ceil (const *batch*<T, N> & x)

Computes the batch of smallest integer values not less than scalars in x .

Return the batch of smallest integer values not less than x .

Parameters

- x : batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::floor (const *batch*<T, N> & x)

Computes the batch of largest integer values not greater than scalars in x .

Return the batch of largest integer values not greater than x .

Parameters

- x : batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::trunc (const *batch*<T, N> & x)

Computes the batch of nearest integer values not greater in magnitude than scalars in x .

Return the batch of nearest integer values not greater in magnitude than x .

Parameters

- x : batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::round (const *batch*<T, N> & x)

Computes the batch of nearest integer values to scalars in x (in floating point format), rounding halfway cases away from zero, regardless of the current rounding mode.

Return the batch of nearest integer values.

Parameters

- x : batch of floating point values.

template <class T, std::size_t N>

batch<T, N> xsimd::nearbyint (const *batch*<T, N> & x)

Rounds the scalars in x to integer values (in floating point format), using the current rounding mode.

Return the batch of nearest integer values.

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch<T, N> xsimd::rint (const batch<T, N> &x)
```

Rounds the scalars in x to integer values (in floating point format), using the current rounding mode.

Return the batch of rounded values.

Parameters

- x : batch of floating point values.

<i>ceil</i>	nearest integers not less
<i>floor</i>	nearest integers not greater
<i>trunc</i>	nearest integers not greater in magnitude
<i>round</i>	nearest integers, rounding away from zero
<i>nearbyint</i>	nearest integers using current rounding mode
<i>rint</i>	nearest integers using current rounding mode

1.7.8 Classification functions

```
template <class T, std::size_t N>
batch_bool<T, N> xsimd::isfinite (const batch<T, N> &x)
```

Determines if the scalars in the given batch x are finite values, i.e. they are different from infinite or NaN.

Return a batch of booleans.

Parameters

- x : batch of floating point values.

```
template <class T, std::size_t N>
batch_bool<T, N> xsimd::isinf (const batch<T, N> &x)
```

Determines if the scalars in the given batch x are positive or negative infinity.

Return a batch of booleans.

Parameters

- x : batch of floating point values.

```
template <class X>
simd_batch_traits<X>::batch_bool_type xsimd::isnan (const simd_batch<X> &x)
```

Determines if the scalars in the given batch x are NaN values.

Return a batch of booleans.

Parameters

- x : batch of floating point values.

<i>isfinite</i>	Checks for finite values
<i>isinf</i>	Checks for infinite values
<i>isnan</i>	Checks for NaN values

1.8 Aligned memory allocator

template <class *T*, size_t *Align*>

class **aligned_allocator**

Allocator for aligned memory.

The *aligned_allocator* class template is an allocator that performs memory allocation aligned by the specified value.

Template Parameters

- *T*: type of objects to allocate.
- *Align*: alignment in bytes.

Public Functions

aligned_allocator ()

Default constructor.

aligned_allocator (const *aligned_allocator* &*rhs*)

Copy constructor.

template <class *U*>

aligned_allocator (const *aligned_allocator*<*U*, *Align*> &*rhs*)

Extended copy constructor.

~aligned_allocator ()

Destructor.

auto **address** (reference *r*)

Returns the actual address of *r* even in presence of overloaded operator&.

Return the actual address of *r*.

Parameters

- *r*: the object to acquire address of.

auto **address** (const_reference *r*) **const**

Returns the actual address of *r* even in presence of overloaded operator&.

Return the actual address of *r*.

Parameters

- *r*: the object to acquire address of.

auto **allocate** (size_type *n*, typename std::allocator<void>::const_pointer *hint* = 0)

Allocates $n * \text{sizeof}(T)$ bytes of uninitialized memory, aligned by *A*.

The alignment may require some extra memory allocation.

Return a pointer to the first byte of a memory block suitably aligned and sufficient to hold an array of *n* objects of type *T*.

Parameters

- *n*: the number of objects to allocate storage for.
- *hint*: unused parameter provided for standard compliance.

void **deallocate** (pointer *p*, size_type *n*)

Deallocates the storage referenced by the pointer *p*, which must be a pointer obtained by an earlier call to *allocate()*.

The argument *n* must be equal to the first argument of the call to *allocate()* that originally produced *p*; otherwise, the behavior is undefined.

Parameters

- *p*: pointer obtained from *allocate()*.
- *n*: number of objects earlier passed to *allocate()*.

auto **max_size** () const

Returns the maximum theoretically possible value of *n*, for which the call *allocate*(*n*, 0) could succeed.

Return the maximum supported allocated size.

auto **size_max** () const

This method is deprecated, use *max_size()* instead.

template <class *U*, class... *Args*>

void **construct** (*U* **p*, *Args*&&... *args*)

Constructs an object of type *T* in allocated uninitialized memory pointed to by *p*, using placement-new.

Parameters

- *p*: pointer to allocated uninitialized memory.
- *args*: the constructor arguments to use.

template <class *U*>

void **destroy** (*U* **p*)

Calls the destructor of the object pointed to by *p*.

Parameters

- *p*: pointer to the object that is going to be destroyed.

1.8.1 Comparison operators

template <class *T1*, size_t *A1*, class *T2*, size_t *A2*>

bool xsimd::operator==(const aligned_allocator<*T1*, *A1*> &*lhs*, const aligned_allocator<*T2*, *A2*> &*rhs*)

Compares two aligned memory allocator for equality.

Since allocators are stateless, return `true` iff $A1 == A2$.

Return true if the allocators have the same alignment.

Parameters

- lhs: *aligned_allocator* to compare.
- rhs: *aligned_allocator* to compare.

```
template <class T1, size_t A1, class T2, size_t A2>  
bool xsimd::operator!=(const aligned_allocator<T1, A1> &lhs, const aligned_allocator<T2, A2>  
                        &rhs)
```

Compares two aligned memory allocator for inequality.

Since allocators are stateless, return true iff `A1 != A2`.

Return true if the allocators have different alignments.

Parameters

- lhs: *aligned_allocator* to compare.
- rhs: *aligned_allocator* to compare.

X

- `xsimd::abs` (C++ function), 48
- `xsimd::acos` (C++ function), 55
- `xsimd::acosh` (C++ function), 56
- `xsimd::aligned_allocator` (C++ class), 60
- `xsimd::aligned_allocator::~~aligned_allocator` (C++ function), 60
- `xsimd::aligned_allocator::address` (C++ function), 60
- `xsimd::aligned_allocator::aligned_allocator` (C++ function), 60
- `xsimd::aligned_allocator::allocate` (C++ function), 60
- `xsimd::aligned_allocator::construct` (C++ function), 61
- `xsimd::aligned_allocator::deallocate` (C++ function), 61
- `xsimd::aligned_allocator::destroy` (C++ function), 61
- `xsimd::aligned_allocator::max_size` (C++ function), 61
- `xsimd::aligned_allocator::size_max` (C++ function), 61
- `xsimd::all` (C++ function), 14
- `xsimd::any` (C++ function), 14
- `xsimd::asin` (C++ function), 55
- `xsimd::asinh` (C++ function), 56
- `xsimd::atan` (C++ function), 55
- `xsimd::atan2` (C++ function), 55
- `xsimd::atanh` (C++ function), 57
- `xsimd::batch` (C++ class), 26
- `xsimd::batch::batch` (C++ function), 26
- `xsimd::batch::load_aligned` (C++ function), 26
- `xsimd::batch::load_unaligned` (C++ function), 26
- `xsimd::batch::operator simd_data` (C++ function), 26
- `xsimd::batch::operator=` (C++ function), 26
- `xsimd::batch::operator[]` (C++ function), 26
- `xsimd::batch::store_aligned` (C++ function), 26
- `xsimd::batch::store_unaligned` (C++ function), 26
- `xsimd::batch_bool` (C++ class), 25
- `xsimd::batch_bool::batch_bool` (C++ function), 25
- `xsimd::batch_bool::operator simd_data` (C++ function), 25
- `xsimd::batch_bool::operator=` (C++ function), 25
- `xsimd::bitwise_andnot` (C++ function), 11, 23
- `xsimd::cbrt` (C++ function), 53
- `xsimd::ceil` (C++ function), 58
- `xsimd::clip` (C++ function), 51
- `xsimd::cos` (C++ function), 54
- `xsimd::cosh` (C++ function), 56
- `xsimd::erf` (C++ function), 57
- `xsimd::erfc` (C++ function), 57
- `xsimd::exp` (C++ function), 51
- `xsimd::exp2` (C++ function), 51
- `xsimd::fabs` (C++ function), 48
- `xsimd::fdim` (C++ function), 51
- `xsimd::floor` (C++ function), 58
- `xsimd::fma` (C++ function), 49
- `xsimd::fmax` (C++ function), 50
- `xsimd::fmin` (C++ function), 50
- `xsimd::fmod` (C++ function), 48
- `xsimd::fms` (C++ function), 49
- `xsimd::fnma` (C++ function), 49
- `xsimd::fnms` (C++ function), 50
- `xsimd::hadd` (C++ function), 24, 40
- `xsimd::haddp` (C++ function), 24
- `xsimd::hypot` (C++ function), 54
- `xsimd::isfinite` (C++ function), 59
- `xsimd::isinf` (C++ function), 59
- `xsimd::isnan` (C++ function), 59
- `xsimd::lgamma` (C++ function), 57
- `xsimd::load_aligned` (C++ function), 43, 44

xsimd::load_simd (C++ function), 46, 47
xsimd::load_unaligned (C++ function), 44
xsimd::log (C++ function), 52
xsimd::log10 (C++ function), 52
xsimd::max (C++ function), 50
xsimd::min (C++ function), 50
xsimd::nearbyint (C++ function), 58
xsimd::operator! (C++ function), 24
xsimd::operator!= (C++ function), 13, 21, 39, 62
xsimd::operator* (C++ function), 19, 35–37
xsimd::operator+ (C++ function), 17, 18, 32, 33
xsimd::operator- (C++ function), 17–19, 31, 34, 35
xsimd::operator/ (C++ function), 20, 37–39
xsimd::operator== (C++ function), 13, 21, 39, 61
xsimd::operator% (C++ function), 20, 21
xsimd::operator& (C++ function), 10, 23
xsimd::operator&& (C++ function), 12
xsimd::operator^ (C++ function), 11, 23
xsimd::operator~ (C++ function), 11, 23
xsimd::operator| (C++ function), 11, 23
xsimd::operator|| (C++ function), 12, 13
xsimd::operator> (C++ function), 22
xsimd::operator>= (C++ function), 22
xsimd::operator< (C++ function), 22
xsimd::operator<= (C++ function), 22
xsimd::operator<< (C++ function), 25, 40
xsimd::remainder (C++ function), 49
xsimd::rint (C++ function), 59
xsimd::round (C++ function), 58
xsimd::select (C++ function), 24, 40
xsimd::set_simd (C++ function), 43
xsimd::simd_batch (C++ class), 14
xsimd::simd_batch::operator() (C++ function), 14
xsimd::simd_batch::operator*= (C++ function), 15
xsimd::simd_batch::operator++ (C++ function), 16
xsimd::simd_batch::operator+= (C++ function), 15
xsimd::simd_batch::operator- (C++ function), 16, 17
xsimd::simd_batch::operator-= (C++ function), 15
xsimd::simd_batch::operator/= (C++ function), 15, 16
xsimd::simd_batch::operator&= (C++ function), 16
xsimd::simd_batch::operator^= (C++ function), 16
xsimd::simd_batch::operator|= (C++ function), 16
xsimd::simd_batch_bool (C++ class), 9
xsimd::simd_batch_bool::operator() (C++ function), 10
xsimd::simd_batch_bool::operator&= (C++ function), 10
xsimd::simd_batch_bool::operator^= (C++ function), 10
xsimd::simd_batch_bool::operator|= (C++ function), 10
xsimd::simd_complex_batch (C++ class), 27
xsimd::simd_complex_batch::imag (C++ function), 31
xsimd::simd_complex_batch::load_aligned (C++ function), 30
xsimd::simd_complex_batch::load_unaligned (C++ function), 30, 31
xsimd::simd_complex_batch::operator() (C++ function), 27
xsimd::simd_complex_batch::operator*= (C++ function), 29
xsimd::simd_complex_batch::operator+= (C++ function), 28
xsimd::simd_complex_batch::operator-= (C++ function), 28, 29
xsimd::simd_complex_batch::operator/= (C++ function), 29, 30
xsimd::simd_complex_batch::real (C++ function), 31
xsimd::simd_complex_batch::simd_complex_batch (C++ function), 31
xsimd::simd_complex_batch::store_aligned (C++ function), 30, 31
xsimd::simd_complex_batch::store_unaligned (C++ function), 30, 31
xsimd::simd_complex_batch_bool (C++ class), 27
xsimd::simd_complex_batch_bool::simd_complex_batch (C++ function), 27
xsimd::sin (C++ function), 54
xsimd::sincos (C++ function), 54
xsimd::sinh (C++ function), 56
xsimd::sqrt (C++ function), 53
xsimd::store_aligned (C++ function), 45
xsimd::store_simd (C++ function), 47, 48
xsimd::store_unaligned (C++ function), 45
xsimd::tan (C++ function), 55
xsimd::tanh (C++ function), 56
xsimd::tgamma (C++ function), 57
xsimd::trunc (C++ function), 58