
Pillow (PIL Fork) Documentation

3.3.0.dev0

Alex Clark

2016 05 29

1		3
1.1	3
1.2	3
1.3	3
1.4	4
1.5	7
1.6	8
2		9
2.1	9
2.2	10
2.3	Concepts	17
2.4	Appendices	19
3	Reference	37
3.1	Image Module	37
3.2	ImageChops (“Channel Operations”) Module	50
3.3	ImageColor Module	52
3.4	ImageCms Module	53
3.5	ImageDraw Module	67
3.6	ImageEnhance Module	71
3.7	ImageFile Module	72
3.8	ImageFilter Module	73
3.9	ImageFont Module	75
3.10	ImageGrab Module (OS X and Windows only)	77
3.11	ImageMath Module	77
3.12	ImageMorph Module	79
3.13	ImageOps Module	80
3.14	ImagePalette Module	83
3.15	ImagePath Module	84
3.16	ImageQt Module	85
3.17	ImageSequence Module	85
3.18	ImageStat Module	85
3.19	ImageTk Module	86
3.20	ImageWin Module (Windows-only)	87
3.21	ExifTags Module	88
3.22	TiffTags Module	89
3.23	OleFileIO Module	90

3.24	PSDraw Module	99
3.25	PixelAccess Class	99
3.26	PyAccess Module	101
3.27	PIL Package (autodoc of remaining modules)	101
3.28	Plugin reference	107
4	Porting	123
5	About	125
5.1	Goals	125
5.2	License	125
5.3	Why a fork?	125
5.4	What about PIL?	125
6	Release Notes	127
6.1	3.2.0	127
6.2	3.1.2	128
6.3	3.1.1	128
6.4	3.1.0	129
6.5	3.0.0	130
6.6	2.8.0	131
6.7	2.7.0	132
7	Indices and tables	135
	Python	137

Pillow [Alex Clark](#) PIL fork . PIL Fredrik Lundh Python Imaging Library.

1.1

```
: Pillow PIL . PillowPIL.
```

```
: Pillow >= 1.0 "import Image". "from PIL import Image" .
```

```
: Pillow >= 2.1.0 "import _imaging". "from PIL.Image import core as _imaging" .
```

1.2

```
: Pillow < 2.0.0 Python : 2.4, 2.5, 2.6, 2.7.
```

```
: Pillow >= 2.0.0 Python : 2.6, 2.7, 3.2, 3.3, 3.4, 3.5
```

1.3

```
: Pillow, , .
```

```
: WindowsOS XPyPI, .
```

pip Pillow:

```
$ pip install Pillow
```

pip easy_install Python Eggs

```
$ easy_install Pillow
```

1.3.1 Windows

3264wheel, eggexeWindows, :

```
$ pip install Pillow
```

:

```
$ easy_install Pillow
```

1.3.2 OS X

OS X Python, , OpenJPEG:

```
$ pip install Pillow
```

1.3.3 Linux

Linux. Linux, Fedora, Debian/Ubuntu ArchLinux Pillow, python-imaging.,.

1.3.4 FreeBSD

FreeBSDPorts:

Ports:

```
$ cd /usr/ports/graphics/py-pillow && make install clean
```

:

```
$ pkg install py27-pillow
```

: Pillow FreeBSD port ports , FreeBSD , Python 2.x and 3.x.

1.4

compressed archive from PyPI.

1.4.1

: Pillow . Zlib libjpeg .

```
: depends .
```

Pillow:

- **libjpeg** JPEG .
 - Pillow **6b**, **8**, **9**, **9a** libjpeg **8** libjpeg-turbo .
 - Pillow 3.0.0, libjpeg , --disable-jpeg .
- **zlib** PNGs
 - Pillow 3.0.0, zlib , --disable-zlib .
- **libtiff** TIFF
 - Pillow **3.x** and **4.0** libtiff .
- **libfreetype**
- **littlecms**
 - Pillow 2.2.1 liblcms1, Pillow 2.3.0 liblcms2. **1.19** **2.7** .
- **libwebp** WebP .
 - Pillow has been tested with version **0.1.3**, which does not read transparent WebP files. Versions **0.3.0** and above support transparency.
- **tcl/tk** tkinter bitmap photo images.
- **openjpeg** JPEG 2000 .
 - Pillow has been tested with openjpeg **2.0.0** and **2.1.0**.
 - Pillow does **not** support the earlier **1.5** series which ships with Ubuntu and Debian.

```
,:
```

```
$ pip install Pillow
```

```
(./usr /usr/local),.,setup.py setup.cfg,:
```

```
$ CFLAGS="-I/usr/pkg/include" pip install pillow
```

Pillow, --no-cache-dir pip, .

1.4.2

- Environment Variable: `MAX_CONCURRENCY=n`. By default, Pillow will use multiprocessing to build the extension on all available CPUs, but not more than 4. Setting `MAX_CONCURRENCY` to 1 will disable parallel building.
- Build flags: `--disable-zlib`, `--disable-jpeg`, `--disable-tiff`, `--disable-freetype`, `--disable-tcl`, `--disable-tk`, `--disable-lcms`, `--disable-webp`, `--disable-webpmux`, `--disable-jpeg2000`. Disable building the corresponding feature even if the development libraries are present on the building machine.
- Build flags: `--enable-zlib`, `--enable-jpeg`, `--enable-tiff`, `--enable-freetype`, `--enable-tcl`, `--enable-tk`, `--enable-lcms`, `--enable-webp`, `--enable-webpmux`, `--enable-jpeg2000`. Require that the corresponding feature is built. The build will raise an exception

if the libraries are not found. Webpmux (WebP metadata) relies on WebP support. Tcl and Tk also must be used together.

- Build flag: `--disable-platform-guessing`. Skips all of the platform dependent guessing of include and library directories for automated build systems that configure the proper paths in the environment variables (e.g. Buildroot).
- Build flag: `--debug`. Adds a debugging flag to the include and library search process to dump all paths searched for and found to stdout.

Sample Usage:

```
$ MAX_CONCURRENCY=1 python setup.py build_ext --enable-[feature] install
```

or using pip:

```
$ pip install pillow --global-option="build_ext" --global-option="--enable-[feature]"
```

1.4.3 OS X

Xcode is required to compile portions of Pillow. Either install the full package from the app store, or run `xcode-select --install` from the command line. It may be necessary to run `sudo xcodebuild -license` to accept the license prior to using the tools.

The easiest way to install external libraries is via [Homebrew](#). After you install Homebrew, run:

```
$ brew install libtiff libjpeg webp little-cms2
```

Install Pillow with:

```
$ pip install Pillow
```

or from within the uncompressed source directory:

```
$ python setup.py install
```

1.4.4 Windows

We don't recommend trying to build on Windows. It is a maze of twisty passages, mostly dead ends. There are build scripts and notes for the Windows build in the `winbuild` directory.

1.4.5 FreeBSD

: Only FreeBSD 10 tested

Make sure you have Python's development libraries installed.:

```
$ sudo pkg install python2
```

Or for Python 3:

```
$ sudo pkg install python3
```

Prerequisites are installed on **FreeBSD 10** with:

```
$ sudo pkg install jpeg tiff webp lcms2 freetype2
```

1.4.6 Linux

If you didn't build Python from source, make sure you have Python's development libraries installed. In Debian or Ubuntu:

```
$ sudo apt-get install python-dev python-setuptools
```

Or for Python 3:

```
$ sudo apt-get install python3-dev python3-setuptools
```

In Fedora, the command is:

```
$ sudo dnf install python-devel redhat-rpm-config
```

: redhat-rpm-config is required on Fedora 23, but not earlier versions.

Prerequisites are installed on **Ubuntu 12.04 LTS** or **Raspian Wheezy 7.0** with:

```
$ sudo apt-get install libtiff4-dev libjpeg8-dev zlib1g-dev \  
libfreetype6-dev liblcms2-dev libwebp-dev tcl8.5-dev tk8.5-dev python-tk
```

Prerequisites are installed on **Ubuntu 14.04 LTS** with:

```
$ sudo apt-get install libtiff5-dev libjpeg8-dev zlib1g-dev \  
libfreetype6-dev liblcms2-dev libwebp-dev tcl8.6-dev tk8.6-dev python-tk
```

Prerequisites are installed on **Fedora 23** with:

```
$ sudo dnf install libtiff-devel libjpeg-devel zlib-devel freetype-devel \  
lcms2-devel libwebp-devel tcl-devel tk-devel
```

1.5

Current platform support for Pillow. Binary distributions are contributed for each release on a volunteer basis, but the source should compile and run everywhere platform support is listed. In general, we aim to support all current versions of Linux, OS X, and Windows.

: Contributors please test Pillow on your platform then update this document and send a pull request.

Operating system	Supported	Tested Python versions	Latest tested Pillow version	Tested processors
Mac OS X 10.11 El Capitan	Yes	2.7,3.3,3.4,3.5	3.2.0	x86-64
Mac OS X 10.10 Yosemite	Yes	2.7,3.3,3.4	3.0.0	x86-64
Mac OS X 10.9 Mavericks	Yes	2.7,3.2,3.3,3.4	3.0.0	x86-64
Mac OS X 10.8 Mountain Lion	Yes	2.6,2.7,3.2,3.3		x86-64
Redhat Linux 6	Yes	2.6		x86
CentOS 6.3	Yes	2.7,3.3		x86
Fedora 23	Yes	2.7,3.4	3.1.0	x86-64
Ubuntu Linux 10.04 LTS	Yes	2.6	2.3.0	x86,x86-64
Ubuntu Linux 12.04 LTS	Yes	2.6,2.7,3.2,3.3,3.4,3.5 PyPy2.4,PyPy3,v2.3 2.7,3.2	3.1.0 2.6.1	x86,x86-64 ppc
Ubuntu Linux 14.04 LTS	Yes	2.7,3.4	3.1.0	x86-64
Debian 8.2 Jessie	Yes	2.7,3.4	3.1.0	x86-64
Raspian Jessie	Yes	2.7,3.4	3.1.0	arm
Gentoo Linux	Yes	2.7,3.2	2.1.0	x86-64
FreeBSD 10.2	Yes	2.7,3.4	3.1.0	x86-64
Windows 7 Pro	Yes	2.7,3.2,3.3	2.2.1	x86-64
Windows Server 2008 R2 Enterprise	Yes	3.3		x86-64
Windows Server 2012 R2	Yes	2.7,3.3,3.4	3.0.0	x86-64
Windows 8 Pro	Yes	2.6,2.7,3.2,3.3,3.4a3	2.2.0	x86,x86-64
Windows 8.1 Pro	Yes	2.6,2.7,3.2,3.3,3.4	2.4.0	x86,x86-64

1.6

PyPI Pillow. Python 2.x 3.x , url e.g. <https://pypi.python.org/pypi/Pillow/1.0>.

2.1

The **Python Imaging Library** adds image processing capabilities to your Python interpreter.

This library provides extensive file format support, an efficient internal representation, and fairly powerful image processing capabilities.

The core image library is designed for fast access to data stored in a few basic pixel formats. It should provide a solid foundation for a general image processing tool.

Let's look at a few possible uses of this library.

2.1.1

The Python Imaging Library is ideal for image archival and batch processing applications. You can use the library to create thumbnails, convert between file formats, print images, etc.

The current version identifies and reads a large number of formats. Write support is intentionally restricted to the most commonly used interchange and presentation formats.

2.1.2

The current release includes Tk *PhotoImage* and *BitmapImage* interfaces, as well as a *Windows DIB interface* that can be used with PythonWin and other Windows-based toolkits. Many other GUI toolkits come with some kind of PIL support.

For debugging, there's also a `show()` method which saves an image to disk, and calls an external display utility.

2.1.3

The library contains basic image processing functionality, including point operations, filtering with a set of built-in convolution kernels, and colour space conversions.

The library also supports image resizing, rotation and arbitrary affine transforms.

There's a histogram method allowing you to pull some statistics out of an image. This can be used for automatic contrast enhancement, and for global statistical analysis.

2.2

2.2.1 Image

Python *Image* , , , , .

, *Image* .open ()

```
>>> from PIL import Image
>>> im = Image.open("lena.ppm")
```

, *Image* .

```
>>> from __future__ import print_function
>>> print(im.format, im.size, im.mode)
PPM (512, 512) RGB
```

format , , None . size , , . mode band, () "L", "RGB", , "CMYK".

, IOError .

Image , , :

```
>>> im.show()
```

: *xv* , *show()* . , *xv* , , , .

2.2.2

Python. *Image* .open () , , .

To save a file, use the *save()* method of the *Image* class. When saving files, the name becomes important. Unless you specify the format, the library uses the filename extension to discover which file storage format to use.

Convert files to JPEG

```
from __future__ import print_function
import os, sys
from PIL import Image

for infile in sys.argv[1:]:
    f, e = os.path.splitext(infile)
    outfile = f + ".jpg"
    if infile != outfile:
        try:
            Image.open(infile).save(outfile)
        except IOError:
            print("cannot convert", infile)
```

A second argument can be supplied to the *save()* method which explicitly specifies a file format. If you use a non-standard extension, you must always specify the format this way:

Create JPEG thumbnails

```

from __future__ import print_function
import os, sys
from PIL import Image

size = (128, 128)

for infile in sys.argv[1:]:
    outfile = os.path.splitext(infile)[0] + ".thumbnail"
    if infile != outfile:
        try:
            im = Image.open(infile)
            im.thumbnail(size)
            im.save(outfile, "JPEG")
        except IOError:
            print("cannot create thumbnail for", infile)

```

It is important to note that the library doesn't decode or load the raster data unless it really has to. When you open a file, the file header is read to determine the file format and extract things like mode, size, and other properties required to decode the file, but the rest of the file is not processed until later.

This means that opening an image file is a fast operation, which is independent of the file size and compression type. Here's a simple script to quickly identify a set of image files:

Identify Image Files

```

from __future__ import print_function
import sys
from PIL import Image

for infile in sys.argv[1:]:
    try:
        with Image.open(infile) as im:
            print(infile, im.format, "%dx%d" % im.size, im.mode)
    except IOError:
        pass

```

2.2.3 Cutting, pasting, and merging images

The *Image* class contains methods allowing you to manipulate regions within an image. To extract a sub-rectangle from an image, use the *crop()* method.

Copying a subrectangle from an image

```

box = (100, 100, 400, 400)
region = im.crop(box)

```

The region is defined by a 4-tuple, where coordinates are (left, upper, right, lower). The Python Imaging Library uses a coordinate system with (0, 0) in the upper left corner. Also note that coordinates refer to positions between the pixels, so the region in the above example is exactly 300x300 pixels.

The region could now be processed in a certain manner and pasted back.

Processing a subrectangle, and pasting it back

```
region = region.transpose(Image.ROTATE_180)
im.paste(region, box)
```

When pasting regions back, the size of the region must match the given region exactly. In addition, the region cannot extend outside the image. However, the modes of the original image and the region do not need to match. If they don't, the region is automatically converted before being pasted (see the section on *Color transforms* below for details).

Here's an additional example:

Rolling an image

```
def roll(image, delta):
    "Roll an image sideways"

    xsize, ysize = image.size

    delta = delta % xsize
    if delta == 0: return image

    part1 = image.crop((0, 0, delta, ysize))
    part2 = image.crop((delta, 0, xsize, ysize))
    part1.load()
    part2.load()
    image.paste(part2, (0, 0, xsize-delta, ysize))
    image.paste(part1, (xsize-delta, 0, xsize, ysize))

    return image
```

Note that when pasting it back from the *crop()* operation, *load()* is called first. This is because cropping is a lazy operation. If *load()* was not called, then the crop operation would not be performed until the images were used in the paste commands. This would mean that *part1* would be cropped from the version of *image* already modified by the first paste.

For more advanced tricks, the paste method can also take a transparency mask as an optional argument. In this mask, the value 255 indicates that the pasted image is opaque in that position (that is, the pasted image should be used as is). The value 0 means that the pasted image is completely transparent. Values in-between indicate different levels of transparency. For example, pasting an RGBA image and also using it as the mask would paste the opaque portion of the image but not its transparent background.

The Python Imaging Library also allows you to work with the individual bands of an multi-band image, such as an RGB image. The *split* method creates a set of new images, each containing one band from the original multi-band image. The *merge* function takes a mode and a tuple of images, and combines them into a new image. The following sample swaps the three bands of an RGB image:

Splitting and merging bands

```
r, g, b = im.split()
im = Image.merge("RGB", (b, g, r))
```

Note that for a single-band image, *split()* returns the image itself. To work with individual color bands, you may want to convert the image to "RGB" first.

2.2.4 Geometrical transforms

The `PIL.Image.Image` class contains methods to `resize()` and `rotate()` an image. The former takes a tuple giving the new size, the latter the angle in degrees counter-clockwise.

Simple geometry transforms

```
out = im.resize((128, 128))
out = im.rotate(45) # degrees counter-clockwise
```

To rotate the image in 90 degree steps, you can either use the `rotate()` method or the `transpose()` method. The latter can also be used to flip an image around its horizontal or vertical axis.

Transposing an image

```
out = im.transpose(Image.FLIP_LEFT_RIGHT)
out = im.transpose(Image.FLIP_TOP_BOTTOM)
out = im.transpose(Image.ROTATE_90)
out = im.transpose(Image.ROTATE_180)
out = im.transpose(Image.ROTATE_270)
```

`transpose(ROTATE)` operations can also be performed identically with `rotate()` operations, provided the `expand` flag is true, to provide for the same changes to the image's size.

A more general form of image transformations can be carried out via the `transform()` method.

2.2.5 Color transforms

The Python Imaging Library allows you to convert images between different pixel representations using the `convert()` method.

Converting between modes

```
im = Image.open("lena.ppm").convert("L")
```

The library supports transformations between each supported mode and the “L” and “RGB” modes. To convert between other modes, you may have to use an intermediate image (typically an “RGB” image).

2.2.6 Image enhancement

The Python Imaging Library provides a number of methods and modules that can be used to enhance images.

Filters

The `ImageFilter` module contains a number of pre-defined enhancement filters that can be used with the `filter()` method.

Applying filters

```
from PIL import ImageFilter
out = im.filter(ImageFilter.DETAIL)
```

Point Operations

The `point()` method can be used to translate the pixel values of an image (e.g. image contrast manipulation). In most cases, a function object expecting one argument can be passed to this method. Each pixel is processed according to that function:

Applying point transforms

```
# multiply each pixel by 1.2
out = im.point(lambda i: i * 1.2)
```

Using the above technique, you can quickly apply any simple expression to an image. You can also combine the `point()` and `paste()` methods to selectively modify an image:

Processing individual bands

```
# split the image into individual bands
source = im.split()

R, G, B = 0, 1, 2

# select regions where red is less than 100
mask = source[R].point(lambda i: i < 100 and 255)

# process the green band
out = source[G].point(lambda i: i * 0.7)

# paste the processed band back, but only where red was < 100
source[G].paste(out, None, mask)

# build a new multiband image
im = Image.merge(im.mode, source)
```

Note the syntax used to create the mask:

```
imout = im.point(lambda i: expression and 255)
```

Python only evaluates the portion of a logical expression as is necessary to determine the outcome, and returns the last value examined as the result of the expression. So if the expression above is false (0), Python does not look at the second operand, and thus returns 0. Otherwise, it returns 255.

Enhancement

For more advanced image enhancement, you can use the classes in the `ImageEnhance` module. Once created from an image, an enhancement object can be used to quickly try out different settings.

You can adjust contrast, brightness, color balance and sharpness in this way.

Enhancing images

```
from PIL import ImageEnhance

enh = ImageEnhance.Contrast(im)
enh.enhance(1.3).show("30% more contrast")
```

2.2.7 Image sequences

The Python Imaging Library contains some basic support for image sequences (also called animation formats). Supported sequence formats include FLI/FLC, GIF, and a few experimental formats. TIFF files can also contain more than one frame.

When you open a sequence file, PIL automatically loads the first frame in the sequence. You can use the `seek` and `tell` methods to move between different frames:

Reading sequences

```
from PIL import Image

im = Image.open("animation.gif")
im.seek(1) # skip to the second frame

try:
    while 1:
        im.seek(im.tell()+1)
        # do something to im
except EOFError:
    pass # end of sequence
```

As seen in this example, you'll get an `EOFError` exception when the sequence ends.

Note that most drivers in the current version of the library only allow you to seek to the next frame (as in the above example). To rewind the file, you may have to reopen it.

The following class lets you use the `for`-statement to loop over the sequence:

Using the `ImageSequence` iterator class

```
from PIL import ImageSequence
for frame in ImageSequence.Iterator(im):
    # ...do something to frame...
```

2.2.8 Postscript printing

The Python Imaging Library includes functions to print images, text and graphics on Postscript printers. Here's a simple example:

Drawing Postscript

```
from PIL import Image
from PIL import PSDraw

im = Image.open("lena.ppm")
title = "lena"
box = (1*72, 2*72, 7*72, 10*72) # in points

ps = PSDraw.PSDraw() # default is sys.stdout
ps.begin_document(title)

# draw the image (75 dpi)
ps.image(box, im, 75)
ps.rectangle(box)

# draw title
ps.setfont("HelveticaNarrow-Bold", 36)
ps.text((3*72, 4*72), title)

ps.end_document()
```

2.2.9 More on reading images

As described earlier, the `open()` function of the `Image` module is used to open an image file. In most cases, you simply pass it the filename as an argument:

```
im = Image.open("lena.ppm")
```

If everything goes well, the result is an `PIL.Image.Image` object. Otherwise, an `IOError` exception is raised.

You can use a file-like object instead of the filename. The object must implement `read()`, `seek()` and `tell()` methods, and be opened in binary mode.

Reading from an open file

```
fp = open("lena.ppm", "rb")
im = Image.open(fp)
```

To read an image from string data, use the `StringIO` class:

Reading from a string

```
import StringIO

im = Image.open(StringIO.StringIO(buffer))
```

Note that the library rewinds the file (using `seek(0)`) before reading the image header. In addition, `seek` will also be used when the image data is read (by the `load` method). If the image file is embedded in a larger file, such as a tar file, you can use the `ContainerIO` or `TarIO` modules to access it.

Reading from a tar archive

```

from PIL import TarIO

fp = TarIO.TarIO("Imaging.tar", "Imaging/test/lena.ppm")
im = Image.open(fp)

```

2.2.10 Controlling the decoder

Some decoders allow you to manipulate the image while reading it from a file. This can often be used to speed up decoding when creating thumbnails (when speed is usually more important than quality) and printing to a monochrome laser printer (when only a greyscale version of the image is needed).

The `draft()` method manipulates an opened but not yet loaded image so it as closely as possible matches the given mode and size. This is done by reconfiguring the image decoder.

Reading in draft mode

```

from __future__ import print_function
im = Image.open(file)
print("original =", im.mode, im.size)

im.draft("L", (100, 100))
print("draft =", im.mode, im.size)

```

This prints something like:

```

original = RGB (512, 512)
draft = L (128, 128)

```

Note that the resulting image may not exactly match the requested mode and size. To make sure that the image is not larger than the given size, use the `thumbnail` method instead.

2.3 Concepts

The Python Imaging Library handles *raster images*; that is, rectangles of pixel data.

2.3.1 Bands

An image can consist of one or more bands of data. The Python Imaging Library allows you to store several bands in a single image, provided they all have the same dimensions and depth. For example, a PNG image might have ‘R’, ‘G’, ‘B’, and ‘A’ bands for the red, green, blue, and alpha transparency values. Many operations act on each band separately, e.g., histograms. It is often useful to think of each pixel as having one value per band.

To get the number and names of bands in an image, use the `getbands()` method.

2.3.2 Modes

The `mode` of an image defines the type and depth of a pixel in the image. The current release supports the following standard modes:

- 1 (1-bit pixels, black and white, stored with one pixel per byte)
- L (8-bit pixels, black and white)

- P (8-bit pixels, mapped to any other mode using a color palette)
- RGB (3x8-bit pixels, true color)
- RGBA (4x8-bit pixels, true color with transparency mask)
- CMYK (4x8-bit pixels, color separation)
- YCbCr (3x8-bit pixels, color video format)
 - Note that this refers to the JPEG, and not the ITU-R BT.2020, standard
- LAB (3x8-bit pixels, the L*a*b color space)
- HSV (3x8-bit pixels, Hue, Saturation, Value color space)
- I (32-bit signed integer pixels)
- F (32-bit floating point pixels)

PIL also provides limited support for a few special modes, including LA (L with alpha), RGBX (true color with padding) and RGBa (true color with premultiplied alpha). However, PIL doesn't support user-defined modes; if you to handle band combinations that are not listed above, use a sequence of Image objects.

You can read the mode of an image through the `mode` attribute. This is a string containing one of the above values.

2.3.3 Size

You can read the image size through the `size` attribute. This is a 2-tuple, containing the horizontal and vertical size in pixels.

2.3.4 Coordinate System

The Python Imaging Library uses a Cartesian pixel coordinate system, with (0,0) in the upper left corner. Note that the coordinates refer to the implied pixel corners; the centre of a pixel addressed as (0, 0) actually lies at (0.5, 0.5).

Coordinates are usually passed to the library as 2-tuples (x, y). Rectangles are represented as 4-tuples, with the upper left corner given first. For example, a rectangle covering all of an 800x600 pixel image is written as (0, 0, 800, 600).

2.3.5 Palette

The palette mode (P) uses a color palette to define the actual color for each pixel.

2.3.6 Info

You can attach auxiliary information to an image using the `info` attribute. This is a dictionary object.

How such information is handled when loading and saving image files is up to the file format handler (see the chapter on *Image file formats*). Most handlers add properties to the `info` attribute when loading an image, but ignore it when saving images.

2.3.7 Filters

For geometry operations that may map multiple input pixels to a single output pixel, the Python Imaging Library provides four different resampling *filters*.

NEAREST Pick the nearest pixel from the input image. Ignore all other input pixels.

BILINEAR For resize calculate the output pixel value using linear interpolation on all pixels that may contribute to the output value. For other transformations linear interpolation over a 2x2 environment in the input image is used.

BICUBIC For resize calculate the output pixel value using cubic interpolation on all pixels that may contribute to the output value. For other transformations cubic interpolation over a 4x4 environment in the input image is used.

LANCZOS Calculate the output pixel value using a high-quality Lanczos filter (a truncated sinc) on all pixels that may contribute to the output value. In the current version of PIL, this filter can only be used with the resize and thumbnail methods.

1.1.3 .

2.4 Appendices

: Contributors please include appendices as needed or appropriate with your bug fixes, feature additions and tests.

2.4.1 Image file formats

The Python Imaging Library supports a wide variety of raster file formats. Over 30 different file formats can be identified and read by the library. Write support is less extensive, but most common interchange and presentation formats are supported.

The `open()` function identifies files from their contents, not their names, but the `save()` method looks at the name to determine which format to use, unless the format is given explicitly.

Fully supported formats

BMP

PIL reads and writes Windows and OS/2 BMP files containing 1, L, P, or RGB data. 16-colour images are read as P images. Run-length encoding is not supported.

The `open()` method sets the following `info` properties:

compression Set to `bmp_rle` if the file is run-length encoded.

EPS

PIL identifies EPS files containing image data, and can read files that contain embedded raster images (ImageData descriptors). If Ghostscript is available, other EPS files can be read as well. The EPS driver can also write EPS images.

If Ghostscript is available, you can call the `load()` method with the following parameter to affect how Ghostscript renders the EPS

scale Affects the scale of the resultant rasterized image. If the EPS suggests that the image be rendered at 100px x 100px, setting this parameter to 2 will make the Ghostscript render a 200px x 200px image instead. The relative position of the bounding box is maintained:

```
im = Image.open(...)
im.size # (100, 100)
im.load(scale=2)
im.size # (200, 200)
```

GIF

PIL reads GIF87a and GIF89a versions of the GIF file format. The library writes run-length encoded files in GIF87a by default, unless GIF89a features are used or GIF89a is already in use.

Note that GIF files are always read as grayscale (L) or palette mode (P) images.

The `open()` method sets the following `info` properties:

background Default background color (a palette color index).

duration Time between frames in an animation (in milliseconds).

transparency Transparency color index. This key is omitted if the image is not transparent.

version Version (either GIF87a or GIF89a).

duration May not be present. The time to display each frame of the GIF, in milliseconds.

loop May not be present. The number of times the GIF should loop.

Reading sequences The GIF loader supports the `seek()` and `tell()` methods. You can seek to the next frame (`im.seek(im.tell() + 1)`), or rewind the file by seeking to the first frame. Random access is not supported.

`im.seek()` raises an `EOFError` if you try to seek after the last frame.

Saving sequences When calling `save()`, if a multiframe image is used, by default only the first frame will be saved. To save all frames, the `save_all` parameter must be present and set to `True`.

If present, the `loop` parameter can be used to set the number of times the GIF should loop, and the `duration` parameter can set the number of milliseconds between each frame.

Reading local images The GIF loader creates an image memory the same size as the GIF file's *logical screen size*, and pastes the actual pixel data (the *local image*) into this image. If you only want the actual pixel rectangle, you can manipulate the `size` and `tile` attributes before loading the file:

```
im = Image.open(...)

if im.tile[0][0] == "gif":
    # only read the first "local image" from this GIF file
    tag, (x0, y0, x1, y1), offset, extra = im.tile[0]
    im.size = (x1 - x0, y1 - y0)
    im.tile = [(tag, (0, 0) + im.size, offset, extra)]
```

ICNS

PIL reads and (OS X only) writes Mac OS X `.icns` files. By default, the largest available icon is read, though you can override this by setting the `size` property before calling `load()`. The `open()` method sets the following `info` property:

sizes A list of supported sizes found in this icon file; these are a 3-tuple, (*width*, *height*, *scale*), where *scale* is 2 for a retina icon and 1 for a standard icon. You *are* permitted to use this 3-tuple format for the *size* property if you set it before calling `load()`; after loading, the size will be reset to a 2-tuple containing pixel dimensions (so, e.g. if you ask for (512, 512, 2), the final value of *size* will be (1024, 1024)).

IM

IM is a format used by LabEye and other applications based on the IFUNC image processing library. The library reads and writes most uncompressed interchange versions of this format.

IM is the only format that can store all internal PIL formats.

JPEG

PIL reads JPEG, JFIF, and Adobe JPEG files containing L, RGB, or CMYK data. It writes standard and progressive JFIF files.

Using the `draft()` method, you can speed things up by converting RGB images to L, and resize images to 1/2, 1/4 or 1/8 of their original size while loading them.

The `open()` method may set the following `info` properties if available:

jfif JFIF application marker found. If the file is not a JFIF file, this key is not present.

jfif_version A tuple representing the jfif version, (major version, minor version).

jfif_density A tuple representing the pixel density of the image, in units specified by `jfif_unit`.

jfif_unit Units for the `jfif_density`:

- 0 - No Units
- 1 - Pixels per Inch
- 2 - Pixels per Centimeter

dpi A tuple representing the reported pixel density in pixels per inch, if the file is a jfif file and the units are in inches.

adobe Adobe application marker found. If the file is not an Adobe JPEG file, this key is not present.

adobe_transform Vendor Specific Tag.

progression Indicates that this is a progressive JPEG file.

icc_profile The ICC color profile for the image.

exif Raw EXIF data from the image.

The `save()` method supports the following options:

quality The image quality, on a scale from 1 (worst) to 95 (best). The default is 75. Values above 95 should be avoided; 100 disables portions of the JPEG compression algorithm, and results in large files with hardly any gain in image quality.

optimize If present, indicates that the encoder should make an extra pass over the image in order to select optimal encoder settings.

progressive If present, indicates that this image should be stored as a progressive JPEG file.

dpi A tuple of integers representing the pixel density, (*x*, *y*).

icc_profile If present, the image is stored with the provided ICC profile. If this parameter is not provided, the image will be saved with no profile attached. To preserve the existing profile:

```
im.save(filename, 'jpeg', icc_profile=im.info.get('icc_profile'))
```

exif If present, the image will be stored with the provided raw EXIF data.

subsampling If present, sets the subsampling for the encoder.

- `keep`: Only valid for JPEG files, will retain the original image setting.
- `4:4:4, 4:2:2, 4:1:1`: Specific sampling values
- `-1`: equivalent to `keep`
- `0`: equivalent to `4:4:4`
- `1`: equivalent to `4:2:2`
- `2`: equivalent to `4:1:1`

qtables If present, sets the qtables for the encoder. This is listed as an advanced option for wizards in the JPEG documentation. Use with caution. `qtables` can be one of several types of values:

- a string, naming a preset, e.g. `keep`, `web_low`, or `web_high`
- a list, tuple, or dictionary (with integer keys = `range(len(keys))`) of lists of 64 integers. There must be between 2 and 4 tables.

2.5.0 .

: To enable JPEG support, you need to build and install the IJG JPEG library before building the Python Imaging Library. See the distribution README for details.

JPEG 2000

2.4.0 .

PIL reads and writes JPEG 2000 files containing L, LA, RGB or RGBA data. It can also read files containing YCbCr data, which it converts on read into RGB or RGBA depending on whether or not there is an alpha channel. PIL supports JPEG 2000 raw codestreams (`.j2k` files), as well as boxed JPEG 2000 files (`.j2p` or `.jpx` files). PIL does *not* support files whose components have different sampling frequencies.

When loading, if you set the `mode` on the image prior to the `load()` method being invoked, you can ask PIL to convert the image to either RGB or RGBA rather than choosing for itself. It is also possible to set `reduce` to the number of resolutions to discard (each one reduces the size of the resulting image by a factor of 2), and `layers` to specify the number of quality layers to load.

The `save()` method supports the following options:

offset The image offset, as a tuple of integers, e.g. (16, 16)

tile_offset The tile offset, again as a 2-tuple of integers.

tile_size The tile size as a 2-tuple. If not specified, or if set to `None`, the image will be saved without tiling.

quality_mode Either “*rates*” or “*dB*” depending on the units you want to use to specify image quality.

quality_layers A sequence of numbers, each of which represents either an approximate size reduction (if quality mode is “*rates*”) or a signal to noise ratio value in decibels. If not specified, defaults to a single layer of full quality.

num_resolutions The number of different image resolutions to be stored (which corresponds to the number of Discrete Wavelet Transform decompositions plus one).

codeblock_size The code-block size as a 2-tuple. Minimum size is 4 x 4, maximum is 1024 x 1024, with the additional restriction that no code-block may have more than 4096 coefficients (i.e. the product of the two numbers must be no greater than 4096).

precinct_size The precinct size as a 2-tuple. Must be a power of two along both axes, and must be greater than the code-block size.

irreversible If `True`, use the lossy Irreversible Color Transformation followed by DWT 9-7. Defaults to `False`, which means to use the Reversible Color Transformation with DWT 5-3.

progression Controls the progression order; must be one of "LRCP", "RLCP", "RPCL", "PCRL", "CPRL". The letters stand for Component, Position, Resolution and Layer respectively and control the order of encoding, the idea being that e.g. an image encoded using LRCP mode can have its quality layers decoded as they arrive at the decoder, while one encoded using RLCP mode will have increasing resolutions decoded as they arrive, and so on.

cinema_mode Set the encoder to produce output compliant with the digital cinema specifications. The options here are "no" (the default), "cinema2k-24" for 24fps 2K, "cinema2k-48" for 48fps 2K, and "cinema4k-24" for 24fps 4K. Note that for compliant 2K files, *at least one* of your image dimensions must match 2048 x 1080, while for compliant 4K files, *at least one* of the dimensions must match 4096 x 2160.

: To enable JPEG 2000 support, you need to build and install the OpenJPEG library, version 2.0.0 or higher, before building the Python Imaging Library.

Windows users can install the OpenJPEG binaries available on the OpenJPEG website, but must add them to their PATH in order to use PIL (if you fail to do this, you will get errors about not being able to load the `_imaging DLL`).

MSP

PIL identifies and reads MSP files from Windows 1 and 2. The library writes uncompressed (Windows 1) versions of this format.

PCX

PIL reads and writes PCX files containing 1, L, P, or RGB data.

PNG

PIL identifies, reads, and writes PNG files containing 1, L, P, RGB, or RGBA data. Interlaced files are supported as of v1.1.7.

The `open()` method sets the following `info` properties, when appropriate:

gamma Gamma, given as a floating point number.

transparency For P images: Either the palette index for full transparent pixels, or a byte string with alpha values for each palette entry.

For L and RGB images, the color that represents full transparent pixels in this image.

This key is omitted if the image is not a transparent palette image.

`Open` also sets `Image.text` to a list of the values of the `tEXt`, `zTXt`, and `iTXt` chunks of the PNG image. Individual compressed chunks are limited to a decompressed size of `PngImagePlugin.MAX_TEXT_CHUNK`, by

default 1MB, to prevent decompression bombs. Additionally, the total size of all of the text chunks is limited to `PngImagePlugin.MAX_TEXT_MEMORY`, defaulting to 64MB.

The `save()` method supports the following options:

optimize If present, instructs the PNG writer to make the output file as small as possible. This includes extra processing in order to find optimal encoder settings.

transparency For P, L, and RGB images, this option controls what color image to mark as transparent.

For P images, this can be either the palette index, or a byte string with alpha values for each palette entry.

dpi A tuple of two numbers corresponding to the desired dpi in each direction.

pnginfo A `PIL.PngImagePlugin.PngInfo` instance containing text tags.

compress_level ZLIB compression level, a number between 0 and 9: 1 gives best speed, 9 gives best compression, 0 gives no compression at all. Default is 6. When `optimize` option is `True` `compress_level` has no effect (it is set to 9 regardless of a value passed).

bits (experimental) For P images, this option controls how many bits to store. If omitted, the PNG writer uses 8 bits (256 colors).

dictionary (experimental) Set the ZLIB encoder dictionary.

: To enable PNG support, you need to build and install the ZLIB compression library before building the Python Imaging Library. See the distribution README for details.

PPM

PIL reads and writes PBM, PGM and PPM files containing 1, L or RGB data.

SPIDER

PIL reads and writes SPIDER image files of 32-bit floating point data (“F;32F”).

PIL also reads SPIDER stack files containing sequences of SPIDER images. The `seek()` and `tell()` methods are supported, and random access is allowed.

The `open()` method sets the following attributes:

format Set to `SPIDER`

istack Set to 1 if the file is an image stack, else 0.

nimages Set to the number of images in the stack.

A convenience method, `convert2byte()`, is provided for converting floating point data to byte data (mode `L`):

```
im = Image.open('image001.spi').convert2byte()
```

Writing files in SPIDER format The extension of SPIDER files may be any 3 alphanumeric characters. Therefore the output format must be specified explicitly:

```
im.save('newimage.spi', format='SPIDER')
```

For more information about the SPIDER image processing package, see the [SPIDER homepage at Wadsworth Center](#).

TIFF

PIL reads and writes TIFF files. It can read both striped and tiled images, pixel and plane interleaved multi-band images, and either uncompressed, or Packbits, LZW, or JPEG compressed images.

If you have libtiff and its headers installed, PIL can read and write many more kinds of compressed TIFF files. If not, PIL will always write uncompressed files.

The `open()` method sets the following `info` properties:

compression Compression mode.

2.0.0 .

dpi Image resolution as an `(xdpi, ydpi)` tuple, where applicable. You can use the `tag` attribute to get more detailed information about the image resolution.

1.1.5 .

resolution Image resolution as an `(xres, yres)` tuple, where applicable. This is a measurement in whichever unit is specified by the file.

1.1.5 .

The `tag_v2` attribute contains a dictionary of TIFF metadata. The keys are numerical indexes from `TAGS_V2`. Values are strings or numbers for single items, multiple values are returned in a tuple of values. Rational numbers are returned as a *IFDRational* object.

3.0.0 .

For compatibility with legacy code, the `tag` attribute contains a dictionary of decoded TIFF fields as returned prior to version 3.0.0. Values are returned as either strings or tuples of numeric values. Rational numbers are returned as a tuple of `(numerator, denominator)`.

3.0.0 .

Saving Tiff Images The `save()` method can take the following keyword arguments:

tiffinfo

A *ImageFileDirectory_v2* object or dict object containing tiff tags and values. The TIFF field type is autodetected for Numeric and string values, any other types require using an *ImageFileDirectory_v2* object and setting the type in `tagtype` with the appropriate numerical value from `TiffTags.TYPES`.

2.3.0 .

Metadata values that are of the rational type should be passed in using a *IFDRational* object.

3.1.0 .

For compatibility with legacy code, a *ImageFileDirectory_v1* object may be passed in this field. However, this is deprecated.

3.0.0 .

: Only some tags are currently supported when writing using libtiff. The supported list is found in `LIBTIFF_CORE`.

compression A string containing the desired compression method for the file. (valid only with libtiff installed)
Valid compression methods are: `None`, `"tiff_ccitt"`, `"group3"`, `"group4"`, `"tiff_jpeg"`,

```
"tiff_adobe_deflate", "tiff_thunderscan", "tiff_deflate", "tiff_sgilog",  
"tiff_sgilog24", "tiff_raw_16"
```

These arguments to set the tiff header fields are an alternative to using the general tags available through `tiffinfo`.

description

software

date_time

artist

copyright Strings

resolution_unit A string of “inch”, “centimeter” or “cm”

resolution

x_resolution

y_resolution

dpi Either a Float, 2 tuple of (numerator, denominator) or a *IFDRational*. Resolution implies an equal x and y resolution, dpi also implies a unit of inches.

WebP

PIL reads and writes WebP files. The specifics of PIL’s capabilities with this format are currently undocumented.

The `save()` method supports the following options:

lossless If present, instructs the WEBP writer to use lossless compression.

quality Integer, 1-100, Defaults to 80. Sets the quality level for lossy compression.

icc_profile The ICC Profile to include in the saved file. Only supported if the system webp library was built with webpmux support.

exif The exif data to include in the saved file. Only supported if the system webp library was built with webpmux support.

XBM

PIL reads and writes X bitmap files (mode 1).

Read-only formats

CUR

CUR is used to store cursors on Windows. The CUR decoder reads the largest available cursor. Animated cursors are not supported.

DCX

DCX is a container file format for PCX files, defined by Intel. The DCX format is commonly used in fax applications. The DCX decoder can read files containing 1, L, P, or RGB data.

When the file is opened, only the first image is read. You can use `seek()` or *ImageSequence* to read other images.

DDS

DDS is a popular container texture format used in video games and natively supported by DirectX. Currently, only DXT1 and DXT5 pixel formats are supported and only in RGBA mode.

FLI, FLC

PIL reads Autodesk FLI and FLC animations.

The `open()` method sets the following `info` properties:

duration The delay (in milliseconds) between each frame.

FPX

PIL reads Kodak FlashPix files. In the current version, only the highest resolution image is read from the file, and the viewing transform is not taken into account.

: To enable full FlashPix support, you need to build and install the IJG JPEG library before building the Python Imaging Library. See the distribution README for details.

FTEX

3.2.0 .

The FTEX decoder reads textures used for 3D objects in Independence War 2: Edge Of Chaos. The plugin reads a single texture per file, in the compressed and uncompressed formats.

GBR

The GBR decoder reads GIMP brush files, version 1 and 2.

The `open()` method sets the following `info` properties:

comment The brush name.

spacing The spacing between the brushes, in pixels. Version 2 only.

GD

PIL reads uncompressed GD files. Note that this file format cannot be automatically identified, so you must use `PIL.GdImageFile.open()` to read such a file.

The `open()` method sets the following `info` properties:

transparency Transparency color index. This key is omitted if the image is not transparent.

ICO

ICO is used to store icons on Windows. The largest available icon is read.

The `save()` method supports the following options:

sizes A list of sizes including in this ico file; these are a 2-tuple, (width, height); Default to [(16, 16), (24, 24), (32, 32), (48, 48), (64, 64), (128, 128), (255, 255)]. Any size is bigger than the original size or 255 will be ignored.

IMT

PIL reads Image Tools images containing `L` data.

IPTC/NAA

PIL provides limited read support for IPTC/NAA newsphoto files.

MCIDAS

PIL identifies and reads 8-bit McIDAS area files.

MIC

PIL identifies and reads Microsoft Image Composer (MIC) files. When opened, the first sprite in the file is loaded. You can use `seek()` and `tell()` to read other sprites from the file.

MPO

Pillow identifies and reads Multi Picture Object (MPO) files, loading the primary image when first opened. The `seek()` and `tell()` methods may be used to read other pictures from the file. The pictures are zero-indexed and random access is supported.

PCD

PIL reads PhotoCD files containing RGB data. By default, the 768x512 resolution is read. You can use the `draft()` method to read the lower resolution versions instead, thus effectively resizing the image to 384x256 or 192x128. Higher resolutions cannot be read by the Python Imaging Library.

PIXAR

PIL provides limited support for PIXAR raster files. The library can identify and read “dumped” RGB files.

The format code is `PIXAR`.

PSD

PIL identifies and reads PSD files written by Adobe Photoshop 2.5 and 3.0.

SGI

PIL reads uncompressed L, RGB, and RGBA files.

TGA

PIL reads 24- and 32-bit uncompressed and run-length encoded TGA files.

WAL

1.1.4 .

PIL reads Quake2 WAL texture files.

Note that this file format cannot be automatically identified, so you must use the `open` function in the `WalImageFile` module to read files in this format.

By default, a Quake2 standard palette is attached to the texture. To override the palette, use the `putpalette` method.

XPM

PIL reads X pixmap files (mode P) with 256 colors or less.

The `open()` method sets the following `info` properties:

transparency Transparency color index. This key is omitted if the image is not transparent.

Write-only formats

PALM

PIL provides write-only support for PALM pixmap files.

The format code is `Palm`, the extension is `.palm`.

PDF

PIL can write PDF (Acrobat) images. Such images are written as binary PDF 1.1 files, using either JPEG or HEX encoding depending on the image mode (and whether JPEG support is available or not).

When calling `save()`, if a multiframe image is used, by default, only the first image will be saved. To save all frames, each frame to a separate page of the PDF, the `save_all` parameter must be present and set to `True`.

XV Thumbnails

PIL can read XV thumbnail files.

Identify-only formats

BUFR

1.1.3 .

PIL provides a stub driver for BUFR files.

To add read or write support to your application, use `PIL.BufrStubImagePlugin.register_handler()`.

FITS

1.1.5 .

PIL provides a stub driver for FITS files.

To add read or write support to your application, use `PIL.FitsStubImagePlugin.register_handler()`.

GRIB

1.1.5 .

PIL provides a stub driver for GRIB files.

The driver requires the file to start with a GRIB header. If you have files with embedded GRIB data, or files with multiple GRIB fields, your application has to seek to the header before passing the file handle to PIL.

To add read or write support to your application, use `PIL.GribStubImagePlugin.register_handler()`.

HDF5

1.1.5 .

PIL provides a stub driver for HDF5 files.

To add read or write support to your application, use `PIL.Hdf5StubImagePlugin.register_handler()`.

MPEG

PIL identifies MPEG files.

WMF

PIL can identify placable WMF files.

In PIL 1.1.4 and earlier, the WMF driver provides some limited rendering support, but not enough to be useful for any real application.

In PIL 1.1.5 and later, the WMF driver is a stub driver. To add WMF read or write support to your application, use `PIL.WmfImagePlugin.register_handler()` to register a WMF handler.

```

from PIL import Image
from PIL import WmfImagePlugin

class WmfHandler:
    def open(self, im):
        ...
    def load(self, im):
        ...
        return image
    def save(self, im, fp, filename):
        ...

wmf_handler = WmfHandler()

WmfImagePlugin.register_handler(wmf_handler)

im = Image.open("sample.wmf")

```

2.4.2 Writing Your Own File Decoder

The Python Imaging Library uses a plug-in model which allows you to add your own decoders to the library, without any changes to the library itself. Such plug-ins usually have names like `XxxImagePlugin.py`, where `Xxx` is a unique format name (usually an abbreviation).

: Pillow >= 2.1.0 no longer automatically imports any file in the Python path with a name ending in `ImagePlugin.py`. You will need to import your decoder manually.

A decoder plug-in should contain a decoder class, based on the `PIL.ImageFile.ImageFile` base class. This class should provide an `_open()` method, which reads the file header and sets up at least the `mode` and `size` attributes. To be able to load the file, the method must also create a list of `tile` descriptors. The class must be explicitly registered, via a call to the `Image` module.

For performance reasons, it is important that the `_open()` method quickly rejects files that do not have the appropriate contents.

Example

The following plug-in supports a simple format, which has a 128-byte header consisting of the words “SPAM” followed by the width, height, and pixel size in bits. The header fields are separated by spaces. The image data follows directly after the header, and can be either bi-level, greyscale, or 24-bit true color.

SpamImagePlugin.py:

```

from PIL import Image, ImageFile
import string

class SpamImageFile(ImageFile.ImageFile):

    format = "SPAM"
    format_description = "Spam raster image"

    def _open(self):

        # check header
        header = self.fp.read(128)

```

```
    if header[:4] != "SPAM":
        raise SyntaxError, "not a SPAM file"

    header = string.split(header)

    # size in pixels (width, height)
    self.size = int(header[1]), int(header[2])

    # mode setting
    bits = int(header[3])
    if bits == 1:
        self.mode = "1"
    elif bits == 8:
        self.mode = "L"
    elif bits == 24:
        self.mode = "RGB"
    else:
        raise SyntaxError, "unknown number of bits"

    # data descriptor
    self.tile = [
        ("raw", (0, 0) + self.size, 128, (self.mode, 0, 1))
    ]

Image.register_open("SPAM", SpamImageFile)

Image.register_extension("SPAM", ".spam")
Image.register_extension("SPAM", ".spa") # dos version
```

The format handler must always set the `size` and `mode` attributes. If these are not set, the file cannot be opened. To simplify the decoder, the calling code considers exceptions like `SyntaxError`, `KeyError`, and `IndexError`, as a failure to identify the file.

Note that the decoder must be explicitly registered using `PIL.Image.register_open()`. Although not required, it is also a good idea to register any extensions used by this format.

The `tile` attribute

To be able to read the file as well as just identifying it, the `tile` attribute must also be set. This attribute consists of a list of tile descriptors, where each descriptor specifies how data should be loaded to a given region in the image. In most cases, only a single descriptor is used, covering the full image.

The tile descriptor is a 4-tuple with the following contents:

```
(decoder, region, offset, parameters)
```

The fields are used as follows:

decoder Specifies which decoder to use. The `raw` decoder used here supports uncompressed data, in a variety of pixel formats. For more information on this decoder, see the description below.

region A 4-tuple specifying where to store data in the image.

offset Byte offset from the beginning of the file to image data.

parameters Parameters to the decoder. The contents of this field depends on the decoder specified by the first field in the tile descriptor tuple. If the decoder doesn't need any parameters, use `None` for this field.

Note that the `tile` attribute contains a list of tile descriptors, not just a single descriptor.

The raw decoder

The `raw` decoder is used to read uncompressed data from an image file. It can be used with most uncompressed file formats, such as PPM, BMP, uncompressed TIFF, and many others. To use the raw decoder with the `PIL.Image.frombytes()` function, use the following syntax:

```
image = Image.frombytes(
    mode, size, data, "raw",
    raw mode, stride, orientation
)
```

When used in a tile descriptor, the parameter field should look like:

```
(raw mode, stride, orientation)
```

The fields are used as follows:

raw mode The pixel layout used in the file, and is used to properly convert data to PIL's internal layout. For a summary of the available formats, see the table below.

stride The distance in bytes between two consecutive lines in the image. If 0, the image is assumed to be packed (no padding between lines). If omitted, the stride defaults to 0.

orientation

Whether the first line in the image is the top line on the screen (1), or the bottom line (-1). If omitted, the orientation defaults to 1.

The **raw mode** field is used to determine how the data should be unpacked to match PIL's internal pixel layout. PIL supports a large set of raw modes; for a complete list, see the table in the `Unpack.c` module. The following table describes some commonly used **raw modes**:

mode	description
1	1-bit bilevel, stored with the leftmost pixel in the most significant bit. 0 means black, 1 means white.
1;I	1-bit inverted bilevel, stored with the leftmost pixel in the most significant bit. 0 means white, 1 means black.
1;R	1-bit reversed bilevel, stored with the leftmost pixel in the least significant bit. 0 means black, 1 means white.
L	8-bit greyscale. 0 means black, 255 means white.
L;I	8-bit inverted greyscale. 0 means white, 255 means black.
P	8-bit palette-mapped image.
RGB	24-bit true colour, stored as (red, green, blue).
BGR	24-bit true colour, stored as (blue, green, red).
RGBX	24-bit true colour, stored as (blue, green, red, pad).
RGB;L	24-bit true colour, line interleaved (first all red pixels, the all green pixels, finally all blue pixels).

Note that for the most common cases, the raw mode is simply the same as the mode.

The Python Imaging Library supports many other decoders, including JPEG, PNG, and PackBits. For details, see the `decode.c` source file, and the standard plug-in implementations provided with the library.

Decoding floating point data

PIL provides some special mechanisms to allow you to load a wide variety of formats into a mode `F` (floating point) image memory.

You can use the `raw` decoder to read images where data is packed in any standard machine data type, using one of the following raw modes:

mode	description
F	32-bit native floating point.
F; 8	8-bit unsigned integer.
F; 8S	8-bit signed integer.
F; 16	16-bit little endian unsigned integer.
F; 16S	16-bit little endian signed integer.
F; 16B	16-bit big endian unsigned integer.
F; 16BS	16-bit big endian signed integer.
F; 16N	16-bit native unsigned integer.
F; 16NS	16-bit native signed integer.
F; 32	32-bit little endian unsigned integer.
F; 32S	32-bit little endian signed integer.
F; 32B	32-bit big endian unsigned integer.
F; 32BS	32-bit big endian signed integer.
F; 32N	32-bit native unsigned integer.
F; 32NS	32-bit native signed integer.
F; 32F	32-bit little endian floating point.
F; 32BF	32-bit big endian floating point.
F; 32NF	32-bit native floating point.
F; 64F	64-bit little endian floating point.
F; 64BF	64-bit big endian floating point.
F; 64NF	64-bit native floating point.

The bit decoder

If the raw decoder cannot handle your format, PIL also provides a special “bit” decoder that can be used to read various packed formats into a floating point image memory.

To use the bit decoder with the `frombytes` function, use the following syntax:

```
image = frombytes(  
    mode, size, data, "bit",  
    bits, pad, fill, sign, orientation  
)
```

When used in a tile descriptor, the parameter field should look like:

```
(bits, pad, fill, sign, orientation)
```

The fields are used as follows:

bits Number of bits per pixel (2-32). No default.

pad Padding between lines, in bits. This is either 0 if there is no padding, or 8 if lines are padded to full bytes. If omitted, the pad value defaults to 8.

fill Controls how data are added to, and stored from, the decoder bit buffer.

fill=0 Add bytes to the LSB end of the decoder buffer; store pixels from the MSB end.

fill=1 Add bytes to the MSB end of the decoder buffer; store pixels from the MSB end.

fill=2 Add bytes to the LSB end of the decoder buffer; store pixels from the LSB end.

fill=3 Add bytes to the MSB end of the decoder buffer; store pixels from the LSB end.

If omitted, the fill order defaults to 0.

sign If non-zero, bit fields are sign extended. If zero or omitted, bit fields are unsigned.

orientation Whether the first line in the image is the top line on the screen (1), or the bottom line (-1). If omitted, the orientation defaults to 1.

3.1 Image Module

The *Image* module provides a class with the same name which is used to represent a PIL image. The module also provides a number of factory functions, including functions to load images from files, and to create new images.

3.1.1 Examples

The following script loads an image, rotates it 45 degrees, and displays it using an external viewer (usually xv on Unix, and the paint program on Windows).

Open, rotate, and display an image (using the default viewer)

```
from PIL import Image
im = Image.open("bride.jpg")
im.rotate(45).show()
```

The following script creates nice 128x128 thumbnails of all JPEG images in the current directory.

Create thumbnails

```
from PIL import Image
import glob, os

size = 128, 128

for infile in glob.glob("*.jpg"):
    file, ext = os.path.splitext(infile)
    im = Image.open(infile)
    im.thumbnail(size)
    im.save(file + ".thumbnail", "JPEG")
```

3.1.2 Functions

`PIL.Image.open(fp, mode='r')`
Opens and identifies the given image file.

This is a lazy operation; this function identifies the file, but the file remains open and the actual image data is not read from the file until you try to process the data (or call the `load()` method). See `new()`.

- **fp** – A filename (string), `pathlib.Path` object or a file object. The file object must implement `read()`, `seek()`, and `tell()` methods, and be opened in binary mode.
- **mode** – The mode. If given, this argument must be “r”.

An *Image* object.

IOError – If the file cannot be found, or the image cannot be opened and identified.

: To protect against potential DOS attacks caused by “decompression bombs” (i.e. malicious files which decompress into a huge amount of data and are designed to crash or cause disruption by using up a lot of memory), Pillow will issue a *DecompressionBombWarning* if the image is over a certain limit. If desired, the warning can be turned into an error with `warnings.simplefilter('error', Image.DecompressionBombWarning)` or suppressed entirely with `warnings.simplefilter('ignore', Image.DecompressionBombWarning)`. See also the [logging documentation](#) to have warnings output to the logging facility instead of `stderr`.

Image processing

PIL. `Image.alpha_composite(im1, im2)`

Alpha composite `im2` over `im1`.

- **im1** – The first image. Must have mode RGBA.
- **im2** – The second image. Must have mode RGBA, and the same size as the first image.

An *Image* object.

PIL. `Image.blend(im1, im2, alpha)`

Creates a new image by interpolating between two input images, using a constant alpha.:

```
out = image1 * (1.0 - alpha) + image2 * alpha
```

- **im1** – The first image.
- **im2** – The second image. Must have the same mode and size as the first image.
- **alpha** – The interpolation alpha factor. If alpha is 0.0, a copy of the first image is returned. If alpha is 1.0, a copy of the second image is returned. There are no restrictions on the alpha value. If necessary, the result is clipped to fit into the allowed output range.

An *Image* object.

PIL. `Image.composite(image1, image2, mask)`

Create composite image by blending images using a transparency mask.

- **image1** – The first image.
- **image2** – The second image. Must have the same mode and size as the first image.

- **mask** – A mask image. This image can have mode “1”, “L”, or “RGBA”, and must have the same size as the other two images.

PIL. Image. **eval** (*image*, **args*)

Applies the function (which should take one argument) to each pixel in the given image. If the image has more than one band, the same function is applied to each band. Note that the function is evaluated once for each possible pixel value, so you cannot use random components or other generators.

- **image** – The input image.
- **function** – A function object, taking one integer argument.

An *Image* object.

PIL. Image. **merge** (*mode*, *bands*)

Merge a set of single band images into a new multiband image.

- **mode** – The mode to use for the output image. See: *Modes*.
- **bands** – A sequence containing one single-band image for each band in the output image. All bands must have the same size.

An *Image* object.

Constructing images

PIL. Image. **new** (*mode*, *size*, *color=0*)

Creates a new image with the given mode and size.

- **mode** – The mode to use for the new image. See: *Modes*.
- **size** – A 2-tuple, containing (width, height) in pixels.
- **color** – What color to use for the image. Default is black. If given, this should be a single integer or floating point value for single-band modes, and a tuple for multi-band modes (one value per band). When creating RGB images, you can also use color strings as supported by the ImageColor module. If the color is None, the image is not initialised.

An *Image* object.

PIL. Image. **fromarray** (*obj*, *mode=None*)

Creates an image memory from an object exporting the array interface (using the buffer protocol).

If *obj* is not contiguous, then the *tobytes* method is called and *frombuffer()* is used.

- **obj** – Object with array interface
- **mode** – Mode to use (will be determined from type if None) See: *Modes*.

An image object.

1.1.6 .

PIL. Image. **frombytes** (*mode*, *size*, *data*, *decoder_name='raw'*, **args*)

Creates a copy of an image memory from pixel data in a buffer.

In its simplest form, this function takes three arguments (mode, size, and unpacked pixel data).

You can also use any pixel decoder supported by PIL. For more information on available decoders, see the section *Writing Your Own File Decoder*.

Note that this function decodes pixel data only, not entire images. If you have an entire image in a string, wrap it in a `BytesIO` object, and use `open()` to load it.

- **mode** – The image mode. See: *Modes*.
- **size** – The image size.
- **data** – A byte buffer containing raw data for the given mode.
- **decoder_name** – What decoder to use.
- **args** – Additional parameters for the given decoder.

An *Image* object.

`PIL.Image.fromstring(*args, **kw)`

`PIL.Image.frombuffer(mode, size, data, decoder_name='raw', *args)`
Creates an image memory referencing pixel data in a byte buffer.

This function is similar to `frombytes()`, but uses data in the byte buffer, where possible. This means that changes to the original buffer object are reflected in this image). Not all modes can share memory; supported modes include “L”, “RGBX”, “RGBA”, and “CMYK”.

Note that this function decodes pixel data only, not entire images. If you have an entire image file in a string, wrap it in a `BytesIO` object, and use `open()` to load it.

In the current version, the default parameters used for the “raw” decoder differs from that used for `frombytes()`. This is a bug, and will probably be fixed in a future release. The current release issues a warning if you do this; to disable the warning, you should provide the full set of parameters. See below for details.

- **mode** – The image mode. See: *Modes*.
- **size** – The image size.
- **data** – A bytes or other buffer object containing raw data for the given mode.
- **decoder_name** – What decoder to use.
- **args** – Additional parameters for the given decoder. For the default encoder (“raw”), it’s recommended that you provide the full set of parameters:

```
frombuffer(mode, size, data, "raw", mode, 0, 1)
```

An *Image* object.

1.1.4 .

Registering plugins

: These functions are for use by plugin authors. Application authors can ignore them.

`PIL.Image.register_open(id, factory, accept=None)`

Register an image file plugin. This function should not be used in application code.

- **id** – An image format identifier.
- **factory** – An image file factory method.
- **accept** – An optional function that can be used to quickly reject images having another format.

`PIL.Image.register_mime(id, mimetype)`

Registers an image MIME type. This function should not be used in application code.

- **id** – An image format identifier.
- **mimetype** – The image MIME type for this format.

`PIL.Image.register_save(id, driver)`

Registers an image save function. This function should not be used in application code.

- **id** – An image format identifier.
- **driver** – A function to save images in this format.

`PIL.Image.register_extension(id, extension)`

Registers an image extension. This function should not be used in application code.

- **id** – An image format identifier.
- **extension** – An extension used for this format.

3.1.3 The Image Class

class `PIL.Image.Image`

This class represents an image object. To create *Image* objects, use the appropriate factory functions. There's hardly ever any reason to call the *Image* constructor directly.

- `open()`
- `new()`
- `frombytes()`

An instance of the *Image* class has the following methods. Unless otherwise stated, all methods return a new instance of the *Image* class, holding the resulting image.

`Image.convert(mode=None, matrix=None, dither=None, palette=0, colors=256)`

Returns a converted copy of this image. For the “P” mode, this method translates pixels through the palette. If mode is omitted, a mode is chosen so that all information in the image and the palette can be represented without a palette.

The current version supports all possible conversions between “L”, “RGB” and “CMYK.” The **matrix** argument only supports “L” and “RGB”.

When translating a color image to black and white (mode “L”), the library uses the ITU-R 601-2 luma transform:

$$L = R * 299/1000 + G * 587/1000 + B * 114/1000$$

The default method of converting a greyscale (“L”) or “RGB” image into a bilevel (mode “1”) image uses Floyd-Steinberg dither to approximate the original image luminosity levels. If dither is NONE, all non-zero values are set to 255 (white). To use other thresholds, use the `point()` method.

- **mode** – The requested mode. See: *Modes*.
- **matrix** – An optional conversion matrix. If given, this should be 4- or 12-tuple containing floating point values.
- **dither** – Dithering method, used when converting from mode “RGB” to “P” or from “RGB” or “L” to “1”. Available methods are NONE or FLOYDSTEINBERG (default).
- **palette** – Palette to use when converting from mode “RGB” to “P”. Available palettes are WEB or ADAPTIVE.
- **colors** – Number of colors to use for the ADAPTIVE palette. Defaults to 256.

Image

An *Image* object.

The following example converts an RGB image (linearly calibrated according to ITU-R 709, using the D65 luminant) to the CIE XYZ color space:

```
rgb2xyz = (  
    0.412453, 0.357580, 0.180423, 0,  
    0.212671, 0.715160, 0.072169, 0,  
    0.019334, 0.119193, 0.950227, 0 )  
out = im.convert("RGB", rgb2xyz)
```

`Image.copy()`

Copies this image. Use this method if you wish to paste things into an image, but still retain the original.

Image

An *Image* object.

`Image.crop(box=None)`

Returns a rectangular region from this image. The box is a 4-tuple defining the left, upper, right, and lower pixel coordinate.

This is a lazy operation. Changes to the source image may or may not be reflected in the cropped image. To break the connection, call the `load()` method on the cropped copy.

box – The crop rectangle, as a (left, upper, right, lower)-tuple.

Image

An *Image* object.

`Image.draft(mode, size)`

Configures the image file loader so it returns a version of the image that as closely as possible matches the given mode and size. For example, you can use this method to convert a color JPEG to greyscale while loading it, or to extract a 128x192 version from a PCD file.

Note that this method modifies the *Image* object in place. If the image has already been loaded, this method has no effect.

- **mode** – The requested mode.
- **size** – The requested size.

`Image.filter` (*filter*)

Filters this image using the given filter. For a list of available filters, see the *ImageFilter* module.

filter – Filter kernel.

An *Image* object.

`Image.getbands` ()

Returns a tuple containing the name of each band in this image. For example, **getbands** on an RGB image returns (“R”, “G”, “B”).

A tuple containing band names.

tuple

`Image.getbbox` ()

Calculates the bounding box of the non-zero regions in the image.

The bounding box is returned as a 4-tuple defining the left, upper, right, and lower pixel coordinate.

If the image is completely empty, this method returns None.

`Image.getcolors` (*maxcolors=256*)

Returns a list of colors used in this image.

maxcolors – Maximum number of colors. If this number is exceeded, this method returns None. The default limit is 256 colors.

An unsorted list of (count, pixel) values.

`Image.getdata` (*band=None*)

Returns the contents of this image as a sequence object containing pixel values. The sequence object is flattened, so that values for line one follow directly after the values of line zero, and so on.

Note that the sequence object returned by this method is an internal PIL data type, which only supports certain sequence operations. To convert it to an ordinary sequence (e.g. for printing), use **list(im.getdata())**.

band – What band to return. The default is to return all bands. To return a single band, pass in the index value (e.g. 0 to get the “R” band from an “RGB” image).

A sequence-like object.

`Image.getextrema` ()

Gets the the minimum and maximum pixel values for each band in the image.

For a single-band image, a 2-tuple containing the minimum and maximum pixel value. For a multi-band image, a tuple containing one 2-tuple for each band.

`Image.getpalette` ()

Returns the image palette as a list.

A list of color values [r, g, b, ...], or None if the image has no palette.

`Image.getpixel` (*xy*)

Returns the pixel value at a given position.

xy – The coordinate, given as (x, y).

The pixel value. If the image is a multi-layer image, this method returns a tuple.

`Image.histogram` (*mask=None, extrema=None*)

Returns a histogram for the image. The histogram is returned as a list of pixel counts, one for each pixel value in the source image. If the image has more than one band, the histograms for all bands are concatenated (for example, the histogram for an “RGB” image contains 768 values).

A bilevel image (mode “1”) is treated as a greyscale (“L”) image by this method.

If a mask is provided, the method returns a histogram for those parts of the image where the mask image is non-zero. The mask image must have the same size as the image, and be either a bi-level image (mode “1”) or a greyscale image (“L”).

mask – An optional mask.

A list containing pixel counts.

`Image.offset` (*xoffset*, *yoffset=None*)

`Image.paste` (*im*, *box=None*, *mask=None*)

Pastes another image into this image. The *box* argument is either a 2-tuple giving the upper left corner, a 4-tuple defining the left, upper, right, and lower pixel coordinate, or *None* (same as (0, 0)). If a 4-tuple is given, the size of the pasted image must match the size of the region.

If the modes don’t match, the pasted image is converted to the mode of this image (see the `convert()` method for details).

Instead of an image, the source can be a integer or tuple containing pixel values. The method then fills the region with the given color. When creating RGB images, you can also use color strings as supported by the `ImageColor` module.

If a mask is given, this method updates only the regions indicated by the mask. You can use either “1”, “L” or “RGBA” images (in the latter case, the alpha band is used as mask). Where the mask is 255, the given image is copied as is. Where the mask is 0, the current value is preserved. Intermediate values will mix the two images together, including their alpha channels if they have them.

See `alpha_composite()` if you want to combine images with respect to their alpha channels.

- **im** – Source image or pixel value (integer or tuple).
- **box** – An optional 4-tuple giving the region to paste into. If a 2-tuple is used instead, it’s treated as the upper left corner. If omitted or *None*, the source is pasted into the upper left corner.

If an image is given as the second argument and there is no third, the *box* defaults to (0, 0), and the second argument is interpreted as a mask image.
- **mask** – An optional mask image.

`Image.point` (*lut*, *mode=None*)

Maps this image through a lookup table or function.

- **lut** – A lookup table, containing 256 (or 65336 if `self.mode=="I"` and `mode=="L"`) values per band in the image. A function can be used instead, it should take a single argument. The function is called once for each possible pixel value, and the resulting table is applied to all bands of the image.
- **mode** – Output mode (default is same as input). In the current version, this can only be used if the source image has mode “L” or “P”, and the output has mode “1” or the source image mode is “I” and the output mode is “L”.

An *Image* object.

`Image.putalpha` (*alpha*)

Adds or replaces the alpha layer in this image. If the image does not have an alpha layer, it’s converted to “LA” or “RGBA”. The new layer must be either “L” or “1”.

alpha – The new alpha layer. This can either be an “L” or “1” image having the same size as this image, or an integer or other color value.

Image.**putdata** (*data*, *scale=1.0*, *offset=0.0*)

Copies pixel data to this image. This method copies data from a sequence object into the image, starting at the upper left corner (0, 0), and continuing until either the image or the sequence ends. The scale and offset values are used to adjust the sequence values: **pixel = value*scale + offset**.

- **data** – A sequence object.
- **scale** – An optional scale value. The default is 1.0.
- **offset** – An optional offset value. The default is 0.0.

Image.**putpalette** (*data*, *rawmode='RGB'*)

Attaches a palette to this image. The image must be a “P” or “L” image, and the palette sequence must contain 768 integer values, where each group of three values represent the red, green, and blue values for the corresponding pixel index. Instead of an integer sequence, you can use an 8-bit string.

data – A palette sequence (either a list or a string).

Image.**putpixel** (*xy*, *value*)

Modifies the pixel at the given position. The color is given as a single numerical value for single-band images, and a tuple for multi-band images.

Note that this method is relatively slow. For more extensive changes, use *paste()* or the *ImageDraw* module instead.

See:

- *paste()*
- *putdata()*
- *ImageDraw*

- **xy** – The pixel coordinate, given as (x, y).
- **value** – The pixel value.

Image.**quantize** (*colors=256*, *method=None*, *kmeans=0*, *palette=None*)

Convert the image to ‘P’ mode with the specified number of colors.

- **colors** – The desired number of colors, <= 256
- **method** – 0 = median cut 1 = maximum coverage 2 = fast octree
- **kmeans** – Integer
- **palette** – Quantize to the `PIL.ImagingPalette` palette.

A new image

Image.**resize** (*size*, *resample=0*)

Returns a resized copy of this image.

- **size** – The requested size in pixels, as a 2-tuple: (width, height).
- **resample** – An optional resampling filter. This can be one of `PIL.Image.NEAREST` (use `nearest neighbour`), `PIL.Image.BILINEAR` (linear interpolation), `PIL.Image.BICUBIC` (cubic spline interpolation), or `PIL.Image.LANCZOS` (a

high-quality downsampling filter). If omitted, or if the image has mode “1” or “P”, it is set `PIL.Image.NEAREST`.

An *Image* object.

`Image.rotate` (*angle*, *resample=0*, *expand=0*)

Returns a rotated copy of this image. This method returns a copy of this image, rotated the given number of degrees counter clockwise around its centre.

- **angle** – In degrees counter clockwise.
- **resample** – An optional resampling filter. This can be one of `PIL.Image.NEAREST` (use nearest neighbour), `PIL.Image.BILINEAR` (linear interpolation in a 2x2 environment), or `PIL.Image.BICUBIC` (cubic spline interpolation in a 4x4 environment). If omitted, or if the image has mode “1” or “P”, it is set `PIL.Image.NEAREST`.
- **expand** – Optional expansion flag. If true, expands the output image to make it large enough to hold the entire rotated image. If false or omitted, make the output image the same size as the input image.

An *Image* object.

`Image.save` (*fp*, *format=None*, ***params*)

Saves this image under the given filename. If no format is specified, the format to use is determined from the filename extension, if possible.

Keyword options can be used to provide additional instructions to the writer. If a writer doesn’t recognise an option, it is silently ignored. The available options are described in the [image format documentation](#) for each writer.

You can use a file object instead of a filename. In this case, you must always specify the format. The file object must implement the `seek`, `tell`, and `write` methods, and be opened in binary mode.

- **fp** – A filename (string), `pathlib.Path` object or file object.
- **format** – Optional format override. If omitted, the format to use is determined from the filename extension. If a file object was used instead of a filename, this parameter should always be used.
- **options** – Extra parameters to the image writer.

None

- **KeyError** – If the output format could not be determined from the file name. Use the `format` option to solve this.
- **IOError** – If the file could not be written. The file may have been created, and may contain partial data.

`Image.seek` (*frame*)

Seeks to the given frame in this sequence file. If you seek beyond the end of the sequence, the method raises an **EOFError** exception. When a sequence file is opened, the library automatically seeks to frame 0.

Note that in the current version of the library, most sequence formats only allows you to seek to the next frame.

See `tell()`.

frame – Frame number, starting at 0.

EOFError – If the call attempts to seek beyond the end of the sequence.

`Image.show` (*title=None, command=None*)

Displays this image. This method is mainly intended for debugging purposes.

On Unix platforms, this method saves the image to a temporary PPM file, and calls either the `xv` utility or the `display` utility, depending on which one can be found.

On OS X, this method saves the image to a temporary BMP file, and opens it with the native Preview application.

On Windows, it saves the image to a temporary BMP file, and uses the standard BMP display utility to show it (usually Paint).

- **title** – Optional title to use for the image window, where possible.
- **command** – command used to show the image

`Image.split` ()

Split this image into individual bands. This method returns a tuple of individual image bands from an image. For example, splitting an “RGB” image creates three new images each containing a copy of one of the original bands (red, green, blue).

A tuple containing bands.

`Image.tell` ()

Returns the current frame number. See `seek` ().

Frame number, starting with 0.

`Image.thumbnail` (*size, resample=3*)

Make this image into a thumbnail. This method modifies the image to contain a thumbnail version of itself, no larger than the given size. This method calculates an appropriate thumbnail size to preserve the aspect of the image, calls the `draft` () method to configure the file reader (where applicable), and finally resizes the image.

Note that this function modifies the `Image` object in place. If you need to use the full resolution image as well, apply this method to a `copy` () of the original image.

- **size** – Requested size.
- **resample** – Optional resampling filter. This can be one of `PIL.Image.NEAREST`, `PIL.Image.BILINEAR`, `PIL.Image.BICUBIC`, or `PIL.Image.LANCZOS`. If omitted, it defaults to `PIL.Image.BICUBIC`. (was `PIL.Image.NEAREST` prior to version 2.5.0)

None

`Image.tobitmap` (*name='image'*)

Returns the image converted to an X11 bitmap.

: This method only works for mode “1” images.

name – The name prefix to use for the bitmap variables.

A string containing an X11 bitmap.

ValueError – If the mode is not “1”

`Image.tobytes` (*encoder_name='raw', *args*)

Return image as a bytes object.

: This method returns the raw image data from the internal storage. For compressed image data (e.g. PNG, JPEG) use `save()`, with a BytesIO parameter for in-memory data.

- **encoder_name** – What encoder to use. The default is to use the standard “raw” encoder.
- **args** – Extra arguments to the encoder.

A bytes object.

`Image.tostring` (**args, **kw*)

`Image.transform` (*size, method, data=None, resample=0, fill=1*)

Transforms this image. This method creates a new image with the given size, and the same mode as the original, and copies data to the new image using the given transform.

- **size** – The output size.
- **method** – The transformation method. This is one of `PIL.Image.EXTENT` (cut out a rectangular subregion), `PIL.Image.AFFINE` (affine transform), `PIL.Image.PERSPECTIVE` (perspective transform), `PIL.Image.QUAD` (map a quadrilateral to a rectangle), or `PIL.Image.MESH` (map a number of source quadrilaterals in one operation).
- **data** – Extra data to the transformation method.
- **resample** – Optional resampling filter. It can be one of `PIL.Image.NEAREST` (use nearest neighbour), `PIL.Image.BILINEAR` (linear interpolation in a 2x2 environment), or `PIL.Image.BICUBIC` (cubic spline interpolation in a 4x4 environment). If omitted, or if the image has mode “I” or “P”, it is set to `PIL.Image.NEAREST`.

An *Image* object.

`Image.transpose` (*method*)

Transpose image (flip or rotate in 90 degree steps)

method – One of `PIL.Image.FLIP_LEFT_RIGHT`, `PIL.Image.FLIP_TOP_BOTTOM`, `PIL.Image.ROTATE_90`, `PIL.Image.ROTATE_180`, `PIL.Image.ROTATE_270` or `PIL.Image.TRANSPOSE`.

Returns a flipped or rotated copy of this image.

`Image.verify` ()

Verifies the contents of a file. For data read from a file, this method attempts to determine if the file is broken, without actually decoding the image data. If this method finds any problems, it raises suitable exceptions. If you need to load the image after using this method, you must reopen the image file.

`Image.fromstring` (**args, **kw*)

`Image.load` ()

Allocates storage for the image and loads the pixel data. In normal cases, you don’t need to call this method, since the Image class automatically loads an opened image when it is accessed for the first time. This method will close the file associated with the image.

An image access object.

PixelAccess Class or *PIL.PyAccess*

`Image.close()`

Closes the file pointer, if possible.

This operation will destroy the image core and release its memory. The image data will be unusable afterward.

This function is only required to close images that have not had their file read and closed by the `load()` method.

3.1.4 Attributes

Instances of the `Image` class have the following attributes:

`PIL.Image.format`

The file format of the source file. For images created by the library itself (via a factory function, or by running a method on an existing image), this attribute is set to `None`.

Type string or `None`

`PIL.Image.mode`

Image mode. This is a string specifying the pixel format used by the image. Typical values are “1”, “L”, “RGB”, or “CMYK.” See *Modes* for a full list.

Type string

`PIL.Image.size`

Image size, in pixels. The size is given as a 2-tuple (width, height).

Type (width, height)

`PIL.Image.width`

Image width, in pixels.

Type `int`

`PIL.Image.height`

Image height, in pixels.

Type `int`

`PIL.Image.palette`

Colour palette table, if any. If mode is “P”, this should be an instance of the `ImagePalette` class. Otherwise, it should be set to `None`.

Type `ImagePalette` or `None`

`PIL.Image.info`

A dictionary holding data associated with the image. This dictionary is used by file handlers to pass on various non-image information read from the file. See documentation for the various file handlers for details.

Most methods ignore the dictionary when returning new images; since the keys are not standardized, it’s not possible for a method to know if the operation affects the dictionary. If you need the information later on, keep a reference to the info dictionary returned from the open method.

Unless noted elsewhere, this dictionary does not affect saving files.

Type dict

3.2 ImageChops (“Channel Operations”) Module

The `ImageChops` module contains a number of arithmetical image operations, called channel operations (“chops”). These can be used for various purposes, including special effects, image compositions, algorithmic painting, and more.

For more pre-made operations, see `ImageOps`.

At this time, most channel operations are only implemented for 8-bit images (e.g. “L” and “RGB”).

3.2.1 Functions

Most channel operations take one or two image arguments and returns a new image. Unless otherwise noted, the result of a channel operation is always clipped to the range 0 to MAX (which is 255 for all modes supported by the operations in this module).

`PIL.ImageChops.add` (*image1*, *image2*, *scale=1.0*, *offset=0*)

Adds two images, dividing the result by *scale* and adding the *offset*. If omitted, *scale* defaults to 1.0, and *offset* to 0.0.

```
out = ((image1 + image2) / scale + offset)
```

Image

`PIL.ImageChops.add_modulo` (*image1*, *image2*)

Add two images, without clipping the result.

```
out = ((image1 + image2) % MAX)
```

Image

`PIL.ImageChops.blend` (*image1*, *image2*, *alpha*)

Blend images using constant transparency weight. Alias for `PIL.Image.Image.blend()`.

Image

`PIL.ImageChops.composite` (*image1*, *image2*, *mask*)

Create composite using transparency mask. Alias for `PIL.Image.Image.composite()`.

Image

`PIL.ImageChops.constant` (*image*, *value*)

Fill a channel with a given grey level.

Image

`PIL.ImageChops.darker` (*image1*, *image2*)

Compares the two images, pixel by pixel, and returns a new image containing the darker values.

```
out = min(image1, image2)
```

Image

`PIL.ImageChops.difference` (*image1*, *image2*)

Returns the absolute value of the pixel-by-pixel difference between the two images.

```
out = abs(image1 - image2)
```

Image

`PIL.ImageChops.duplicate(image)`
 Copy a channel. Alias for `PIL.Image.Image.copy()`.

Image

`PIL.ImageChops.invert(image)`
 Invert an image (channel).

```
out = MAX - image
```

Image

`PIL.ImageChops.lighter(image1, image2)`
 Compares the two images, pixel by pixel, and returns a new image containing the lighter values.

```
out = max(image1, image2)
```

Image

`PIL.ImageChops.logical_and(image1, image2)`
 Logical AND between two images.

```
out = ((image1 and image2) % MAX)
```

Image

`PIL.ImageChops.logical_or(image1, image2)`
 Logical OR between two images.

```
out = ((image1 or image2) % MAX)
```

Image

`PIL.ImageChops.multiply(image1, image2)`
 Superimposes two images on top of each other.

If you multiply an image with a solid black image, the result is black. If you multiply with a solid white image, the image is unaffected.

```
out = image1 * image2 / MAX
```

Image

`PIL.ImageChops.offset(image, xoffset, yoffset=None)`
 Returns a copy of the image where data has been offset by the given distances. Data wraps around the edges. If **yoffset** is omitted, it is assumed to be equal to **xoffset**.

- **xoffset** – The horizontal distance.
- **yoffset** – The vertical distance. If omitted, both distances are set to the same value.

Image

`PIL.ImageChops.screen(image1, image2)`

Superimposes two inverted images on top of each other.

```
out = MAX - ((MAX - image1) * (MAX - image2) / MAX)
```

Image

`PIL.ImageChops.subtract(image1, image2, scale=1.0, offset=0)`

Subtracts two images, dividing the result by scale and adding the offset. If omitted, scale defaults to 1.0, and offset to 0.0.

```
out = ((image1 - image2) / scale + offset)
```

Image

`PIL.ImageChops.subtract_modulo(image1, image2)`

Subtract two images, without clipping the result.

```
out = ((image1 - image2) % MAX)
```

Image

3.3 ImageColor Module

The `ImageColor` module contains color tables and converters from CSS3-style color specifiers to RGB tuples. This module is used by `PIL.Image.Image.new()` and the `ImageDraw` module, among others.

3.3.1 Color Names

The `ImageColor` module supports the following string formats:

- Hexadecimal color specifiers, given as `#rgb` or `#rrggbb`. For example, `#ff0000` specifies pure red.
- RGB functions, given as `rgb(red, green, blue)` where the color values are integers in the range 0 to 255. Alternatively, the color values can be given as three percentages (0% to 100%). For example, `rgb(255, 0, 0)` and `rgb(100%, 0%, 0%)` both specify pure red.
- Hue-Saturation-Lightness (HSL) functions, given as `hsl(hue, saturation%, lightness%)` where hue is the color given as an angle between 0 and 360 (red=0, green=120, blue=240), saturation is a value between 0% and 100% (gray=0%, full color=100%), and lightness is a value between 0% and 100% (black=0%, normal=50%, white=100%). For example, `hsl(0, 100%, 50%)` is pure red.
- Common HTML color names. The `ImageColor` module provides some 140 standard color names, based on the colors supported by the X Window system and most web browsers. color names are case insensitive. For example, `red` and `Red` both specify pure red.

3.3.2 Functions

`PIL.ImageColor.getrgb(color)`

Convert a color string to an RGB tuple. If the string cannot be parsed, this function raises a `ValueError` exception.

1.1.4 .

color – A color string
(red, green, blue[, alpha])

PIL. ImageColor.**getcolor**(color, mode)

Same as *getrgb()*, but converts the RGB value to a greyscale value if the mode is not color or a palette image. If the string cannot be parsed, this function raises a `ValueError` exception.

1.1.4 .

color – A color string
(graylevel [, alpha]) or (red, green, blue[, alpha])

3.4 ImageCms Module

The `ImageCms` module provides color profile management support using the LittleCMS2 color management engine, based on Kevin Cazabon's PyCMS library.

exception PIL. ImageCms. **PyCMSError**

(pyCMS) Exception class. This is used for all errors in the pyCMS API.

PIL. ImageCms. **applyTransform**(im, transform, inPlace=0)

(pyCMS) Applies a transform to a given image.

If `im.mode != transform.inMode`, a `PyCMSError` is raised.

If `inPlace == TRUE` and `transform.inMode != transform.outMode`, a `PyCMSError` is raised.

If `im.mode`, `transform.inMode`, or `transform.outMode` is not supported by `pyCMSdll` or the profiles you used for the transform, a `PyCMSError` is raised.

If an error occurs while the transform is being applied, a `PyCMSError` is raised.

This function applies a pre-calculated transform (from `ImageCms.buildTransform()` or `ImageCms.buildTransformFromOpenProfiles()`) to an image. The transform can be used for multiple images, saving considerable calculation time if doing the same conversion multiple times.

If you want to modify `im` in-place instead of receiving a new image as the return value, set `inPlace` to `TRUE`. This can only be done if `transform.inMode` and `transform.outMode` are the same, because we can't change the mode in-place (the buffer sizes for some modes are different). The default behavior is to return a new Image object of the same dimensions in mode `transform.outMode`.

- **im** – A PIL Image object, and `im.mode` must be the same as the `inMode` supported by the transform.
- **transform** – A valid `CmsTransform` class object
- **inPlace** – Bool (1 == True, 0 or None == False). If True, `im` is modified in place and None is returned, if False, a new Image object with the transform applied is returned (and `im` is not changed). The default is False.

Either None, or a new PIL Image object, depending on the value of `inPlace`. The profile will be returned in the image's `info['icc_profile']`.

PyCMSError –

PIL. ImageCms.**buildProofTransform** (*inputProfile, outputProfile, proofProfile, inMode, outMode, renderingIntent=0, proofRenderingIntent=3, flags=16384*)

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device.

If the input, output, or proof profiles specified are not valid filenames, a PyCMSError will be raised.

If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device using renderingIntent and proofRenderingIntent to determine what to do with out-of-gamut colors. This is known as “soft-proofing”. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Usage of the resulting transform object is exactly the same as with ImageCms.buildTransform().

Proof profiling is generally used when using an output device to get a good idea of what the final printed/displayed image would look like on the proofProfile device when it’s quicker and easier to use the output device for judging color. Generally, this means that the output device is a monitor, or a dye-sub printer (etc.), and the simulated device is something more expensive, complicated, or time consuming (making it difficult to make a real print for color judgement purposes).

Soft-proofing basically functions by adjusting the colors on the output device to match the colors of the device being simulated. However, when the simulated device has a much wider gamut than the output device, you may obtain marginal results.

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output (monitor, usually) profile you wish to use for this transform, or a profile object
- **proofProfile** – String, as a valid filename path to the ICC proof profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the input->proof (simulated) transform

INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)

see the pyCMS documentation for details on rendering intents and what they do.

- **proofRenderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for proof->output transform

```

INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)

```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

A CmsTransform class object.

PyCMSError –

PIL. ImageCms.**buildProofTransformFromOpenProfiles** (*inputProfile, outputProfile, proofProfile, inMode, outMode, renderingIntent=0, proofRenderingIntent=3, flags=16384*)

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device.

If the input, output, or proof profiles specified are not valid filenames, a PyCMSError will be raised.

If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile, but tries to simulate the result that would be obtained on the proofProfile device using renderingIntent and proofRenderingIntent to determine what to do with out-of-gamut colors. This is known as “soft-proofing”. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Usage of the resulting transform object is exactly the same as with ImageCms.buildTransform().

Proof profiling is generally used when using an output device to get a good idea of what the final printed/displayed image would look like on the proofProfile device when it’s quicker and easier to use the output device for judging color. Generally, this means that the output device is a monitor, or a dye-sub printer (etc.), and the simulated device is something more expensive, complicated, or time consuming (making it difficult to make a real print for color judgement purposes).

Soft-proofing basically functions by adjusting the colors on the output device to match the colors of the device being simulated. However, when the simulated device has a much wider gamut than the output device, you may obtain marginal results.

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output (monitor, usually) profile you wish to use for this transform, or a profile object
- **proofProfile** – String, as a valid filename path to the ICC proof profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)

- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the input->proof (simulated) transform

```
INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)
```

see the pyCMS documentation for details on rendering intents and what they do.

- **proofRenderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for proof->output transform

```
INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

A CmsTransform class object.

PyCMSError –

`PIL.ImageCms.buildTransform(inputProfile, outputProfile, inMode, outMode, renderingIntent=0, flags=0)`

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile. Use applyTransform to apply the transform to a given image.

If the input or output profiles specified are not valid filenames, a PyCMSError will be raised. If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile using the renderingIntent to determine what to do with out-of-gamut colors. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Building the transform is a fair part of the overhead in ImageCms.profileToProfile(), so if you’re planning on converting multiple images using the same input/output settings, this can save you time. Once you have a transform object, it can be used with ImageCms.applyProfile() to convert images without the need to re-compute the lookup table for the transform.

The reason pyCMS returns a class object rather than a handle directly to the transform is that it needs to keep track of the PIL input/output modes that the transform is meant for. These attributes are stored in the “inMode” and “outMode” attributes of the object (which can be manually overridden if you really want to, but I don’t know of any time that would be of use, or would even work).

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)

- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

```

INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)

```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

A CmsTransform class object.

PyCMSError –

PIL. ImageCms.**buildTransformFromOpenProfiles** (*inputProfile, outputProfile, inMode, outMode, renderingIntent=0, flags=0*)

(pyCMS) Builds an ICC transform mapping from the inputProfile to the outputProfile. Use applyTransform to apply the transform to a given image.

If the input or output profiles specified are not valid filenames, a PyCMSError will be raised. If an error occurs during creation of the transform, a PyCMSError will be raised.

If inMode or outMode are not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function builds and returns an ICC transform from the inputProfile to the outputProfile using the renderingIntent to determine what to do with out-of-gamut colors. It will ONLY work for converting images that are in inMode to images that are in outMode color format (PIL mode, i.e. “RGB”, “RGBA”, “CMYK”, etc.).

Building the transform is a fair part of the overhead in ImageCms.profileToProfile(), so if you’re planning on converting multiple images using the same input/output settings, this can save you time. Once you have a transform object, it can be used with ImageCms.applyProfile() to convert images without the need to re-compute the lookup table for the transform.

The reason pyCMS returns a class object rather than a handle directly to the transform is that it needs to keep track of the PIL input/output modes that the transform is meant for. These attributes are stored in the “inMode” and “outMode” attributes of the object (which can be manually overridden if you really want to, but I don’t know of any time that would be of use, or would even work).

- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this transform, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this transform, or a profile object
- **inMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **outMode** – String, as a valid PIL mode that the appropriate profile also supports (i.e. “RGB”, “RGBA”, “CMYK”, etc.)
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

```
INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)
```

see the pyCMS documentation for details on rendering intents and what they do.

- **flags** – Integer (0-...) specifying additional flags

A CmsTransform class object.

PyCMSError –

PIL. ImageCms.**createProfile** (*colorSpace*, *colorTemp=-1*)
(pyCMS) Creates a profile.

If *colorSpace* not in ["LAB", "XYZ", "sRGB"], a PyCMSError is raised

If using LAB and *colorTemp* != a positive integer, a PyCMSError is raised.

If an error occurs while creating the profile, a PyCMSError is raised.

Use this function to create common profiles on-the-fly instead of having to supply a profile on disk and knowing the path to it. It returns a normal CmsProfile object that can be passed to ImageCms.buildTransformFromOpenProfiles() to create a transform to apply to images.

- **colorSpace** – String, the color space of the profile you wish to create. Currently only "LAB", "XYZ", and "sRGB" are supported.
- **colorTemp** – Positive integer for the white point for the profile, in degrees Kelvin (i.e. 5000, 6500, 9600, etc.). The default is for D50 illuminant if omitted (5000k). *colorTemp* is ONLY applied to LAB profiles, and is ignored for XYZ and sRGB.

A CmsProfile class object

PyCMSError –

PIL. ImageCms.**getDefaultIntent** (*profile*)
(pyCMS) Gets the default intent name for the given profile.

If *profile* isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the default intent, a PyCMSError is raised.

Use this function to determine the default (and usually best optimized) rendering intent for this profile. Most profiles support multiple rendering intents, but are intended mostly for one type of conversion. If you wish to use a different intent than returned, use ImageCms.isIntentSupported() to verify it will work first.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

Integer 0-3 specifying the default rendering intent for this profile.

```
INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)
```

see the pyCMS documentation for details on rendering intents and what they do.

PyCMSError –

PIL. ImageCms.**getOpenProfile** (*profileFilename*)
(pyCMS) Opens an ICC profile file.

The PyCMSProfile object can be passed back into pyCMS for use in creating transforms and such (as in ImageCms.buildTransformFromOpenProfiles()).

If profileFilename is not a valid filename for an ICC profile, a PyCMSError will be raised.

profileFilename – String, as a valid filename path to the ICC profile you wish to open, or a file-like object.

A CmsProfile class object.

PyCMSError –

PIL. ImageCms.**getProfileCopyright** (*profile*)
(pyCMS) Gets the copyright for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the copyright tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's copyright tag.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal profile information stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**getProfileDescription** (*profile*)
(pyCMS) Gets the description for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the description tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's description tag.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal profile information stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**getProfileInfo** (*profile*)
(pyCMS) Gets the internal product information for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the info tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's info tag. This often contains details about the profile, and how it was created, as supplied by the creator.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal profile information stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**getProfileManufacturer** (*profile*)
(pyCMS) Gets the manufacturer for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the manufacturer tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's manufacturer tag.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal profile information stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**getProfileModel** (*profile*)
(pyCMS) Gets the model for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised.

If an error occurs while trying to obtain the model tag, a PyCMSError is raised

Use this function to obtain the information stored in the profile's model tag.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal profile information stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**getProfileName** (*profile*)
(pyCMS) Gets the internal product name for the given profile.

If profile isn't a valid CmsProfile object or filename to a profile, a PyCMSError is raised If an error occurs while trying to obtain the name tag, a PyCMSError is raised.

Use this function to obtain the INTERNAL name of the profile (stored in an ICC tag in the profile itself), usually the one used when the profile was originally created. Sometimes this tag also contains additional information supplied by the creator.

profile – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.

A string containing the internal name of the profile as stored in an ICC tag.

PyCMSError –

PIL. ImageCms.**get_display_profile** (*handle=None*)
(experimental) Fetches the profile for the current display device. :returns: None if the profile is not known.

PIL. ImageCms.**isIntentSupported** (*profile, intent, direction*)
(pyCMS) Checks if a given intent is supported.

Use this function to verify that you can use your desired renderingIntent with profile, and that profile can be used for the input/output/proof profile as you desire.

Some profiles are created specifically for one "direction", can cannot be used for others. Some profiles can only be used for certain rendering intents... so it's best to either verify this before trying to create a transform with them (using this function), or catch the potential PyCMSError that will occur if they don't support the modes you select.

- **profile** – EITHER a valid CmsProfile object, OR a string of the filename of an ICC profile.
- **intent** – Integer (0-3) specifying the rendering intent you wish to use with this profile
 - INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
 - INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
 - INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
 - INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)

see the pyCMS documentation for details on rendering intents and what they do.

- **direction** – Integer specifying if the profile is to be used for input, output, or proof
INPUT = 0 (or use ImageCms.DIRECTION_INPUT) OUTPUT = 1
(or use ImageCms.DIRECTION_OUTPUT) PROOF = 2 (or use ImageCms.DIRECTION_PROOF)

1 if the intent/direction are supported, -1 if they are not.

PyCMSError –

PIL. ImageCms.**profileToProfile**(*im, inputProfile, outputProfile, renderingIntent=0, outputMode=None, inPlace=0, flags=0*)

(pyCMS) Applies an ICC transformation to a given image, mapping from inputProfile to outputProfile.

If the input or output profiles specified are not valid filenames, a PyCMSError will be raised. If inPlace == TRUE and outputMode != im.mode, a PyCMSError will be raised. If an error occurs during application of the profiles, a PyCMSError will be raised. If outputMode is not a mode supported by the outputProfile (or by pyCMS), a PyCMSError will be raised.

This function applies an ICC transformation to im from inputProfile’s color space to outputProfile’s color space using the specified rendering intent to decide how to handle out-of-gamut colors.

OutputMode can be used to specify that a color mode conversion is to be done using these profiles, but the specified profiles must be able to handle that mode. I.e., if converting im from RGB to CMYK using profiles, the input profile must handle RGB data, and the output profile must handle CMYK data.

- **im** – An open PIL image object (i.e. Image.new(...) or Image.open(...), etc.)
- **inputProfile** – String, as a valid filename path to the ICC input profile you wish to use for this image, or a profile object
- **outputProfile** – String, as a valid filename path to the ICC output profile you wish to use for this image, or a profile object
- **renderingIntent** – Integer (0-3) specifying the rendering intent you wish to use for the transform

```

INTENT_PERCEPTUAL = 0 (DEFAULT) (ImageCms.INTENT_PERCEPTUAL)
INTENT_RELATIVE_COLORIMETRIC = 1 (ImageCms.INTENT_RELATIVE_COLORIMETRIC)
INTENT_SATURATION = 2 (ImageCms.INTENT_SATURATION)
INTENT_ABSOLUTE_COLORIMETRIC = 3 (ImageCms.INTENT_ABSOLUTE_COLORIMETRIC)

```

see the pyCMS documentation for details on rendering intents and what they do.

- **outputMode** – A valid PIL mode for the output image (i.e. “RGB”, “CMYK”, etc.). Note: if rendering the image “inPlace”, outputMode MUST be the same mode as the input, or omitted completely. If omitted, the outputMode will be the same as the mode of the input image (im.mode)
- **inPlace** – Boolean (1 = True, None or 0 = False). If True, the original image is modified in-place, and None is returned. If False (default), a new Image object is returned with the transform applied.
- **flags** – Integer (0-...) specifying additional flags

Either None or a new PIL image object, depending on value of inPlace

PyCMSError –

`PIL.ImageCms.versions()`
(pyCMS) Fetches versions.

3.4.1 CmsProfile

The ICC color profiles are wrapped in an instance of the class `CmsProfile`. The specification ICC.1:2010 contains more information about the meaning of the values in ICC profiles.

For convenience, all XYZ-values are also given as xyY-values (so they can be easily displayed in a chromaticity diagram, for example).

class `PIL.ImageCms.CmsProfile`

creation_date

Date and time this profile was first created (see 7.2.1 of ICC.1:2010).

Type `datetime.datetime` or `None`

version

The version number of the ICC standard that this profile follows (e.g. 2.0).

Type `float`

icc_version

Same as `version`, but in encoded format (see 7.2.4 of ICC.1:2010).

device_class

4-character string identifying the profile class. One of `scnr`, `mnr`, `prtr`, `link`, `spac`, `abst`, `nmcl` (see 7.2.5 of ICC.1:2010 for details).

Type `string`

xcolor_space

4-character string (padded with whitespace) identifying the color space, e.g. `XYZ_`, `RGB_` or `CMYK` (see 7.2.6 of ICC.1:2010 for details).

Note that the deprecated attribute `color_space` contains an interpreted (non-padded) variant of this (but can be empty on unknown input).

Type `string`

connection_space

4-character string (padded with whitespace) identifying the color space on the B-side of the transform (see 7.2.7 of ICC.1:2010 for details).

Note that the deprecated attribute `pcs` contains an interpreted (non-padded) variant of this (but can be empty on unknown input).

Type `string`

header_flags

The encoded header flags of the profile (see 7.2.11 of ICC.1:2010 for details).

Type `int`

header_manufacturer

4-character string (padded with whitespace) identifying the device manufacturer, which shall match the signature contained in the appropriate section of the ICC signature registry found at www.color.org (see 7.2.12 of ICC.1:2010).

Type `string`

header_model

4-character string (padded with whitespace) identifying the device model, which shall match the signature contained in the appropriate section of the ICC signature registry found at www.color.org (see 7.2.13 of ICC.1:2010).

Type `string`

attributes

Flags used to identify attributes unique to the particular device setup for which the profile is applicable (see 7.2.14 of ICC.1:2010 for details).

Type `int`

rendering_intent

The rendering intent to use when combining this profile with another profile (usually overridden at runtime, but provided here for DeviceLink and embedded source profiles, see 7.2.15 of ICC.1:2010).

One of `ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`.

Type `int`

profile_id

A sequence of 16 bytes identifying the profile (via a specially constructed MD5 sum), or 16 binary zeroes if the profile ID has not been calculated (see 7.2.18 of ICC.1:2010).

Type `bytes`

copyright

The text copyright information for the profile (see 9.2.21 of ICC.1:2010).

Type `unicode` or `None`

manufacturer

The (english) display string for the device manufacturer (see 9.2.22 of ICC.1:2010).

Type `unicode` or `None`

model

The (english) display string for the device model of the device for which this profile is created (see 9.2.23 of ICC.1:2010).

Type `unicode` or `None`

profile_description

The (english) display string for the profile description (see 9.2.41 of ICC.1:2010).

Type `unicode` or `None`

target

The name of the registered characterization data set, or the measurement data for a characterization target (see 9.2.14 of ICC.1:2010).

Type `unicode` or `None`

red_colorant

The first column in the matrix used in matrix/TRC transforms (see 9.2.44 of ICC.1:2010).

Type `((X, Y, Z), (x, y, Y))` or `None`

green_colorant

The second column in the matrix used in matrix/TRC transforms (see 9.2.30 of ICC.1:2010).

Type `((X, Y, Z), (x, y, Y))` or `None`

blue_colorant

The third column in the matrix used in matrix/TRC transforms (see 9.2.4 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

luminance

The absolute luminance of emissive devices in candelas per square metre as described by the Y channel (see 9.2.32 of ICC.1:2010).

Type ((X, Y, Z), (x, y, Y)) or None

chromaticity

The data of the phosphor/colorant chromaticity set used (red, green and blue channels, see 9.2.16 of ICC.1:2010).

Type ((x, y, Y), (x, y, Y), (x, y, Y)) or None

chromatic_adaption

The chromatic adaption matrix converts a color measured using the actual illumination conditions and relative to the actual adopted white, to an color relative to the PCS adopted white, with complete adaptation from the actual adopted white chromaticity to the PCS adopted white chromaticity (see 9.2.15 of ICC.1:2010).

Two matrices are returned, one in (X, Y, Z) space and one in (x, y, Y) space.

Type 2-tuple of 3-tuple, the first with (X, Y, Z) and the second with (x, y, Y) values

colorant_table

This tag identifies the colorants used in the profile by a unique name and set of PCSXYZ or PCSLAB values (see 9.2.19 of ICC.1:2010).

Type list of strings

colorant_table_out

This tag identifies the colorants used in the profile by a unique name and set of PCSLAB values (for DeviceLink profiles only, see 9.2.19 of ICC.1:2010).

Type list of strings

colorimetric_intent

4-character string (padded with whitespace) identifying the image state of PCS colorimetry produced using the colorimetric intent transforms (see 9.2.20 of ICC.1:2010 for details).

Type string or None

perceptual_rendering_intent_gamut

4-character string (padded with whitespace) identifying the (one) standard reference medium gamut (see 9.2.37 of ICC.1:2010 for details).

Type string or None

saturation_rendering_intent_gamut

4-character string (padded with whitespace) identifying the (one) standard reference medium gamut (see 9.2.37 of ICC.1:2010 for details).

Type string or None

technology

4-character string (padded with whitespace) identifying the device technology (see 9.2.47 of ICC.1:2010 for details).

Type string or None

media_black_point

This tag specifies the media black point and is used for generating absolute colorimetry.

This tag was available in ICC 3.2, but it is removed from version 4.

Type ((X, Y, Z), (x, y, Y)) or None

media_white_point_temperature

Calculates the white point temperature (see the LCMS documentation for more information).

Type *float* or *None*

viewing_condition

The (english) display string for the viewing conditions (see 9.2.48 of ICC.1:2010).

Type *unicode* or *None*

screening_description

The (english) display string for the screening conditions.

This tag was available in ICC 3.2, but it is removed from version 4.

Type *unicode* or *None*

red_primary

The XYZ-transformed of the RGB primary color red (1, 0, 0).

Type ((X, Y, Z), (x, y, Y)) or None

green_primary

The XYZ-transformed of the RGB primary color green (0, 1, 0).

Type ((X, Y, Z), (x, y, Y)) or None

blue_primary

The XYZ-transformed of the RGB primary color blue (0, 0, 1).

Type ((X, Y, Z), (x, y, Y)) or None

is_matrix_shaper

True if this profile is implemented as a matrix shaper (see documentation on LCMS).

Type *bool*

clut

Returns a dictionary of all supported intents and directions for the CLUT model.

The dictionary is indexed by intents (`ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`).

The values are 3-tuples indexed by directions (`ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT`, `ImageCms.DIRECTION_PROOF`).

The elements of the tuple are booleans. If the value is `True`, that intent is supported for that direction.

Type *dict* of boolean 3-tuples

intent_supported

Returns a dictionary of all supported intents and directions.

The dictionary is indexed by intents (`ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`).

The values are 3-tuples indexed by directions (`ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT`, `ImageCms.DIRECTION_PROOF`).

The elements of the tuple are booleans. If the value is `True`, that intent is supported for that direction.

Type dict of boolean 3-tuples

color_space

Deprecated but retained for backwards compatibility. Interpreted value of `xcolor_space`. May be the empty string if value could not be decoded.

Type string

pcs

Deprecated but retained for backwards compatibility. Interpreted value of `connection_space`. May be the empty string if value could not be decoded.

Type string

product_model

Deprecated but retained for backwards compatibility. ASCII-encoded value of `model`.

Type string

product_manufacturer

Deprecated but retained for backwards compatibility. ASCII-encoded value of `manufacturer`.

Type string

product_copyright

Deprecated but retained for backwards compatibility. ASCII-encoded value of `copyright`.

Type string

product_description

Deprecated but retained for backwards compatibility. ASCII-encoded value of `profile_description`.

Type string

product_desc

Deprecated but retained for backwards compatibility. ASCII-encoded value of `profile_description`.

This alias of `product_description` used to contain a derived informative string about the profile, depending on the value of the description, copyright, manufacturer and model fields).

Type string

There is one function defined on the class:

is_intent_supported (*intent*, *direction*)

Returns if the intent is supported for the given direction.

Note that you can also get this information for all intents and directions with `intent_supported`.

- **intent** – One of `ImageCms.INTENT_ABSOLUTE_COLORIMETRIC`, `ImageCms.INTENT_PERCEPTUAL`, `ImageCms.INTENT_RELATIVE_COLORIMETRIC` and `ImageCms.INTENT_SATURATION`.
- **direction** – One of `ImageCms.DIRECTION_INPUT`, `ImageCms.DIRECTION_OUTPUT` and `ImageCms.DIRECTION_PROOF`

Boolean if the intent and direction is supported.

3.5 ImageDraw Module

The `ImageDraw` module provide simple 2D graphics for *Image* objects. You can use this module to create new images, annotate or retouch existing images, and to generate graphics on the fly for web use.

For a more advanced drawing library for PIL, see the `aggdraw` module.

3.5.1 Example: Draw a gray cross over an image

```
from PIL import Image, ImageDraw

im = Image.open("lena.pgm")

draw = ImageDraw.Draw(im)
draw.line((0, 0) + im.size, fill=128)
draw.line((0, im.size[1], im.size[0], 0), fill=128)
del draw

# write to stdout
im.save(sys.stdout, "PNG")
```

3.5.2 Concepts

Coordinates

The graphics interface uses the same coordinate system as PIL itself, with (0, 0) in the upper left corner.

Colors

To specify colors, you can use numbers or tuples just as you would use with `PIL.Image.Image.new()` or `PIL.Image.Image.putpixel()`. For “1”, “L”, and “I” images, use integers. For “RGB” images, use a 3-tuple containing integer values. For “F” images, use integer or floating point values.

For palette images (mode “P”), use integers as color indexes. In 1.1.4 and later, you can also use RGB 3-tuples or color names (see below). The drawing layer will automatically assign color indexes, as long as you don’t draw with more than 256 colors.

Color Names

See *Color Names* for the color names supported by Pillow.

Fonts

PIL can use bitmap fonts or OpenType/TrueType fonts.

Bitmap fonts are stored in PIL’s own format, where each font typically consists of a two files, one named `.pil` and the other usually named `.pbm`. The former contains font metrics, the latter raster data.

To load a bitmap font, use the load functions in the *ImageFont* module.

To load a OpenType/TrueType font, use the `truetype` function in the *ImageFont* module. Note that this function depends on third-party libraries, and may not available in all PIL builds.

3.5.3 Example: Draw Partial Opacity Text

```

from PIL import Image, ImageDraw, ImageFont
# get an image
base = Image.open('Pillow/Tests/images/lena.png').convert('RGBA')

# make a blank image for the text, initialized to transparent text color
txt = Image.new('RGBA', base.size, (255,255,255,0))

# get a font
fnt = ImageFont.truetype('Pillow/Tests/fonts/FreeMono.ttf', 40)
# get a drawing context
d = ImageDraw.Draw(txt)

# draw text, half opacity
d.text((10,10), "Hello", font=fnt, fill=(255,255,255,128))
# draw text, full opacity
d.text((10,60), "World", font=fnt, fill=(255,255,255,255))

out = Image.alpha_composite(base, txt)

out.show()

```

3.5.4 Functions

class `PIL.ImageDraw.Draw` (*im, mode=None*)
 Creates an object that can be used to draw in the given image.

Note that the image will be modified in place.

- **im** – The image to draw in.
- **mode** – Optional mode to use for color values. For RGB images, this argument can be RGB or RGBA (to blend the drawing into the image). For all other modes, this argument must be the same as the image mode. If omitted, the mode defaults to the mode of the image.

3.5.5 Methods

`PIL.ImageDraw.Draw.arc` (*xy, start, end, fill=None*)
 Draws an arc (a portion of a circle outline) between the start and end angles, inside the given bounding box.

- **xy** – Four points to define the bounding box. Sequence of [(x0, y0), (x1, y1)] or [x0, y0, x1, y1].
- **start** – Starting angle, in degrees. Angles are measured from 3 o’clock, increasing clockwise.
- **end** – Ending angle, in degrees.
- **fill** – Color to use for the arc.

`PIL.ImageDraw.Draw.bitmap` (*xy, bitmap, fill=None*)
 Draws a bitmap (mask) at the given position, using the current fill color for the non-zero portions. The bitmap should be a valid transparency mask (mode “1”) or matte (mode “L” or “RGBA”).

This is equivalent to doing `image.paste(xy, color, bitmap)`.

To paste pixel data into an image, use the `paste()` method on the image itself.

`PIL.ImageDraw.Draw.chord(xy, start, end, fill=None, outline=None)`

Same as `arc()`, but connects the end points with a straight line.

- **xy** – Four points to define the bounding box. Sequence of `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.

`PIL.ImageDraw.Draw.ellipse(xy, fill=None, outline=None)`

Draws an ellipse inside the given bounding box.

- **xy** – Four points to define the bounding box. Sequence of either `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.

`PIL.ImageDraw.Draw.line(xy, fill=None, width=0)`

Draws a line between the coordinates in the **xy** list.

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **fill** – Color to use for the line.
- **width** – The line width, in pixels. Note that line joins are not handled well, so wide polylines will not look good.

1.1.5 .

: This option was broken until version 1.1.6.

`PIL.ImageDraw.Draw.pieslice(xy, start, end, fill=None, outline=None)`

Same as `arc`, but also draws straight lines between the end points and the center of the bounding box.

- **xy** – Four points to define the bounding box. Sequence of `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`.
- **start** – Starting angle, in degrees. Angles are measured from 3 o'clock, increasing clockwise.
- **end** – Ending angle, in degrees.
- **fill** – Color to use for the fill.
- **outline** – Color to use for the outline.

`PIL.ImageDraw.Draw.point(xy, fill=None)`

Draws points (individual pixels) at the given coordinates.

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **fill** – Color to use for the point.

`PIL.ImageDraw.Draw.polyagon(xy, fill=None, outline=None)`

Draws a polygon.

The polygon outline consists of straight lines between the given coordinates, plus a straight line between the last and the first coordinate.

- **xy** – Sequence of either 2-tuples like `[(x, y), (x, y), ...]` or numeric values like `[x, y, x, y, ...]`.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.

`PIL.ImageDraw.Draw.rectangle(xy, fill=None, outline=None)`

Draws a rectangle.

- **xy** – Four points to define the bounding box. Sequence of either `[(x0, y0), (x1, y1)]` or `[x0, y0, x1, y1]`. The second point is just outside the drawn rectangle.
- **outline** – Color to use for the outline.
- **fill** – Color to use for the fill.

`PIL.ImageDraw.Draw.shape(shape, fill=None, outline=None)`

: This method is experimental.

Draw a shape.

`PIL.ImageDraw.Draw.text(xy, text, fill=None, font=None, anchor=None, spacing=0, align="left")`

Draws the string at the given position.

- **xy** – Top left corner of the text.
- **text** – Text to be drawn. If it contains any newline characters, the text is passed on to `multiline_text()`
- **fill** – Color to use for the text.
- **font** – An `ImageFont` instance.
- **spacing** – If the text is passed on to `multiline_text()`, the number of pixels between lines.
- **align** – If the text is passed on to `multiline_text()`, “left”, “center” or “right”.

`PIL.ImageDraw.Draw.multiline_text(xy, text, fill=None, font=None, anchor=None, spacing=0, align="left")`

Draws the string at the given position.

- **xy** – Top left corner of the text.
- **text** – Text to be drawn.

- **fill** – Color to use for the text.
- **font** – An ImageFont instance.
- **spacing** – The number of pixels between lines.
- **align** – “left”, “center” or “right”.

PIL.ImageDraw.Draw.**textsize** (*text*, *font=None*, *spacing=0*)
Return the size of the given string, in pixels.

- **text** – Text to be measured. If it contains any newline characters, the text is passed on to `multiline_textsize()`
- **font** – An ImageFont instance.
- **spacing** – If the text is passed on to `multiline_textsize()`, the number of pixels between lines.

PIL.ImageDraw.Draw.**multiline_textsize** (*text*, *font=None*, *spacing=0*)
Return the size of the given string, in pixels.

- **text** – Text to be measured.
- **font** – An ImageFont instance.
- **spacing** – The number of pixels between lines.

3.5.6 Legacy API

The `Draw` class contains a constructor and a number of methods which are provided for backwards compatibility only. For this to work properly, you should either use options on the drawing primitives, or these methods. Do not mix the old and new calling conventions.

PIL.ImageDraw.**ImageDraw** (*image*)

Draw

PIL.ImageDraw.Draw.**setfont** (*font*)

1.1.5.

Sets the default font to use for the text method.

font – An ImageFont instance.

3.6 ImageEnhance Module

The ImageEnhance module contains a number of classes that can be used for image enhancement.

3.6.1 Example: Vary the sharpness of an image

```
from PIL import ImageEnhance

enhancer = ImageEnhance.Sharpness(image)

for i in range(8):
```

```
factor = i / 4.0
enhancer.enhance(factor).show("Sharpness %f" % factor)
```

Also see the `enhancer.py` demo program in the `Scripts/` directory.

3.6.2 Classes

All enhancement classes implement a common interface, containing a single method:

class `PIL.ImageEnhance._Enhance`

enhance (*factor*)

Returns an enhanced image.

factor – A floating point value controlling the enhancement. Factor 1.0 always returns a copy of the original image, lower factors mean less color (brightness, contrast, etc), and higher values more. There are no restrictions on this value.

Image

class `PIL.ImageEnhance.Color` (*image*)

Adjust image color balance.

This class can be used to adjust the colour balance of an image, in a manner similar to the controls on a colour TV set. An enhancement factor of 0.0 gives a black and white image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Contrast` (*image*)

Adjust image contrast.

This class can be used to control the contrast of an image, similar to the contrast control on a TV set. An enhancement factor of 0.0 gives a solid grey image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Brightness` (*image*)

Adjust image brightness.

This class can be used to control the brightness of an image. An enhancement factor of 0.0 gives a black image. A factor of 1.0 gives the original image.

class `PIL.ImageEnhance.Sharpness` (*image*)

Adjust image sharpness.

This class can be used to adjust the sharpness of an image. An enhancement factor of 0.0 gives a blurred image, a factor of 1.0 gives the original image, and a factor of 2.0 gives a sharpened image.

3.7 ImageFile Module

The `ImageFile` module provides support functions for the image open and save functions.

In addition, it provides a `Parser` class which can be used to decode an image piece by piece (e.g. while receiving it over a network connection). This class implements the same consumer interface as the standard `sgmlib` and `xmllib` modules.

3.7.1 Example: Parse an image

```

from PIL import ImageFile

fp = open("lena.pgm", "rb")

p = ImageFile.Parser()

while 1:
    s = fp.read(1024)
    if not s:
        break
    p.feed(s)

im = p.close()

im.save("copy.jpg")

```

3.7.2 Parser

class `PIL.ImageFile.Parser`

Incremental image parser. This class implements the standard feed/close consumer interface.

In Python 2.x, this is an old-style class.

close()

(Consumer) Close the stream.

An image object.

IOError – If the parser failed to parse the image file either because it cannot be identified or cannot be decoded.

feed(*data*)

(Consumer) Feed data to the parser.

data – A string buffer.

IOError – If the parser failed to parse the image file.

reset()

(Consumer) Reset the parser. Note that you can only call this method immediately after you've created a parser; parser instances cannot be reused.

3.8 ImageFilter Module

The `ImageFilter` module contains definitions for a pre-defined set of filters, which can be used with the `Image.filter()` method.

3.8.1 Example: Filter an image

```

from PIL import ImageFilter

im1 = im.filter(ImageFilter.BLUR)

im2 = im.filter(ImageFilter.MinFilter(3))
im3 = im.filter(ImageFilter.MinFilter) # same as MinFilter(3)

```

3.8.2 Filters

The current version of the library provides the following set of predefined image enhancement filters:

- **BLUR**
- **CONTOUR**
- **DETAIL**
- **EDGE_ENHANCE**
- **EDGE_ENHANCE_MORE**
- **EMBOSS**
- **FIND_EDGES**
- **SMOOTH**
- **SMOOTH_MORE**
- **SHARPEN**

class `PIL.ImageFilter.GaussianBlur` (*radius=2*)
Gaussian blur filter.

radius – Blur radius.

class `PIL.ImageFilter.UnsharpMask` (*radius=2, percent=150, threshold=3*)
Unsharp mask filter.

See Wikipedia’s entry on [digital unsharp masking](#) for an explanation of the parameters.

- **radius** – Blur Radius
- **percent** – Unsharp strength, in percent
- **threshold** – Threshold controls the minimum brightness change that will be sharpened

class `PIL.ImageFilter.Kernel` (*size, kernel, scale=None, offset=0*)

Create a convolution kernel. The current version only supports 3x3 and 5x5 integer and floating point kernels.

In the current version, kernels can only be applied to “L” and “RGB” images.

- **size** – Kernel size, given as (width, height). In the current version, this must be (3,3) or (5,5).
- **kernel** – A sequence containing kernel weights.
- **scale** – Scale factor. If given, the result for each pixel is divided by this value. the default is the sum of the kernel weights.
- **offset** – Offset. If given, this value is added to the result, after it has been divided by the scale factor.

class `PIL.ImageFilter.RankFilter` (*size, rank*)

Create a rank filter. The rank filter sorts all pixels in a window of the given size, and returns the **rank**’th value.

- **size** – The kernel size, in pixels.

- **rank** – What pixel value to pick. Use 0 for a min filter, $\text{size} * \text{size} / 2$ for a median filter, $\text{size} * \text{size} - 1$ for a max filter, etc.

class `PIL.ImageFilter.MedianFilter` (*size=3*)

Create a median filter. Picks the median pixel value in a window with the given size.

size – The kernel size, in pixels.

class `PIL.ImageFilter.MinFilter` (*size=3*)

Create a min filter. Picks the lowest pixel value in a window with the given size.

size – The kernel size, in pixels.

class `PIL.ImageFilter.MaxFilter` (*size=3*)

Create a max filter. Picks the largest pixel value in a window with the given size.

size – The kernel size, in pixels.

class `PIL.ImageFilter.ModeFilter` (*size=3*)

Create a mode filter. Picks the most frequent pixel value in a box with the given size. Pixel values that occur only once or twice are ignored; if no pixel value occurs more than twice, the original pixel value is preserved.

size – The kernel size, in pixels.

3.9 ImageFont Module

The `ImageFont` module defines a class with the same name. Instances of this class store bitmap fonts, and are used with the `PIL.ImageDraw.Draw.text()` method.

PIL uses its own font file format to store bitmap fonts. You can use the `:command:pilfont` utility to convert BDF and PCF font descriptors (X window font formats) to this format.

Starting with version 1.1.4, PIL can be configured to support TrueType and OpenType fonts (as well as other font formats supported by the FreeType library). For earlier versions, TrueType support is only available as part of the `imToolkit` package

3.9.1 Example

```
from PIL import ImageFont, ImageDraw

draw = ImageDraw.Draw(image)

# use a bitmap font
font = ImageFont.load("arial.pil")

draw.text((10, 10), "hello", font=font)

# use a truetype font
font = ImageFont.truetype("arial.ttf", 15)

draw.text((10, 25), "world", font=font)
```

3.9.2 Functions

`PIL.ImageFont.load` (*filename*)

Load a font file. This function loads a font object from the given bitmap font file, and returns the corresponding

font object.

filename – Name of font file.

A font object.

IOError – If the file could not be read.

PIL. ImageFont. **load_path** (*filename*)

Load font file. Same as *load()*, but searches for a bitmap font along the Python path.

filename – Name of font file.

A font object.

IOError – If the file could not be read.

PIL. ImageFont. **truetype** (*font=None, size=10, index=0, encoding=''*)

Load a TrueType or OpenType font file, and create a font object. This function loads a font object from the given file, and creates a font object for a font of the given size.

This function requires the `_imagingft` service.

- **font** – A truetype font file. Under Windows, if the file is not found in this filename, the loader also looks in Windows `fonts/` directory.
- **size** – The requested size, in points.
- **index** – Which font face to load (default is first available face).
- **encoding** – Which font encoding to use (default is Unicode). Common encodings are “unic” (Unicode), “symb” (Microsoft Symbol), “ADOB” (Adobe Standard), “ADBE” (Adobe Expert), and “armn” (Apple Roman). See the FreeType documentation for more information.

A font object.

IOError – If the file could not be read.

PIL. ImageFont. **load_default** ()

Load a “better than nothing” default font.

1.1.4 .

A font object.

3.9.3 Methods

PIL. ImageFont. ImageFont. **getsize** (*text*)

(width, height)

PIL. ImageFont. ImageFont. **getmask** (*text, mode=''*)

Create a bitmap for the text.

If the font uses antialiasing, the bitmap should have mode “L” and use a maximum value of 255. Otherwise, it should have mode “1”.

- **text** – Text to render.

- **mode** – Used by some graphics drivers to indicate what mode the driver prefers; if empty, the renderer may return either mode. Note that the mode is always a string, to simplify C-level implementations.

1.1.5 .

An internal PIL storage memory instance as defined by the `PIL.Image.core` interface module.

3.10 ImageGrab Module (OS X and Windows only)

The `ImageGrab` module can be used to copy the contents of the screen or the clipboard to a PIL image memory.

: The current version works on OS X and Windows only.

1.1.3 .

`PIL.ImageGrab.grab` (*bbox=None*)

Take a snapshot of the screen. The pixels inside the bounding box are returned as an “RGB” image on Windows or “RGBA” on OS X. If the bounding box is omitted, the entire screen is copied.

1.1.3 : (Windows), 3.0.0 (OS X)

bbox – What region to copy. Default is the entire screen.

An image

`PIL.ImageGrab.grabclipboard` ()

Take a snapshot of the clipboard image, if any.

1.1.4 : (Windows), 3.3.0 (OS X)

On Windows, an image, a list of filenames, or `None` if the clipboard does not contain image data or filenames. Note that if a list is returned, the filenames may not represent image files.

On Mac, an image, or `None` if the clipboard does not contain image data.

3.11 ImageMath Module

The `ImageMath` module can be used to evaluate “image expressions”. The module provides a single `eval` function, which takes an expression string and one or more images.

3.11.1 Example: Using the `ImageMath` module

```
from PIL import Image, ImageMath

im1 = Image.open("image1.jpg")
im2 = Image.open("image2.jpg")

out = ImageMath.eval("convert(min(a, b), 'L')", a=im1, b=im2)
out.save("result.png")
```

`PIL.ImageMath.eval` (*expression, environment*)
Evaluate expression in the given environment.

In the current version, *ImageMath* only supports single-layer images. To process multi-band images, use the *split()* method or *merge()* function.

- **expression** – A string which uses the standard Python expression syntax. In addition to the standard operators, you can also use the functions described below.
- **environment** – A dictionary that maps image names to Image instances. You can use one or more keyword arguments instead of a dictionary, as shown in the above example. Note that the names must be valid Python identifiers.

An image, an integer value, a floating point value, or a pixel tuple, depending on the expression.

3.11.2 Expression syntax

Expressions are standard Python expressions, but they're evaluated in a non-standard environment. You can use PIL methods as usual, plus the following set of operators and functions:

Standard Operators

You can use standard arithmetical operators for addition (+), subtraction (-), multiplication (*), and division (/).

The module also supports unary minus (-), modulo (%), and power (**) operators.

Note that all operations are done with 32-bit integers or 32-bit floating point values, as necessary. For example, if you add two 8-bit images, the result will be a 32-bit integer image. If you add a floating point constant to an 8-bit image, the result will be a 32-bit floating point image.

You can force conversion using the `convert()`, `float()`, and `int()` functions described below.

Bitwise Operators

The module also provides operations that operate on individual bits. This includes and (&), or (|), and exclusive or (^). You can also invert (~) all pixel bits.

Note that the operands are converted to 32-bit signed integers before the bitwise operation is applied. This means that you'll get negative values if you invert an ordinary greyscale image. You can use the and (&) operator to mask off unwanted bits.

Bitwise operators don't work on floating point images.

Logical Operators

Logical operators like `and`, `or`, and `not` work on entire images, rather than individual pixels.

An empty image (all pixels zero) is treated as false. All other images are treated as true.

Note that `and` and `or` return the last evaluated operand, while `not` always returns a boolean value.

Built-in Functions

These functions are applied to each individual pixel.

abs (*image*)

Absolute value.

convert (*image, mode*)

Convert image to the given mode. The mode must be given as a string constant.

float (*image*)

Convert image to 32-bit floating point. This is equivalent to `convert(image, "F")`.

int (*image*)

Convert image to 32-bit integer. This is equivalent to `convert(image, "I")`.

Note that 1-bit and 8-bit images are automatically converted to 32-bit integers if necessary to get a correct result.

max (*image1, image2*)

Maximum value.

min (*image1, image2*)

Minimum value.

3.12 ImageMorph Module

The ImageMorph module provides morphology operations on images.

class `PIL.ImageMorph.LutBuilder` (*patterns=None, op_name=None*)

object

A class for building a MorphLut from a descriptive language

The input patterns is a list of a strings sequences like these:

```
4: (. . .
  . 1 .
  1 1 1) -> 1
```

(whitespaces including linebreaks are ignored). The option 4 describes a series of symmetry operations (in this case a 4-rotation), the pattern is described by:

- or X - Ignore
- 1 - Pixel is on
- 0 - Pixel is off

The result of the operation is described after “->” string.

The default is to return the current pixel value, which is returned if no other match is found.

Operations:

- 4 - 4 way rotation
- N - Negate
- 1 - Dummy op for no other operation (an op must always be given)
- M - Mirroring

Example:

```
lb = LutBuilder(patterns = ["4:(... .1. 111)->1"])
lut = lb.build_lut()
```

add_patterns (*patterns*)

build_default_lut ()

build_lut ()

Compile all patterns into a morphology lut.

TBD :Build based on (file) morphlut:modify_lut

get_lut ()

class PIL. ImageMorph. **MorphOp** (*lut=None, op_name=None, patterns=None*)

object

A class for binary morphological operators

apply (*image*)

Run a single morphological operation on an image

Returns a tuple of the number of changed pixels and the morphed image

get_on_pixels (*image*)

Get a list of all turned on pixels in a binary image

Returns a list of tuples of (x,y) coordinates of all matching pixels.

load_lut (*filename*)

Load an operator from an mrl file

match (*image*)

Get a list of coordinates matching the morphological operation on an image.

Returns a list of tuples of (x,y) coordinates of all matching pixels.

save_lut (*filename*)

Save an operator to an mrl file

set_lut (*lut*)

Set the lut from an external source

3.13 ImageOps Module

The ImageOps module contains a number of ‘ready-made’ image processing operations. This module is somewhat experimental, and most operators only work on L and RGB images.

Only bug fixes have been added since the Pillow fork.

1.1.3 .

PIL. ImageOps. **autocontrast** (*image, cutoff=0, ignore=None*)

Maximize (normalize) image contrast. This function calculates a histogram of the input image, removes **cutoff** percent of the lightest and darkest pixels from the histogram, and remaps the image so that the darkest pixel becomes black (0), and the lightest becomes white (255).

- **image** – The image to process.
- **cutoff** – How many percent to cut off from the histogram.

- **ignore** – The background pixel value (use None for no background).

An image.

PIL. ImageOps.**colorize** (*image, black, white*)

Colorize grayscale image. The **black** and **white** arguments should be RGB tuples; this function calculates a color wedge mapping all black pixels in the source image to the first color, and all white pixels to the second color.

- **image** – The image to colorize.
- **black** – The color to use for black input pixels.
- **white** – The color to use for white input pixels.

An image.

PIL. ImageOps.**crop** (*image, border=0*)

Remove border from image. The same amount of pixels are removed from all four sides. This function works on all image modes.

:

crop()

- **image** – The image to crop.
- **border** – The number of pixels to remove.

An image.

PIL. ImageOps.**deform** (*image, deformer, resample=2*)

Deform the image.

- **image** – The image to deform.
- **deformer** – A deformer object. Any object that implements a **getmesh** method can be used.
- **resample** – What resampling filter to use.

An image.

PIL. ImageOps.**equalize** (*image, mask=None*)

Equalize the image histogram. This function applies a non-linear mapping to the input image, in order to create a uniform distribution of grayscale values in the output image.

- **image** – The image to equalize.
- **mask** – An optional mask. If given, only the pixels selected by the mask are included in the analysis.

An image.

PIL. ImageOps.**expand** (*image, border=0, fill=0*)

Add border to the image

- **image** – The image to expand.
- **border** – Border width, in pixels.
- **fill** – Pixel fill value (a color value). Default is 0 (black).

An image.

`PIL.ImageOps.fit` (*image*, *size*, *method=0*, *bleed=0.0*, *centering=(0.5, 0.5)*)

Returns a sized and cropped version of the image, cropped to the requested aspect ratio and size.

This function was contributed by Kevin Cazabon.

- **size** – The requested output size in pixels, given as a (width, height) tuple.
- **method** – What resampling method to use. Default is `PIL.Image.NEAREST`.
- **bleed** – Remove a border around the outside of the image (from all four edges. The value is a decimal percentage (use 0.01 for one percent). The default value is 0 (no border).
- **centering** – Control the cropping position. Use (0.5, 0.5) for center cropping (e.g. if cropping the width, take 50% off of the left side, and therefore 50% off the right side). (0.0, 0.0) will crop from the top left corner (i.e. if cropping the width, take all of the crop off of the right side, and if cropping the height, take all of it off the bottom). (1.0, 0.0) will crop from the bottom left corner, etc. (i.e. if cropping the width, take all of the crop off the left side, and if cropping the height take none from the top, and therefore all off the bottom).

An image.

`PIL.ImageOps.flip` (*image*)

Flip the image vertically (top to bottom).

image – The image to flip.

An image.

`PIL.ImageOps.grayscale` (*image*)

Convert the image to grayscale.

image – The image to convert.

An image.

`PIL.ImageOps.invert` (*image*)

Invert (negate) the image.

image – The image to invert.

An image.

`PIL.ImageOps.mirror` (*image*)

Flip image horizontally (left to right).

image – The image to mirror.

An image.

`PIL.ImageOps.posterize` (*image*, *bits*)

Reduce the number of bits for each color channel.

- **image** – The image to posterize.
- **bits** – The number of bits to keep for each channel (1-8).

An image.

`PIL.ImageOps.solarize` (*image*, *threshold=128*)
 Invert all pixel values above a threshold.

- **image** – The image to solarize.
- **threshold** – All pixels above this greyscale level are inverted.

An image.

3.14 ImagePalette Module

The `ImagePalette` module contains a class of the same name to represent the color palette of palette mapped images.

: This module was never well-documented. It hasn't changed since 2001, though, so it's probably safe for you to read the source code and puzzle out the internals if you need to.

The `ImagePalette` class has several methods, but they are all marked as “experimental.” Read that as you will. The `[source]` link is there for a reason.

class `PIL.ImagePalette.ImagePalette` (*mode='RGB'*, *palette=None*, *size=0*)
 Color palette for palette mapped images

- **mode** – The mode to use for the Palette. See: [Modes](#). Defaults to “RGB”
- **palette** – An optional palette. If given, it must be a bytearray, an array or a list of ints between 0-255 and of length *size* times the number of colors in *mode*. The list must be aligned by channel (All R values must be contiguous in the list before G and B values.) Defaults to 0 through 255 per channel.
- **size** – An optional palette size. If given, it cannot be equal to or greater than 256. Defaults to 0.

getcolor (*color*)

Given an rgb tuple, allocate palette entry.

: This method is experimental.

getdata ()

Get palette contents in format suitable # for the low-level `im.putpalette` primitive.

: This method is experimental.

save (*fp*)

Save palette to text file.

: This method is experimental.

tobytes ()

Convert palette to bytes.

: This method is experimental.

tostring ()

Convert palette to bytes.

: This method is experimental.

3.15 ImagePath Module

The `ImagePath` module is used to store and manipulate 2-dimensional vector data. Path objects can be passed to the methods on the `ImageDraw` module.

class `PIL.ImagePath.Path`

A path object. The coordinate list can be any sequence object containing either 2-tuples [(x, y), ...] or numeric values [x, y, ...].

You can also create a path object from another path object.

In 1.1.6 and later, you can also pass in any object that implements Python's buffer API. The buffer should provide read access, and contain C floats in machine byte order.

The path object implements most parts of the Python sequence interface, and behaves like a list of (x, y) pairs. You can use `len()`, item access, and slicing as usual. However, the current version does not support slice assignment, or item and slice deletion.

xy – A sequence. The sequence can contain 2-tuples [(x, y), ...] or a flat list of numbers [x, y, ...].

`PIL.ImagePath.Path.compact` (*distance=2*)

Compacts the path, by removing points that are close to each other. This method modifies the path in place, and returns the number of points left in the path.

distance is measured as [Manhattan distance](#) and defaults to two pixels.

`PIL.ImagePath.Path.getbbox` ()

Gets the bounding box of the path.

(x0, y0, x1, y1)

`PIL.ImagePath.Path.map` (*function*)

Maps the path through a function.

`PIL.ImagePath.Path.tolist` (*flat=0*)

Converts the path to a Python list [(x, y), ...].

flat – By default, this function returns a list of 2-tuples [(x, y), ...]. If this argument is *True*, it returns a flat list [x, y, ...] instead.

A list of coordinates. See **flat**.

`PIL.ImagePath.Path.transform` (*matrix*)

Transforms the path in place, using an affine transform. The matrix is a 6-tuple (a, b, c, d, e, f), and each point is mapped as follows:

```
xOut = xIn * a + yIn * b + c
yOut = xIn * d + yIn * e + f
```

3.16 ImageQt Module

The `ImageQt` module contains support for creating PyQt4 or PyQt5 `QImage` objects from PIL images.

1.1.6 .

class `ImageQt . ImageQt` (*image*)

Creates an `ImageQt` object from a PIL `Image` object. This class is a subclass of `QtGui.QImage`, which means that you can pass the resulting objects directly to PyQt4/5 API functions and methods.

This operation is currently supported for mode 1, L, P, RGB, and RGBA images. To handle other modes, you need to convert the image first.

3.17 ImageSequence Module

The `ImageSequence` module contains a wrapper class that lets you iterate over the frames of an image sequence.

3.17.1 Extracting frames from an animation

```
from PIL import Image, ImageSequence

im = Image.open("animation.fli")

index = 1
for frame in ImageSequence.Iterator(im):
    frame.save("frame%d.png" % index)
    index = index + 1
```

3.17.2 The Iterator class

class `PIL . ImageSequence . Iterator` (*im*)

This class implements an iterator object that can be used to loop over an image sequence.

You can use the `[]` operator to access elements by index. This operator will raise an `IndexError` if you try to access a nonexistent frame.

im – An image object.

3.18 ImageStat Module

The `ImageStat` module calculates global statistics for an image, or for a region of an image.

class `PIL . ImageStat . Stat` (*image_or_list*, *mask=None*)

Calculate statistics for the given image. If a mask is included, only the regions covered by that mask are included in the statistics. You can also pass in a previously calculated histogram.

- **image** – A PIL image, or a precalculated histogram.
- **mask** – An optional mask.

extrema

Min/max values for each band in the image.

count

Total number of pixels for each band in the image.

sum

Sum of all pixels for each band in the image.

sum2

Squared sum of all pixels for each band in the image.

mean

Average (arithmetic mean) pixel level for each band in the image.

median

Median pixel level for each band in the image.

rms

RMS (root-mean-square) for each band in the image.

var

Variance for each band in the image.

stddev

Standard deviation for each band in the image.

3.19 ImageTk Module

The `ImageTk` module contains support to create and modify Tkinter `BitmapImage` and `PhotoImage` objects from PIL images.

For examples, see the demo programs in the `Scripts` directory.

class `PIL.ImageTk.BitmapImage` (*image=None, **kw*)

A Tkinter-compatible bitmap image. This can be used everywhere Tkinter expects an image object.

The given image must have mode “1”. Pixels having value 0 are treated as transparent. Options, if any, are passed on to Tkinter. The most commonly used option is **foreground**, which is used to specify the color for the non-transparent parts. See the Tkinter documentation for information on how to specify colours.

image – A PIL image.

height ()

Get the height of the image.

The height, in pixels.

width ()

Get the width of the image.

The width, in pixels.

class `PIL.ImageTk.PhotoImage` (*image=None, size=None, **kw*)

A Tkinter-compatible photo image. This can be used everywhere Tkinter expects an image object. If the image is an RGBA image, pixels having alpha 0 are treated as transparent.

The constructor takes either a PIL image, or a mode and a size. Alternatively, you can use the **file** or **data** options to initialize the photo image object.

- **image** – Either a PIL image, or a mode string. If a mode string is used, a size must also be given.

- **size** – If the first argument is a mode string, this defines the size of the image.
- **file** – A filename to load the image from (using `Image.open(file)`).
- **data** – An 8-bit string containing image data (as loaded from an image file).

height ()

Get the height of the image.

The height, in pixels.

paste (*im*, *box=None*)

Paste a PIL image into the photo image. Note that this can be very slow if the photo image is displayed.

- **im** – A PIL image. The size must match the target region. If the mode does not match, the image is converted to the mode of the bitmap image.
- **box** – A 4-tuple defining the left, upper, right, and lower pixel coordinate. If None is given instead of a tuple, all of the image is assumed.

width ()

Get the width of the image.

The width, in pixels.

3.20 ImageWin Module (Windows-only)

The `ImageWin` module contains support to create and display images on Windows.

`ImageWin` can be used with `PythonWin` and other user interface toolkits that provide access to Windows device contexts or window handles. For example, `Tkinter` makes the window handle available via the `winfo_id` method:

```
from PIL import ImageWin

dib = ImageWin.Dib(...)

hwnd = ImageWin.HWND(widget.winfo_id())
dib.draw(hwnd, xy)
```

class `PIL.ImageWin.Dib` (*image*, *size=None*)

A Windows bitmap with the given mode and size. The mode can be one of “1”, “L”, “P”, or “RGB”.

If the display requires a palette, this constructor creates a suitable palette and associates it with the image. For an “L” image, 128 greylevels are allocated. For an “RGB” image, a 6x6x6 colour cube is used, together with 20 greylevels.

To make sure that palettes work properly under Windows, you must call the **palette** method upon certain events from Windows.

- **image** – Either a PIL image, or a mode string. If a mode string is used, a size must also be given. The mode can be one of “1”, “L”, “P”, or “RGB”.
- **size** – If the first argument is a mode string, this defines the size of the image.

draw (*handle*, *dst*, *src=None*)

Same as `expose`, but allows you to specify where to draw the image, and what part of it to draw.

The destination and source areas are given as 4-tuple rectangles. If the source is omitted, the entire image is copied. If the source and the destination have different sizes, the image is resized as necessary.

expose (*handle*)

Copy the bitmap contents to a device context.

handle – Device context (HDC), cast to a Python integer, or an HDC or HWND instance. In PythonWin, you can use the `CDC.GetHandleAttrib()` to get a suitable handle.

frombytes (*buffer*)

Load display memory contents from byte data.

buffer – A buffer containing display data (usually data returned from `tobytes`)

paste (*im, box=None*)

Paste a PIL image into the bitmap image.

- **im** – A PIL image. The size must match the target region. If the mode does not match, the image is converted to the mode of the bitmap image.
- **box** – A 4-tuple defining the left, upper, right, and lower pixel coordinate. If None is given instead of a tuple, all of the image is assumed.

query_palette (*handle*)

Installs the palette associated with the image in the given device context.

This method should be called upon **QUERYNEWPALETTE** and **PALETTECHANGED** events from Windows. If this method returns a non-zero value, one or more display palette entries were changed, and the image should be redrawn.

handle – Device context (HDC), cast to a Python integer, or an HDC or HWND instance.

A true value if one or more entries were changed (this indicates that the image should be redrawn).

tobytes ()

Copy display memory contents to bytes object.

A bytes object containing display data.

class `PIL.ImageWin.HDC` (*dc*)

Wraps an HDC integer. The resulting object can be passed to the `draw()` and `expose()` methods.

class `PIL.ImageWin.HWND` (*wnd*)

Wraps an HWND integer. The resulting object can be passed to the `draw()` and `expose()` methods, instead of a DC.

3.21 ExifTags Module

The `ExifTags` module exposes two dictionaries which provide constants and clear-text names for various well-known EXIF tags.

class `PIL.ExifTags.TAGS`

The TAG dictionary maps 16-bit integer EXIF tag enumerations to descriptive string names. For instance:

```
>>> from PIL.ExifTags import TAGS
>>> TAGS[0x010e]
'ImageDescription'
```

class `PIL.ExifTags.GPSTAGS`

The GPSTAGS dictionary maps 8-bit integer EXIF gps enumerations to descriptive string names. For instance:

```
>>> from PIL.ExifTags import GPSTAGS
>>> GPSTAGS[20]
'GPSDestLatitude'
```

3.22 TiffTags Module

The `TiffTags` module exposes many of the standard TIFF metadata tag numbers, names, and type information.

`PIL.TiffTags.lookup(tag)`

tag – Integer tag number

Taginfo namedtuple, From the `TAGS_V2` info if possible, otherwise just populating the value and name from `TAGS`. If the tag is not recognized, “unknown” is returned for the name

3.1.0 .

class `PIL.TiffTags.TagInfo`

`__init__(self, value=None, name="unknown", type=None, length=0, enum=None)`

- **value** – Integer Tag Number
- **name** – Tag Name
- **type** – Integer type from `PIL.TiffTags.TYPES`
- **length** – Array length: 0 == variable, 1 == single value, n = fixed
- **enum** – Dict of name:integer value options for an enumeration

`cvt_enum(self, value)`

value – The enumerated value name

The integer corresponding to the name.

3.0.0 .

`PIL.TiffTags.TAGS_V2`

The `TAGS_V2` dictionary maps 16-bit integer tag numbers to `PIL.TagTypes.TagInfo` tuples for metadata fields defined in the TIFF spec.

3.0.0 .

`PIL.TiffTags.TAGS`

The `TAGS` dictionary maps 16-bit integer TIFF tag number to descriptive string names. For instance:

```
>>> from PIL.TiffTags import TAGS
>>> TAGS[0x010e]
'ImageDescription'
```

This dictionary contains a superset of the tags in `TAGS_V2`, common EXIF tags, and other well known metadata tags.

`PIL.TiffTags.TYPES`

The `TYPES` dictionary maps the TIFF type short integer to a human readable type name.

3.23 OleFileIO Module

The `OleFileIO` module reads Microsoft OLE2 files (also called Structured Storage or Microsoft Compound Document File Format), such as Microsoft Office documents, Image Composer and FlashPix files, and Outlook messages.

This module is the `OleFileIO_PL` project by Philippe Lagadec, v0.42, merged back into Pillow.

3.23.1 How to use this module

For more information, see also the file `PIL/OleFileIO.py`, sample code at the end of the module itself, and docstrings within the code.

About the structure of OLE files

An OLE file can be seen as a mini file system or a Zip archive: It contains **streams** of data that look like files embedded within the OLE file. Each stream has a name. For example, the main stream of a MS Word document containing its text is named “WordDocument”.

An OLE file can also contain **storages**. A storage is a folder that contains streams or other storages. For example, a MS Word document with VBA macros has a storage called “Macros”.

Special streams can contain **properties**. A property is a specific value that can be used to store information such as the metadata of a document (title, author, creation date, etc). Property stream names usually start with the character ‘05’.

For example, a typical MS Word document may look like this:

```
\x05DocumentSummaryInformation (stream)
\x05SummaryInformation (stream)
WordDocument (stream)
Macros (storage)
  PROJECT (stream)
  PROJECTWm (stream)
  VBA (storage)
    Module1 (stream)
    ThisDocument (stream)
    _VBA_PROJECT (stream)
    dir (stream)
ObjectPool (storage)
```

Test if a file is an OLE container

Use `isOleFile` to check if the first bytes of the file contain the Magic for OLE files, before opening it. `isOleFile` returns True if it is an OLE file, False otherwise.

```
assert OleFileIO.isOleFile('myfile.doc')
```

Open an OLE file from disk

Create an `OleFileIO` object with the file path as parameter:

```
ole = OleFileIO.OleFileIO('myfile.doc')
```

Open an OLE file from a file-like object

This is useful if the file is not on disk, e.g. already stored in a string or as a file-like object.

```
ole = OleFileIO.OleFileIO(f)
```

For example the code below reads a file into a string, then uses BytesIO to turn it into a file-like object.

```
data = open('myfile.doc', 'rb').read()
f = io.BytesIO(data) # or StringIO.StringIO for Python 2.x
ole = OleFileIO.OleFileIO(f)
```

How to handle malformed OLE files

By default, the parser is configured to be as robust and permissive as possible, allowing to parse most malformed OLE files. Only fatal errors will raise an exception. It is possible to tell the parser to be more strict in order to raise exceptions for files that do not fully conform to the OLE specifications, using the `raise_defect` option:

```
ole = OleFileIO.OleFileIO('myfile.doc', raise_defects=DEFECT_INCORRECT)
```

When the parsing is done, the list of non-fatal issues detected is available as a list in the `parsing_issues` attribute of the `OleFileIO` object:

```
print('Non-fatal issues raised during parsing:')
if ole.parsing_issues:
    for exctype, msg in ole.parsing_issues:
        print('- %s: %s' % (exctype.__name__, msg))
else:
    print('None')
```

Syntax for stream and storage path

Two different syntaxes are allowed for methods that need or return the path of streams and storages:

1. Either a **list of strings** including all the storages from the root up to the stream/storage name. For example a stream called “WordDocument” at the root will have [`WordDocument`] as full path. A stream called “ThisDocument” located in the storage “Macros/VBA” will be [`Macros`, `VBA`, `ThisDocument`]. This is the original syntax from PIL. While hard to read and not very convenient, this syntax works in all cases.
2. Or a **single string with slashes** to separate storage and stream names (similar to the Unix path syntax). The previous examples would be `WordDocument` and `Macros/VBA/ThisDocument`. This syntax is easier, but may fail if a stream or storage name contains a slash.

Both are case-insensitive.

Switching between the two is easy:

```
slash_path = '/'.join(list_path)
list_path = slash_path.split('/')
```

Get the list of streams

`listdir()` returns a list of all the streams contained in the OLE file, including those stored in storages. Each stream is listed itself as a list, as described above.

```
print(ole.listdir())
```

Sample result:

```
[['\x01CompObj'], ['\x05DocumentSummaryInformation'], ['\x05SummaryInformation'], ['1Table'], ['Macros', 'PROJECT'], ['Macros', 'PROJECTwm'], ['Macros', 'VBA', 'Module1'], ['Macros', 'VBA', 'ThisDocument'], ['Macros', 'VBA', '_VBA_PROJECT'], ['Macros', 'VBA', 'dir'], ['ObjectPool'], ['WordDocument']]
```

As an option it is possible to choose if storages should also be listed, with or without streams:

```
ole.listdir(streams=False, storages=True)
```

Test if known streams/storages exist:

`exists(path)` checks if a given stream or storage exists in the OLE file.

```
if ole.exists('worddocument'):
    print("This is a Word document.")
    if ole.exists('macros/vba'):
        print("This document seems to contain VBA macros.")
```

Read data from a stream

`openstream(path)` opens a stream as a file-like object.

The following example extracts the “Pictures” stream from a PPT file:

```
pics = ole.openstream('Pictures')
data = pics.read()
```

Get information about a stream/storage

Several methods can provide the size, type and timestamps of a given stream/storage:

`get_size(path)` returns the size of a stream in bytes:

```
s = ole.get_size('WordDocument')
```

`get_type(path)` returns the type of a stream/storage, as one of the following constants: `STGTY_STREAM` for a stream, `STGTY_STORAGE` for a storage, `STGTY_ROOT` for the root entry, and `False` for a non existing path.

```
t = ole.get_type('WordDocument')
```

`get_ctime(path)` and `get_mtime(path)` return the creation and modification timestamps of a stream/storage, as a Python `datetime` object with UTC timezone. Please note that these timestamps are only present if the application that created the OLE file explicitly stored them, which is rarely the case. When not present, these methods return `None`.

```
c = ole.get_ctime('WordDocument')
m = ole.get_mtime('WordDocument')
```

The root storage is a special case: You can get its creation and modification timestamps using the `OleFileIO.root` attribute:

```
c = ole.root.getctime()
m = ole.root.getmtime()
```

Extract metadata

`get_metadata()` will check if standard property streams exist, parse all the properties they contain, and return an `OleMetadata` object with the found properties as attributes.

```
meta = ole.get_metadata()
print('Author:', meta.author)
print('Title:', meta.title)
print('Creation date:', meta.create_time)
# print all metadata:
meta.dump()
```

Available attributes include:

```
codepage, title, subject, author, keywords, comments, template,
last_saved_by, revision_number, total_edit_time, last_printed, create_time,
last_saved_time, num_pages, num_words, num_chars, thumbnail,
creating_application, security, codepage_doc, category, presentation_target,
bytes, lines, paragraphs, slides, notes, hidden_slides, mm_clips,
scale_crop, heading_pairs, titles_of_parts, manager, company, links_dirty,
chars_with_spaces, unused, shared_doc, link_base, hlinks, hlinks_changed,
version, dig_sig, content_type, content_status, language, doc_version
```

See the source code of the `OleMetadata` class for more information.

Parse a property stream

`get_properties(path)` can be used to parse any property stream that is not handled by `get_metadata`. It returns a dictionary indexed by integers. Each integer is the index of the property, pointing to its value. For example in the standard property stream `'05SummaryInformation'`, the document title is property #2, and the subject is #3.

```
p = ole.getproperties('specialprops')
```

By default as in the original PIL version, timestamp properties are converted into a number of seconds since Jan 1,1601. With the option `convert_time`, you can obtain more convenient Python datetime objects (UTC timezone). If some time properties should not be converted (such as total editing time in `'05SummaryInformation'`), the list of indexes can be passed as `no_conversion`:

```
p = ole.getproperties('specialprops', convert_time=True, no_conversion=[10])
```

Close the OLE file

Unless your application is a simple script that terminates after processing an OLE file, do not forget to close each `OleFileIO` object after parsing to close the file on disk.

```
ole.close()
```

Use OleFileIO as a script

`OleFileIO` can also be used as a script from the command-line to display the structure of an OLE file and its metadata, for example:

```
PIL/OleFileIO.py myfile.doc
```

You can use the option `-c` to check that all streams can be read fully, and `-d` to generate very verbose debugging information.

3.23.2 How to contribute

The code is available in a [Mercurial repository on bitbucket](#). You may use it to submit enhancements or to report any issue.

If you would like to help us improve this module, or simply provide feedback, please [contact me](#). You can help in many ways:

- test this module on different platforms / Python versions
- find and report bugs
- improve documentation, code samples, docstrings
- write unittest test cases
- provide tricky malformed files

3.23.3 How to report bugs

To report a bug, for example a normal file which is not parsed correctly, please use the [issue reporting page](#), or if you prefer to do it privately, use this [contact form](#). Please provide all the information about the context and how to reproduce the bug.

If possible please join the debugging output of OleFileIO. For this, launch the following command :

```
PIL/OleFileIO.py -d -c file >debug.txt
```

3.23.4 Classes and Methods

class PIL.OleFileIO.OleFileIO (*filename=None, raise_defects=40, write_mode=False, debug=False, path_encoding=None*)

object

OLE container object

This class encapsulates the interface to an OLE 2 structured storage file. Use the `listdir()` and `openstream()` methods to access the contents of this file.

Object names are given as a list of strings, one for each subentry level. The root entry should be omitted. For example, the following code extracts all image streams from a Microsoft Image Composer file:

```
ole = OleFileIO("fan.mic")

for entry in ole.listdir():
    if entry[1:2] == "Image":
        fin = ole.openstream(entry)
        fout = open(entry[0:1], "wb")
        while True:
            s = fin.read(8192)
            if not s:
                break
            fout.write(s)
```

You can use the viewer application provided with the Python Imaging Library to view the resulting files (which happens to be standard TIFF files).

close()

close the OLE file, to release the file object

dumpdirectory ()

Dump directory (for debugging only)

dumpfat (*fat*, *firstindex=0*)

Displays a part of FAT in human-readable form for debugging purpose

dumpsect (*sector*, *firstindex=0*)

Displays a sector in a human-readable form, for debugging purpose.

exists (*filename*)

Test if given filename exists as a stream or a storage in the OLE container. Note: filename is case-insensitive.

filename – path of stream in storage tree. (see `openstream` for syntax)

True if object exist, else False.

get_metadata ()

Parse standard properties streams, return an `OleMetadata` object containing all the available metadata. (also stored in the metadata attribute of the `OleFileIO` object)

new in version 0.25

get_rootentry_name ()

Return root entry name. Should usually be 'Root Entry' or 'R' in most implementations.

get_size (*filename*)

Return size of a stream in the OLE container, in bytes.

filename – path of stream in storage tree (see `openstream` for syntax)

size in bytes (long integer)

- **IOError** – if file not found
- **TypeError** – if this is not a stream.

get_type (*filename*)

Test if given filename exists as a stream or a storage in the OLE container, and return its type.

filename – path of stream in storage tree. (see `openstream` for syntax)

False if object does not exist, its entry type (>0) otherwise:

- `STGTY_STREAM`: a stream
- `STGTY_STORAGE`: a storage
- `STGTY_ROOT`: the root entry

getctime (*filename*)

Return creation time of a stream/storage.

filename – path of stream/storage in storage tree. (see `openstream` for syntax)

None if creation time is null, a python datetime object otherwise (UTC timezone)

new in version 0.26

getmtime (*filename*)

Return modification time of a stream/storage.

filename – path of stream/storage in storage tree. (see `openstream` for syntax)

None if modification time is null, a python datetime object otherwise (UTC timezone)

new in version 0.26

getproperties (*filename, convert_time=False, no_conversion=None*)

Return properties described in substream.

- **filename** – path of stream in storage tree (see `openstream` for syntax)
- **convert_time** – bool, if True timestamps will be converted to Python datetime
- **no_conversion** – None or list of int, timestamps not to be converted (for example total editing time is not a real timestamp)

a dictionary of values indexed by id (integer)

getsect (*sect*)

Read given sector from file on disk.

sect – int, sector index

a string containing the sector data.

listdir (*streams=True, storages=False*)

Return a list of streams and/or storages stored in this file

- **streams** – bool, include streams if True (True by default) - new in v0.26
- **storages** – bool, include storages if True (False by default) - new in v0.26 (note: the root storage is never included)

list of stream and/or storage paths

loaddirectory (*sect*)

Load the directory.

sect – sector index of directory stream.

loadfat (*header*)

Load the FAT table.

loadfat_sect (*sect*)

Adds the indexes of the given sector to the FAT

sect – string containing the first FAT sector, or array of long integers

index of last FAT sector.

loadminifat ()

Load the MiniFAT table.

open (*filename, write_mode=False*)

Open an OLE2 file in read-only or read/write mode. Read and parse the header, FAT and directory.

- **filename** – string-like or file-like object, OLE file to parse
 - if filename is a string smaller than 1536 bytes, it is the path of the file to open. (bytes or unicode string)
 - if filename is a string longer than 1535 bytes, it is parsed as the content of an OLE file in memory. (bytes type only)

– if filename is a file-like object (with read, seek and tell methods), it is parsed as-is.

- **write_mode** – bool, if True the file is opened in read/write mode instead of read-only by default. (ignored if filename is not a path)

openstream (*filename*)

Open a stream as a read-only file object (BytesIO). Note: filename is case-insensitive.

filename – path of stream in storage tree (except root entry), either:

- a string using Unix path syntax, for example: ‘storage_1/storage_1.2/stream’
- or a list of storage filenames, path to the desired stream/storage. Example: [‘storage_1’, ‘storage_1.2’, ‘stream’]

file object (read-only)

IOError – if filename not found, or if this is not a stream.

raise_defect (*defect_level, message, exception_type=<class ‘OSError’>*)

This method should be called for any defect found during file parsing. It may raise an IOError exception according to the minimal level chosen for the OleFileIO object.

- **defect_level** – defect level, possible values are:
 - DEFECT_UNSURE : a case which looks weird, but not sure it’s a defect
 - DEFECT_POTENTIAL : a potential defect
 - DEFECT_INCORRECT : an error according to specifications, but parsing can go on
 - DEFECT_FATAL : an error which cannot be ignored, parsing is impossible
- **message** – string describing the defect, used with raised exception.
- **exception_type** – exception class to be raised, IOError by default

sect2array (*sect*)

convert a sector to an array of 32 bits unsigned integers, swapping bytes on big endian CPUs such as PowerPC (old Macs)

write_sect (*sect, data, padding=b‘\x00’*)

Write given sector to file on disk.

- **sect** – int, sector index
- **data** – bytes, sector data
- **padding** – single byte, padding character if data < sector size

write_stream (*stream_name, data*)

Write a stream to disk. For now, it is only possible to replace an existing stream by data of the same size.

- **stream_name** – path of stream in storage tree (except root entry), either:
 - a string using Unix path syntax, for example: ‘storage_1/storage_1.2/stream’
 - or a list of storage filenames, path to the desired stream/storage. Example: [‘storage_1’, ‘storage_1.2’, ‘stream’]
- **data** – bytes, data to be written, must be the same size as the original stream.

class `PIL.OleFileIO.OleMetadata`

object

class to parse and store metadata from standard properties of OLE files.

Available attributes: `codepage`, `title`, `subject`, `author`, `keywords`, `comments`, `template`, `last_saved_by`, `revision_number`, `total_edit_time`, `last_printed`, `create_time`, `last_saved_time`, `num_pages`, `num_words`, `num_chars`, `thumbnail`, `creating_application`, `security`, `codepage_doc`, `category`, `presentation_target`, `bytes`, `lines`, `paragraphs`, `slides`, `notes`, `hidden_slides`, `mm_clips`, `scale_crop`, `heading_pairs`, `titles_of_parts`, `manager`, `company`, `links_dirty`, `chars_with_spaces`, `unused`, `shared_doc`, `link_base`, `hlinks`, `hlinks_changed`, `version`, `dig_sig`, `content_type`, `content_status`, `language`, `doc_version`

Note: an attribute is set to `None` when not present in the properties of the OLE file.

References for `SummaryInformation` stream: - <https://msdn.microsoft.com/en-us/library/dd942545.aspx> - <https://msdn.microsoft.com/en-us/library/dd925819%28v=office.12%29.aspx> - <https://msdn.microsoft.com/en-us/library/windows/desktop/aa380376%28v=vs.85%29.aspx> - <https://msdn.microsoft.com/en-us/library/aa372045.aspx> - <http://sedna-soft.de/articles/summary-information-stream/> - <http://poi.apache.org/apidocs/org/apache/poi/hpsf/SummaryInformation.html>

References for `DocumentSummaryInformation` stream: - <https://msdn.microsoft.com/en-us/library/dd945671%28v=office.12%29.aspx> - <https://msdn.microsoft.com/en-us/library/windows/desktop/aa380374%28v=vs.85%29.aspx> - <http://poi.apache.org/apidocs/org/apache/poi/hpsf/DocumentSummaryInformation.html>

new in version 0.25

DOCSUM_ATTRIBS = ['codepage_doc', 'category', 'presentation_target', 'bytes', 'lines', 'paragraphs', 'slides', 'notes', 'h

SUMMARY_ATTRIBS = ['codepage', 'title', 'subject', 'author', 'keywords', 'comments', 'template', 'last_saved_by', 'revis

dump ()

Dump all metadata, for debugging purposes.

parse_properties (*olefile*)

Parse standard properties of an OLE file, from the streams “`SummaryInformation`” and “`DocumentSummaryInformation`”, if present. Properties are converted to strings, integers or python datetime objects. If a property is not present, its value is set to `None`.

`PIL.OleFileIO.debug` (*msg*)

`PIL.OleFileIO.debug_pass` (*msg*)

`PIL.OleFileIO.debug_print` (*msg*)

`PIL.OleFileIO.filetime2datetime` (*filetime*)

convert FILETIME (64 bits int) to Python datetime.datetime

`PIL.OleFileIO.i16` (*c*, *o=0*)

Converts a 2-bytes (16 bits) string to an integer.

c: string containing bytes to convert *o*: offset of bytes to convert in string

`PIL.OleFileIO.i32` (*c*, *o=0*)

Converts a 4-bytes (32 bits) string to an integer.

c: string containing bytes to convert *o*: offset of bytes to convert in string

`PIL.OleFileIO.i8` (*c*)

`PIL.OleFileIO.isOleFile` (*filename*)

Test if a file is an OLE container (according to the magic bytes in its header).

filename – string-like or file-like object, OLE file to parse

- if filename is a string smaller than 1536 bytes, it is the path of the file to open. (bytes or unicode string)
- if filename is a string longer than 1535 bytes, it is parsed as the content of an OLE file in memory. (bytes type only)
- if filename is a file-like object (with read and seek methods), it is parsed as-is.

True if OLE, False otherwise.

`PIL.OleFileIO.set_debug_mode(debug_mode)`

Set debug mode on or off, to control display of debugging messages. :param mode: True or False

3.24 PSDraw Module

The `PSDraw` module provides simple print support for Postscript printers. You can print text, graphics and images through this module.

class `PIL.PSDraw.PSDraw` (*fp=None*)

Sets up printing to the given file. If **file** is omitted, `sys.stdout` is assumed.

begin_document (*id=None*)

Set up printing of a document. (Write Postscript DSC header.)

end_document ()

Ends printing. (Write Postscript DSC footer.)

image (*box, im, dpi=None*)

Draw a PIL image, centered in the given box.

line (*xy0, xy1*)

Draws a line between the two points. Coordinates are given in Postscript point coordinates (72 points per inch, (0, 0) is the lower left corner of the page).

rectangle (*box*)

Draws a rectangle.

box – A 4-tuple of integers whose order and function is currently undocumented.

Hint: the tuple is passed into this format string:

```
%d %d M %d %d 0 Vr
```

set_font (*font, size*)

Selects which font to use.

- **font** – A Postscript font name
- **size** – Size in points.

text (*xy, text*)

Draws text at the given position. You must use `set_font()` before calling this method.

3.25 PixelAccess Class

The `PixelAccess` class provides read and write access to `PIL.Image` data at a pixel level.

: Accessing individual pixels is fairly slow. If you are looping over all of the pixels in an image, there is likely a faster way using other parts of the Pillow API.

3.25.1 Example

The following script loads an image, accesses one pixel from it, then changes it.

```
from PIL import Image
im = Image.open('hopper.jpg')
px = im.load()
print (px[4,4])
px[4,4] = (0,0,0)
print (px[4,4])
```

Results in the following:

```
(23, 24, 68)
(0, 0, 0)
```

3.25.2 PixelAccess Class

class PixelAccess

`__setitem__(self, xy, color):`

Modifies the pixel at x,y. The color is given as a single numerical value for single band images, and a tuple for multi-band images

- **xy** – The pixel coordinate, given as (x, y).
- **value** – The pixel value.

`__getitem__(self, xy):`

Returns the pixel at x,y. The pixel is returned as a single value for single band images or a tuple for multiple band images

param xy The pixel coordinate, given as (x, y).

returns a pixel value for single band images, a tuple of pixel values for multiband images.

`putpixel(self, xy, color):`

Modifies the pixel at x,y. The color is given as a single numerical value for single band images, and a tuple for multi-band images

- **xy** – The pixel coordinate, given as (x, y).
- **value** – The pixel value.

`getpixel(self, xy):`

Returns the pixel at x,y. The pixel is returned as a single value for single band images or a tuple for multiple band images

param xy The pixel coordinate, given as (x, y).

returns a pixel value for single band images, a tuple of pixel values for multiband images.

3.26 PyAccess Module

The `PyAccess` module provides a CFFI/Python implementation of the `PixelAccess Class`. This implementation is far faster on PyPy than the `PixelAccess` version.

: Accessing individual pixels is fairly slow. If you are looping over all of the pixels in an image, there is likely a faster way using other parts of the Pillow API.

3.26.1 Example

The following script loads an image, accesses one pixel from it, then changes it.

```
from PIL import Image
im = Image.open('hopper.jpg')
px = im.load()
print(px[4,4])
px[4,4] = (0,0,0)
print(px[4,4])
```

Results in the following:

```
(23, 24, 68)
(0, 0, 0)
```

3.26.2 PyAccess Class

3.27 PIL Package (autodoc of remaining modules)

Reference for modules whose documentation has not yet been ported or written can be found here.

3.27.1 BdfFontFile Module

```
class PIL.BdfFontFile.BdfFontFile(fp)
```

```
    PIL.FontFile.FontFile
```

```
PIL.BdfFontFile.bdf_char(f)
```

3.27.2 ContainerIO Module

```
class PIL.ContainerIO.ContainerIO(file, offset, length)
```

```
    object
```

```
    isatty()
```

```
    read(n=0)
```

```
    readline()
```

```
readlines ()  
seek (offset, mode=0)  
tell ()
```

3.27.3 FontFile Module

```
class PIL.FontFile.FontFile  
    object  
  
    bitmap = None  
  
    compile ()  
        Create metrics and bitmap  
  
    save (filename)  
        Save font  
  
PIL.FontFile.putil16 (fp, values)
```

3.27.4 GdImageFile Module

```
class PIL.GdImageFile.GdImageFile (fp=None, filename=None)  
    PIL.ImageFile.ImageFile  
  
    format = 'GD'  
  
    format_description = 'GD uncompressed images'  
  
PIL.GdImageFile.open (fp, mode='r')
```

3.27.5 GimpGradientFile Module

```
class PIL.GimpGradientFile.GimpGradientFile (fp)  
    PIL.GimpGradientFile.GradientFile  
  
class PIL.GimpGradientFile.GradientFile  
    object  
  
    getpalette (entries=256)  
  
    gradient = None  
  
PIL.GimpGradientFile.curved (middle, pos)  
PIL.GimpGradientFile.linear (middle, pos)  
PIL.GimpGradientFile.sine (middle, pos)  
PIL.GimpGradientFile.sphere_decreasing (middle, pos)  
PIL.GimpGradientFile.sphere_increasing (middle, pos)
```

3.27.6 GimpPaletteFile Module

```
class PIL.GimpPaletteFile.GimpPaletteFile (fp)  
    object
```

```

getpalette ()
rawmode = 'RGB'

```

3.27.7 ImageDraw2 Module

```

class PIL. ImageDraw2. Brush (color, opacity=255)
    object

class PIL. ImageDraw2. Draw (image, size=None, color=None)
    object

    arc (xy, start, end, *options)
    chord (xy, start, end, *options)
    ellipse (xy, *options)
    flush ()
    line (xy, *options)
    pieslice (xy, start, end, *options)
    polygon (xy, *options)
    rectangle (xy, *options)
    render (op, xy, pen, brush=None)
    settransform (offset)
    symbol (xy, symbol, *options)
    text (xy, text, font)
    textsize (text, font)

class PIL. ImageDraw2. Font (color, file, size=12)
    object

class PIL. ImageDraw2. Pen (color, width=1, opacity=255)
    object

```

3.27.8 ImageShow Module

```

class PIL. ImageShow. DisplayViewer
    PIL. ImageShow. UnixViewer

    get_command_ex (file, **options)

class PIL. ImageShow. UnixViewer
    PIL. ImageShow. Viewer

    show_file (file, **options)

class PIL. ImageShow. Viewer
    object

    format = None

    get_command (file, **options)

    get_format (image)

```

```
save_image (image)  
show (image, **options)  
show_file (file, **options)  
show_image (image, **options)
```

```
class PIL. ImageShow. XVViewer  
    PIL. ImageShow. UnixViewer  
  
    get_command_ex (file, title=None, **options)  
  
PIL. ImageShow. register (viewer, order=1)  
PIL. ImageShow. show (image, title=None, **options)  
PIL. ImageShow. which (executable)
```

3.27.9 ImageTransform Module

```
class PIL. ImageTransform. AffineTransform (data)  
    PIL. ImageTransform. Transform  
  
    method = 0  
  
class PIL. ImageTransform. ExtentTransform (data)  
    PIL. ImageTransform. Transform  
  
    method = 1  
  
class PIL. ImageTransform. MeshTransform (data)  
    PIL. ImageTransform. Transform  
  
    method = 4  
  
class PIL. ImageTransform. QuadTransform (data)  
    PIL. ImageTransform. Transform  
  
    method = 3  
  
class PIL. ImageTransform. Transform (data)  
    PIL. Image. ImageTransformHandler  
  
    getdata ()  
  
    ttransform (size, image, **options)
```

3.27.10 JpegPresets Module

JPEG quality settings equivalent to the Photoshop settings.

More presets can be added to the presets dict if needed.

Can be use when saving JPEG file.

To apply the preset, specify:

```
quality="preset_name"
```

To apply only the quantization table:

```
qtables="preset_name"
```

To apply only the subsampling setting:

```
subsampling="preset_name"
```

Example:

```
im.save("image_name.jpg", quality="web_high")
```

Subsampling

Subsampling is the practice of encoding images by implementing less resolution for chroma information than for luma information. (ref.: https://en.wikipedia.org/wiki/Chroma_subsampling)

Possible subsampling values are 0, 1 and 2 that correspond to 4:4:4, 4:2:2 and 4:1:1 (or 4:2:0?).

You can get the subsampling of a JPEG with the *JpegImagePlugin.get_subsampling(im)* function.

Quantization tables

They are values use by the DCT (Discrete cosine transform) to remove *unnecessary* information from the image (the lossy part of the compression). (ref.: https://en.wikipedia.org/wiki/Quantization_matrix#Quantization_matrices, <https://en.wikipedia.org/wiki/JPEG#Quantization>)

You can get the quantization tables of a JPEG with:

```
im.quantization
```

This will return a dict with a number of arrays. You can pass this dict directly as the *qtables* argument when saving a JPEG.

The tables format between *im.quantization* and *quantization* in presets differ in 3 ways:

1. The base container of the preset is a list with sublists instead of dict. *dict[0] -> list[0]*, *dict[1] -> list[1]*, ...
2. Each table in a preset is a list instead of an array.
3. The zigzag order is remove in the preset (needed by *libjpeg >= 6a*).

You can convert the dict format to the preset format with the *JpegImagePlugin.convert_dict_qtables(dict_qtables)* function.

Libjpeg ref.: <http://web.archive.org/web/20120328125543/http://www.jpegcameras.com/libjpeg/libjpeg-3.html>

3.27.11 PaletteFile Module

```
class PIL.PaletteFile.PaletteFile(fp)
    object

    getpalette()

    rawmode = 'RGB'
```

3.27.12 PcfFontFile Module

```
class PIL.PcfFontFile.PcfFontFile(fp)
    PIL.FontFile.FontFile
```

```
    name = 'name'
```

```
PIL.PcfFontFile.sz(s, o)
```

3.27.13 PngImagePlugin.iTXXt Class

```
class PIL.PngImagePlugin.iTXXt
    str
```

Subclass of string to allow iTXt chunks to look like strings while keeping their extra information

```
__new__(cls, text, lang, tkey)
```

- **value** – value for this key
- **lang** – language code
- **tkey** – UTF-8 version of the key name

3.27.14 PngImagePlugin.PngInfo Class

```
class PIL.PngImagePlugin.PngInfo
    object
```

PNG chunk container (for use with save(pnginfo=))

```
add(cid, data)
```

Appends an arbitrary chunk. Use with caution.

- **cid** – a byte string, 4 bytes long.
- **data** – a byte string of the encoded data

```
add_itxt(key, value, lang='', tkey='', zip=False)
```

Appends an iTXt chunk.

- **key** – latin-1 encodable text key name
- **value** – value for this key
- **lang** – language code
- **tkey** – UTF-8 version of the key name
- **zip** – compression flag

```
add_text(key, value, zip=0)
```

Appends a text chunk.

- **key** – latin-1 encodable text key name

- **value** – value for this key, text or an `PIL.PngImagePlugin.iTXt` instance
- **zip** – compression flag

3.27.15 TarIO Module

```
class PIL.TarIO.TarIO(tarfile, file)
    PIL.ContainerIO.ContainerIO
```

3.27.16 WalImageFile Module

```
PIL.WalImageFile.open(filename)
```

3.27.17 _binary Module

```
PIL._binary.i16be(c, o=0)
```

```
PIL._binary.i16le(c, o=0)
    Converts a 2-bytes (16 bits) string to an integer.
```

c: string containing bytes to convert *o*: offset of bytes to convert in string

```
PIL._binary.i32be(c, o=0)
```

```
PIL._binary.i32le(c, o=0)
    Converts a 4-bytes (32 bits) string to an integer.
```

c: string containing bytes to convert *o*: offset of bytes to convert in string

```
PIL._binary.i8(c)
```

```
PIL._binary.o16be(i)
```

```
PIL._binary.o16le(i)
```

```
PIL._binary.o32be(i)
```

```
PIL._binary.o32le(i)
```

```
PIL._binary.o8(i)
```

3.28 Plugin reference

3.28.1 BmpImagePlugin Module

```
class PIL.BmpImagePlugin.BmpImageFile(fp=None, filename=None)
    PIL.ImageFile.ImageFile
```

Image plugin for the Windows Bitmap format (BMP)

```
BITFIELDS = 3
```

```
COMPRESSIONS = {'RAW': 0, 'JPEG': 4, 'BITFIELDS': 3, 'RLE4': 2, 'RLE8': 1, 'PNG': 5}
```

```
JPEG = 4
```

```
PNG = 5
```

```
RAW = 0  
RLE4 = 2  
RLE8 = 1  
format = 'BMP'  
format_description = 'Windows Bitmap'
```

```
class PIL.BmpImagePlugin.DibImageFile (fp=None, filename=None)  
    PIL.BmpImagePlugin.BmpImageFile  
format = 'DIB'  
format_description = 'Windows Bitmap'
```

3.28.2 BufrStubImagePlugin Module

```
class PIL.BufrStubImagePlugin.BufrStubImageFile (fp=None, filename=None)  
    PIL.ImageFile.StubImageFile  
format = 'BUFR'  
format_description = 'BUFR'
```

```
PIL.BufrStubImagePlugin.register_handler (handler)
```

3.28.3 CurImagePlugin Module

```
class PIL.CurImagePlugin.CurImageFile (fp=None, filename=None)  
    PIL.BmpImagePlugin.BmpImageFile  
format = 'CUR'  
format_description = 'Windows Cursor'
```

3.28.4 DcxImagePlugin Module

```
class PIL.DcxImagePlugin.DcxImageFile (fp=None, filename=None)  
    PIL.PcxImagePlugin.PcxImageFile  
format = 'DCX'  
format_description = 'Intel DCX'  
is_animated  
n_frames  
seek (frame)  
tell ()
```

3.28.5 EpsImagePlugin Module

```
class PIL.EpsImagePlugin.EpsImageFile (fp=None, filename=None)  
    PIL.ImageFile.ImageFile  
    EPS File Parser for the Python Imaging Library
```

```

format = 'EPS'
format_description = 'Encapsulated Postscript'
load (scale=1)
load_seek (*args, **kwargs)
mode_map = {1: 'L', 2: 'LAB', 3: 'RGB'}

```

`PIL.EpsImagePlugin.Ghostscript` (*tile, size, fp, scale=1*)
Render an image using Ghostscript

```

class PIL.EpsImagePlugin.PSFile (fp)
    object

    Wrapper for bytesio object that treats either CR or LF as end of line.

    readline ()

    seek (offset, whence=0)

```

`PIL.EpsImagePlugin.has_ghostscript` ()

3.28.6 FitsStubImagePlugin Module

```

class PIL.FitsStubImagePlugin.FITSStubImageFile (fp=None, filename=None)
    PIL.ImageFile.StubImageFile

```

```

format = 'FITS'
format_description = 'FITS'

```

`PIL.FitsStubImagePlugin.register_handler` (*handler*)

3.28.7 FliImagePlugin Module

```

class PIL.FliImagePlugin.FliImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

```

```

format = 'FLI'
format_description = 'Autodesk FLI/FLC Animation'
is_animated
n_frames
seek (frame)
tell ()

```

3.28.8 FpxImagePlugin Module

```

class PIL.FpxImagePlugin.FpxImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

```

```

format = 'FPX'
format_description = 'FlashPix'
load ()

```

3.28.9 GbrImagePlugin Module

```
class PIL.GbrImagePlugin.GbrImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'GBR'

    format_description = 'GIMP brush file'

    load()
```

3.28.10 GifImagePlugin Module

```
class PIL.GifImagePlugin.GifImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    data ()

    format = 'GIF'

    format_description = 'Compuserve GIF'

    global_palette = None

    is_animated

    load_end ()

    n_frames

    seek (frame)

    tell ()

PIL.GifImagePlugin.get_interlace (im)

PIL.GifImagePlugin.getdata (im, offset=(0, 0), **params)
    Return a list of strings representing this image. The first string is a local image header, the rest contains encoded image data.

PIL.GifImagePlugin.getheader (im, palette=None, info=None)
    Return a list of strings representing a GIF header
```

3.28.11 GribStubImagePlugin Module

```
class PIL.GribStubImagePlugin.GribStubImageFile (fp=None, filename=None)
    PIL.ImageFile.StubImageFile

    format = 'GRIB'

    format_description = 'GRIB'

PIL.GribStubImagePlugin.register_handler (handler)
```

3.28.12 Hdf5StubImagePlugin Module

```
class PIL.Hdf5StubImagePlugin.HDF5StubImageFile (fp=None, filename=None)
    PIL.ImageFile.StubImageFile

    format = 'HDF5'
```

```
format_description = 'HDF5'
```

```
PIL.Hdf5StubImagePlugin.register_handler (handler)
```

3.28.13 IcmsImagePlugin Module

```
class PIL.IcmsImagePlugin.IcmsFile (fobj)
    object
```

```
SIZES = {(32, 32, 2): [(b'ic12', <function read_png_or_jpeg2000 at 0x7f7dfa98b048>)], (256, 256, 1): [(b'ic08', <function
```

```
bestsize ()
```

```
dataforsize (size)
```

Get an icon resource as {channel: array}. Note that the arrays are bottom-up like windows bitmaps and will likely need to be flipped or transposed in some way.

```
getimage (size=None)
```

```
itersizes ()
```

```
class PIL.IcmsImagePlugin.IcmsImageFile (fp=None, filename=None)
```

```
PIL.ImageFile.ImageFile
```

PIL image support for Mac OS .icns files. Chooses the best resolution, but will possibly load a different size image if you mutate the size attribute before calling 'load'.

The info dictionary has a key 'sizes' that is a list of sizes that the icns file has.

```
format = 'ICNS'
```

```
format_description = 'Mac OS icns resource'
```

```
load ()
```

```
PIL.IcmsImagePlugin.nextheader (fobj)
```

```
PIL.IcmsImagePlugin.read_32 (fobj, start_length, size)
```

Read a 32bit RGB icon resource. Seems to be either uncompressed or an RLE packbits-like scheme.

```
PIL.IcmsImagePlugin.read_32t (fobj, start_length, size)
```

```
PIL.IcmsImagePlugin.read_mk (fobj, start_length, size)
```

```
PIL.IcmsImagePlugin.read_png_or_jpeg2000 (fobj, start_length, size)
```

3.28.14 IcoImagePlugin Module

```
class PIL.IcoImagePlugin.IcoFile (buf)
    object
```

```
frame (idx)
```

Get an image from frame idx

```
getimage (size, bpp=False)
```

Get an image from the icon

```
sizes ()
```

Get a list of all available icon sizes and color depths.

```
class PIL.IcoImagePlugin.IcoImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile
```

PIL read-only image support for Microsoft Windows .ico files.

By default the largest resolution image in the file will be loaded. This can be changed by altering the 'size' attribute before calling 'load'.

The info dictionary has a key 'sizes' that is a list of the sizes available in the icon file.

Handles classic, XP and Vista icon formats.

This plugin is a refactored version of Win32IconImagePlugin by Bryan Davis <casadebender@gmail.com>. <https://code.google.com/archive/p/casadebender/wikis/Win32IconImagePlugin.wiki>

```
format = 'ICO'
```

```
format_description = 'Windows Icon'
```

```
load ()
```

```
load_seek ()
```

3.28.15 ImImagePlugin Module

```
class PIL.ImImagePlugin.ImImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile
```

```
format = 'IM'
```

```
format_description = 'IFUNC Image Memory'
```

```
is_animated
```

```
n_frames
```

```
seek (frame)
```

```
tell ()
```

```
PIL.ImImagePlugin.number (s)
```

3.28.16 ImtImagePlugin Module

```
class PIL.ImtImagePlugin.ImtImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile
```

```
format = 'IMT'
```

```
format_description = 'IM Tools'
```

3.28.17 IptcImagePlugin Module

```
class PIL.IptcImagePlugin.IptcImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile
```

```
field ()
```

```
format = 'IPTC'
```

```
format_description = 'IPTC/NAA'
```

getint (*key*)**load** ()PIL.IptcImagePlugin.**dump** (*c*)PIL.IptcImagePlugin.**getiptcinfo** (*im*)PIL.IptcImagePlugin.**i** (*c*)

3.28.18 JpegImagePlugin Module

PIL.JpegImagePlugin.**APP** (*self, marker*)PIL.JpegImagePlugin.**COM** (*self, marker*)PIL.JpegImagePlugin.**DQT** (*self, marker*)**class** PIL.JpegImagePlugin.**JpegImageFile** (*fp=None, filename=None*)
PIL.ImageFile.ImageFile**draft** (*mode, size*)**format** = 'JPEG'**format_description** = 'JPEG (ISO 10918)'**load_djpeg** ()PIL.JpegImagePlugin.**SOF** (*self, marker*)PIL.JpegImagePlugin.**Skip** (*self, marker*)PIL.JpegImagePlugin.**convert_dict_qtables** (*qtables*)PIL.JpegImagePlugin.**get_sampling** (*im*)PIL.JpegImagePlugin.**jpeg_factory** (*fp=None, filename=None*)

3.28.19 Jpeg2KImagePlugin Module

class PIL.Jpeg2KImagePlugin.**Jpeg2KImageFile** (*fp=None, filename=None*)
PIL.ImageFile.ImageFile**format** = 'JPEG2000'**format_description** = 'JPEG 2000 (ISO 15444)'**load** ()

3.28.20 McIDASImagePlugin Module

class PIL.McIDASImagePlugin.**McIDASImageFile** (*fp=None, filename=None*)
PIL.ImageFile.ImageFile**format** = 'MCIDAS'**format_description** = 'McIDAS area file'

3.28.21 MicImagePlugin Module

```
class PIL.MicImagePlugin.MicImageFile (fp=None, filename=None)
    PIL.TiffImagePlugin.TiffImageFile

    format = 'MIC'
    format_description = 'Microsoft Image Composer'
    is_animated
    n_frames
    seek (frame)
    tell ()
```

3.28.22 MpegImagePlugin Module

```
class PIL.MpegImagePlugin.BitStream (fp)
    object

    next ()
    peek (bits)
    read (bits)
    skip (bits)

class PIL.MpegImagePlugin.MpegImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'MPEG'
    format_description = 'MPEG'
```

3.28.23 MspImagePlugin Module

```
class PIL.MspImagePlugin.MspImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'MSP'
    format_description = 'Windows Paint'
```

3.28.24 PalmImagePlugin Module

```
PIL.PalmImagePlugin.build_prototype_image ()
```

3.28.25 PcdImagePlugin Module

```
class PIL.PcdImagePlugin.PcdImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'PCD'
    format_description = 'Kodak PhotoCD'
```

3.28.26 PcxImagePlugin Module

```
class PIL.PcxImagePlugin.PcxImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'PCX'
    format_description = 'Paintbrush'
```

3.28.27 PdfImagePlugin Module

3.28.28 PixarImagePlugin Module

```
class PIL.PixarImagePlugin.PixarImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'PIXAR'
    format_description = 'PIXAR raster image'
```

3.28.29 PngImagePlugin Module

```
PIL.PngImagePlugin.getchunks (im, **params)
    Return a list of PNG chunks representing this image.

PIL.PngImagePlugin.is_cid ()
    match(string[, pos[, endpos]]) -> match object or None. Matches zero or more characters at the beginning of the string

PIL.PngImagePlugin.putchunk (fp, cid, *data)
    Write a PNG chunk (including CRC field)

class PIL.PngImagePlugin.ChunkStream (fp)
    object

    call (cid, pos, length)
        Call the appropriate chunk handler

    close ()

    crc (cid, data)
        Read and verify checksum

    crc_skip (cid, data)
        Read checksum. Used if the C module is not present

    push (cid, pos, length)

    read ()
        Fetch a new chunk. Returns header information.

    verify (endchunk=b'IEND')
```

```
class PIL.PngImagePlugin.PngImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'PNG'
    format_description = 'Portable network graphics'
```

load_end()
internal: finished reading image data

load_prepare()
internal: prepare to read PNG file

load_read(*read_bytes*)
internal: read more image data

verify()
Verify PNG file

class PIL.PngImagePlugin.**PngStream**(*fp*)
PIL.PngImagePlugin.ChunkStream

check_text_memory(*chunklen*)

chunk_IDAT(*pos, length*)

chunk_IEND(*pos, length*)

chunk_IHDR(*pos, length*)

chunk_PLTE(*pos, length*)

chunk_gAMA(*pos, length*)

chunk_iCCP(*pos, length*)

chunk_iTXt(*pos, length*)

chunk_pHYs(*pos, length*)

chunk_tEXt(*pos, length*)

chunk_tRNS(*pos, length*)

chunk_zTXt(*pos, length*)

3.28.30 PpmImagePlugin Module

class PIL.PpmImagePlugin.**PpmImageFile**(*fp=None, filename=None*)
PIL.ImageFile.ImageFile

format = 'PPM'

format_description = 'Pbmplus image'

3.28.31 PsdImagePlugin Module

class PIL.PsdImagePlugin.**PsdImageFile**(*fp=None, filename=None*)
PIL.ImageFile.ImageFile

format = 'PSD'

format_description = 'Adobe Photoshop'

is_animated

load_prepare()

n_frames

seek(*layer*)

```
tell()
```

3.28.32 SgiImagePlugin Module

```
class PIL.SgiImagePlugin.SgiImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'SGI'
    format_description = 'SGI Image File Format'
```

3.28.33 SpiderImagePlugin Module

```
class PIL.SpiderImagePlugin.SpiderImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    convert2byte (depth=255)
    format = 'SPIDER'
    format_description = 'Spider 2D image'
    is_animated
    n_frames
    seek (frame)
    tell ()
    tkPhotoImage ()

PIL.SpiderImagePlugin.isInt (f)
PIL.SpiderImagePlugin.isSpiderHeader (t)
PIL.SpiderImagePlugin.isSpiderImage (filename)
PIL.SpiderImagePlugin.loadImageSeries (filelist=None)
    create a list of Image.images for use in montage
PIL.SpiderImagePlugin.makeSpiderHeader (im)
```

3.28.34 SunImagePlugin Module

```
class PIL.SunImagePlugin.SunImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'SUN'
    format_description = 'Sun Raster File'
```

3.28.35 TgaImagePlugin Module

```
class PIL.TgaImagePlugin.TgaImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'TGA'
    format_description = 'Targa'
```

3.28.36 TiffImagePlugin Module

class `PIL.TiffImagePlugin.IFDRational` (*value*, *denominator=1*)
`numbers.Rational`

Implements a rational class where 0/0 is a legal value to match the in the wild use of exif rationals.

e.g., DigitalZoomRatio - 0.00/0.00 indicates that no digital zoom was used

denominator

limit_rational (*max_denominator*)

max_denominator – Integer, the maximum denominator value

Tuple of (numerator, denominator)

numerator

`PIL.TiffImagePlugin.ImageFileDirectory`
`ImageFileDirectory_v1`

class `PIL.TiffImagePlugin.ImageFileDirectory_v1` (**args*, ***kwargs*)
`PIL.TiffImagePlugin.ImageFileDirectory_v2`

This class represents the **legacy** interface to a TIFF tag directory.

Exposes a dictionary interface of the tags in the directory:

```
ifd = ImageFileDirectory_v1()
ifd[key] = 'Some Data'
ifd.tagtype[key] = 2
print ifd[key]
('Some Data',)
```

Also contains a dictionary of tag types as read from the tiff image file,
~`PIL.TiffImagePlugin.ImageFileDirectory_v1.tagtype`.

Values are returned as a tuple.

3.0.0 .

classmethod `from_v2` (*original*)

Returns an `ImageFileDirectory_v1` instance with the same data as is contained in the original
`ImageFileDirectory_v2` instance.

`ImageFileDirectory_v1`

tagdata

tags

to_v2 ()

Returns an `ImageFileDirectory_v2` instance with the same data as is contained in the original
`ImageFileDirectory_v1` instance.

`ImageFileDirectory_v2`

class `PIL.TiffImagePlugin.ImageFileDirectory_v2` (*ifh=b'II*x00x00x00x00x00'*, *pre-*
fix=None)

`collections.abc.MutableMapping`

This class represents a TIFF tag directory. To speed things up, we don't decode tags unless they're asked for.

Exposes a dictionary interface of the tags in the directory:

```

ifd = ImageFileDirectory_v2()
ifd[key] = 'Some Data'
ifd.tagtype[key] = 2
print(ifd[key])
'Some Data'

```

Individual values are returned as the strings or numbers, sequences are returned as tuples of the values.

The tiff metadata type of each item is stored in a dictionary of tag types in `~PIL.TiffImagePlugin.ImageFileDirectory_v2.tagtype`. The types are read from a tiff file, guessed from the type added, or added manually.

Data Structures:

- `self.tagtype = {}`
 - Key: numerical tiff tag number
 - Value: integer corresponding to the data type from `~PIL.TiffTags.TYPES`

3.0.0 .

as_dict()

Return a dictionary of the image's tags.

3.0.0 .

legacy_api

load(fp)

load_byte(data, legacy_api=True)

load_double(data, legacy_api=True)

load_float(data, legacy_api=True)

load_long(data, legacy_api=True)

load_rational(data, legacy_api=True)

load_short(data, legacy_api=True)

load_signed_byte(data, legacy_api=True)

load_signed_long(data, legacy_api=True)

load_signed_rational(data, legacy_api=True)

load_signed_short(data, legacy_api=True)

load_string(data, legacy_api=True)

load_undefined(data, legacy_api=True)

named()

dict of name:key: value

Returns the complete tag dictionary, with named tags where possible.

offset

prefix

reset()

save(fp)

```
write_byte (data)  
write_double (*values)  
write_float (*values)  
write_long (*values)  
write_rational (*values)  
write_short (*values)  
write_signed_byte (*values)  
write_signed_long (*values)  
write_signed_rational (*values)  
write_signed_short (*values)  
write_string (value)  
write_undefined (value)
```

```
class PIL.TiffImagePlugin.TiffImageFile (fp=None, filename=None)  
    PIL.ImageFile.ImageFile  
  
    format = 'TIFF'  
    format_description = 'Adobe TIFF'  
    is_animated  
    load ()  
    n_frames  
    seek (frame)  
        Select a given frame as current image  
    tell ()  
        Return the current frame number
```

3.28.37 WebPImagePlugin Module

```
class PIL.WebPImagePlugin.WebPImageFile (fp=None, filename=None)  
    PIL.ImageFile.ImageFile  
  
    format = 'WEBP'  
    format_description = 'WebP image'
```

3.28.38 WmfImagePlugin Module

```
class PIL.WmfImagePlugin.WmfStubImageFile (fp=None, filename=None)  
    PIL.ImageFile.StubImageFile  
  
    format = 'WMF'  
    format_description = 'Windows Metafile'  
  
PIL.WmfImagePlugin.register_handler (handler)  
PIL.WmfImagePlugin.short (c, o=0)
```

3.28.39 XVThumbImagePlugin Module

```
class PIL.XVThumbImagePlugin.XVThumbImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'XVThumb'
    format_description = 'XV thumbnail image'
```

3.28.40 XbmImagePlugin Module

```
class PIL.XbmImagePlugin.XbmImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'XBM'
    format_description = 'X11 Bitmap'
```

3.28.41 XpmImagePlugin Module

```
class PIL.XpmImagePlugin.XpmImageFile (fp=None, filename=None)
    PIL.ImageFile.ImageFile

    format = 'XPM'
    format_description = 'X11 Pixel Map'
    load_read (bytes)
```

Porting

Porting existing PIL-based code to Pillow

Pillow is a functional drop-in replacement for the Python Imaging Library. To run your existing PIL-compatible code with Pillow, it needs to be modified to import the `Image` module from the `PIL` namespace *instead* of the global namespace. Change this:

```
import Image
```

to this:

```
from PIL import Image
```

The `_imaging` module has been moved. You can now import it like this:

```
from PIL.Image import core as _imaging
```

The image plugin loading mechanism has changed. Pillow no longer automatically imports any file in the Python path with a name ending in `ImagePlugin.py`. You will need to import your image plugin manually.

Pillow will raise an exception if the core extension can't be loaded for any reason, including a version mismatch between the Python and extension code. Previously PIL allowed Python only code to run if the core extension was not available.

5.1 Goals

The fork author’s goal is to foster and support active development of PIL through:

- Continuous integration testing via [Travis CI](#) and [AppVeyor](#)
- Publicized development activity on [GitHub](#)
- Regular releases to the [Python Package Index](#)

5.2 License

Like PIL, Pillow is licensed under the [MIT-like open source PIL Software License](#)

5.3 Why a fork?

PIL is not [setuptools](#) compatible. Please see [this Image-SIG post](#) for a more detailed explanation. Also, PIL’s current bi-yearly (or greater) release schedule is too infrequent to accommodate the large number and frequency of issues reported.

5.4 What about PIL?

: Prior to Pillow 2.0.0, very few image code changes were made. Pillow 2.0.0 added Python 3 support and includes many bug fixes from many contributors.

As more time passes since the last PIL release, the likelihood of a new PIL release decreases. However, we’ve yet to hear an official “PIL is dead” announcement. So if you still want to support PIL, please [report issues here first](#), then [open corresponding Pillow tickets here](#).

Please provide a link to the first ticket so we can track the issue(s) upstream.

Release Notes

: Contributors please include release notes as needed or appropriate with your bug fixes, feature additions and tests.

6.1 3.2.0

6.1.1 New DDS and FTEX Image Plugins

The `DdsImagePlugin` reading DXT1 and DXT5 encoded `.dds` images was added. DXT3 images are not currently supported.

The `FtexImagePlugin` reads textures used for 3D objects in *Independence War 2: Edge Of Chaos*. The plugin reads a single texture per file, in the `.ftc` (compressed) and `.ftu` (uncompressed) formats.

6.1.2 Updates to the `GbrImagePlugin`

The `GbrImagePlugin` (GIMP brush format) has been updated to fix support for version 1 files and add support for version 2 files.

6.1.3 Passthrough Parameters for `ImageDraw.text`

`ImageDraw.multiline_text` and `ImageDraw.multiline_size` take extra spacing parameters above what are used in `ImageDraw.text` and `ImageDraw.size`. These parameters can now be passed into `ImageDraw.text` and `ImageDraw.size` and they will be passed through to the corresponding multiline functions.

6.1.4 `ImageSequence.Iterator` changes

`ImageSequence.Iterator` is now an actual iterator implementing the `Iterator` protocol. It is also now possible to seek to the first image of the file when using direct indexing.

6.2 3.1.2

6.2.1 CVE-2016-3076 – Buffer overflow in Jpeg2KEncode.c

Pillow between 2.5.0 and 3.1.1 may overflow a buffer when writing large Jpeg2000 files, allowing for code execution or other memory corruption.

This occurs specifically in the function `j2k_encode_entry`, at the line:

```
state->buffer = malloc (tile_width * tile_height * components * prec / 8);
```

This vulnerability requires a particular value for `height * width` such that `height * width * components * precision` overflows, at which point the `malloc` will be for a smaller value than expected. The buffer that is allocated will be $((\text{height} * \text{width} * \text{components} * \text{precision}) \bmod (2^{31}) / 8)$, where `components` is 1-4 and `precision` is either 8 or 16. Common values would be 4 components at precision 8 for a standard RGBA image.

The unpackers then split an image that is laid out:

```
RGBARGBARGBA...
```

into:

```
RRR.  
GGG.  
BBB.  
AAA.
```

If this buffer is smaller than expected, the `jpeg2k` unpacker functions will write outside the allocation and onto the heap, corrupting memory.

This issue was found by Alyssa Besseling at Atlassian.

6.3 3.1.1

6.3.1 CVE-2016-0740 – Buffer overflow in TiffDecode.c

Pillow 3.1.0 and earlier when linked against `libtiff >= 4.0.0` on x64 may overflow a buffer when reading a specially crafted `tiff` file.

Specifically, `libtiff >= 4.0.0` changed the return type of `TIFFScanlineSize` from `int32` to machine dependent `int32|64`. If the scanline is sized so that it overflows an `int32`, it may be interpreted as a negative number, which will then pass the size check in `TiffDecode.c` line 236. To do this, the logical scanline size has to be $> 2\text{gb}$, and for the test file, the allocated buffer size is 64k against a roughly 4gb scan line size. Any image data over 64k is written over the heap, causing a segfault.

This issue was found by security researcher FourOne.

6.3.2 CVE-2016-0775 – Buffer overflow in FliDecode.c

In all versions of Pillow, dating back at least to the last PIL 1.1.7 release, `FliDecode.c` has a buffer overflow error.

Around line 192:

```

case 16:
    /* COPY chunk */
    for (y = 0; y < state->ysize; y++) {
        UINT8* buf = (UINT8*) im->image[y];
        memcpy(buf+x, data, state->xsize);
        data += state->xsize;
    }
    break;

```

The `memcpy` has error where `x` is added to the target buffer address. `x` is used in several internal temporary variable roles, but can take a value up to the width of the image. `im->image[y]` is a set of row pointers to segments of memory that are the size of the row. At the max `y`, this will write the contents of the line off the end of the memory buffer, causing a segfault.

This issue was found by Alyssa Besseling at Atlassian

6.3.3 CVE-2016-2533 – Buffer overflow in PcdDecode.c

In all versions of Pillow, dating back at least to the last PIL 1.1.7 release, `PcdDecode.c` has a buffer overflow error.

The `state.buffer` for `PcdDecode.c` is allocated based on a 3 bytes per pixel sizing, where `PcdDecode.c` wrote into the buffer assuming 4 bytes per pixel. This writes 768 bytes beyond the end of the buffer into other Python object storage. In some cases, this causes a segfault, in others an internal Python malloc error.

6.3.4 Integer overflow in Resample.c

If a large value was passed into the new size for an image, it is possible to overflow an `int32` value passed into `malloc`.

```
kk = malloc(xsize * kmax * sizeof(float)); ... xbounds = malloc(xsize * 2 * sizeof(int));
```

`xsize` is trusted user input. These multiplications can overflow, leading the malloc'd buffer to be undersized. These allocations are followed by a loop that writes out of bounds. This can lead to corruption on the heap of the Python process with attacker controlled float data.

This issue was found by Ned Williamson.

6.4 3.1.0

6.4.1 ImageDraw arc, chord and pieslice can now use floats

There is no longer a need to ensure that the start and end arguments for `arc`, `chord` and `pieslice` are integers.

Note that these numbers are not simply rounded internally, but are actually utilised in the drawing process.

6.4.2 Consistent multiline text spacing

When using the `ImageDraw` multiline methods, the spacing between lines was inconsistent, based on the combination on ascenders and descenders.

This has now been fixed, so that lines are offset by their baselines, not the absolute height of each line.

There is also now a default spacing of 4px between lines.

6.4.3 Exif, Jpeg and Tiff Metadata

There were major changes in the TIFF ImageFileDirectory support in Pillow 3.0 that led to a number of regressions. Some of them have been fixed in Pillow 3.1, and some of them have been extended to have different behavior.

TiffImagePlugin.IFDRational

Pillow 3.0 changed rational metadata to use a float. In Pillow 3.1, this has changed to allow the expression of 0/0 as a valid piece of rational metadata to reflect usage in the wild.

Rational metadata is now encapsulated in an `IFDRational` instance. This class extends the `Rational` class to allow a denominator of 0. It compares as a float or a number, but does allow access to the raw numerator and denominator values through attributes.

When used in a `ImageFileDirectory_v1`, a 2 item tuple is returned of the numerator and denominator, as was done previously.

This class should be used when adding a rational value to an `ImageFileDirectory` for saving to image metadata.

JpegImagePlugin._getexif

In Pillow 3.0, the dictionary returned from the private, experimental, but generally widely used `_getexif` function changed to reflect the `ImageFileDirectory_v2` format, without a fallback to the previous format.

In Pillow 3.1, `_getexif` now returns a dictionary compatible with Pillow 2.9 and earlier, built with `ImageFileDirectory_v1` instances. Additionally, any single item tuples have been unwrapped and return a bare element.

The format returned by Pillow 3.0 has been abandoned. A more fully featured interface for EXIF is anticipated in a future release.

Out of Spec Metadata

In Pillow 3.0 and 3.1, images that contain metadata that is internally consistent but not in agreement with the TIFF spec may cause an exception when reading the metadata. This can happen when a tag that is specified to have a single value is stored with an array of values.

It is anticipated that this behavior will change in future releases.

6.5 3.0.0

6.5.1 Saving Multipage Images

There is now support for saving multipage images in the *GIF* and *PDF* formats. To enable this functionality, pass in `save_all=True` as a keyword argument to the `save`:

```
im.save('test.pdf', save_all=True)
```

6.5.2 Tiff ImageFileDirectory Rewrite

The Tiff ImageFileDirectory metadata code has been rewritten. Where previously it returned a somewhat arbitrary set of values and tuples, it now returns bare values where appropriate and tuples when the metadata item is a sequence or collection.

The original metadata is still available in the `TiffImage.tags`, the new values are available in the `TiffImage.tags_v2` member. The old structures will be deprecated at some point in the future. When saving Tiff metadata, new code should use the `TiffImagePlugin.ImageFileDirectory_v2` class.

6.5.3 Deprecated Methods

Several methods that have been marked as deprecated for many releases have been removed in this release:

```
Image.tostring()
Image.fromstring()
Image.offset()
ImageDraw.setink()
ImageDraw.setfill()
The ImageFileIO module
The ImageFont.FreeTypeFont and ImageFont.truetype `file` keyword arg
The ImagePalette private _make functions
ImageWin.fromstring()
ImageWin.tostring()
```

6.5.4 LibJpeg and Zlib are Required by Default

The external dependencies on libjpeg and zlib are now required by default. If the headers or libraries are not found, then installation will abort with an error. This behaviour can be disabled with the `--disable-libjpeg` and `--disable-zlib` flags.

6.6 2.8.0

6.6.1 Open HTTP response objects with Image.open

HTTP response objects returned from `urllib2.urlopen(url)` or `requests.get(url, stream=True).raw` are ‘file-like’ but do not support `.seek()` operations. As a result PIL was unable to open them as images, requiring a wrap in `cStringIO` or `BytesIO`.

Now new functionality has been added to `Image.open()` by way of an `.seek(0)` check and catch on exception `AttributeError` or `io.UnsupportedOperation`. If this is caught we attempt to wrap the object using `io.BytesIO` (which will only work on buffer-file-like objects).

This allows opening of files using both `urllib2` and `requests`, e.g.:

```
Image.open(urllib2.urlopen(url))
Image.open(requests.get(url, stream=True).raw)
```

If the response uses content-encoding (compression, either gzip or deflate) then this will fail as both the `urllib2` and `requests` raw file object will produce compressed data in that case. Using Content-Encoding on images is rather non-sensical as most images are already compressed, but it can still happen.

For `requests` the work-around is to set the `decode_content` attribute on the raw object to `True`:

```
response = requests.get(url, stream=True)
response.raw.decode_content = True
image = Image.open(response.raw)
```

6.7 2.7.0

6.7.1 Sane Plugin

The Sane plugin has now been split into its own repo: <https://github.com/python-pillow/Sane> .

6.7.2 Png text chunk size limits

To prevent potential denial of service attacks using compressed text chunks, there are now limits to the decompressed size of text chunks decoded from PNG images. If the limits are exceeded when opening a PNG image a `ValueError` will be raised.

Individual text chunks are limited to `PIL.PngImagePlugin.MAX_TEXT_CHUNK`, set to 1MB by default. The total decompressed size of all text chunks is limited to `PIL.PngImagePlugin.MAX_TEXT_MEMORY`, which defaults to 64MB. These values can be changed prior to opening PNG images if you know that there are large text blocks that are desired.

6.7.3 Image resizing filters

Image resizing methods `resize()` and `thumbnail()` take a *resample* argument, which tells which filter should be used for resampling. Possible values are: `PIL.Image.NEAREST`, `PIL.Image.BILINEAR`, `PIL.Image.BICUBIC` and `PIL.Image.ANTIALIAS`. Almost all of them were changed in this version.

Bicubic and bilinear downscaling

From the beginning `BILINEAR` and `BICUBIC` filters were based on affine transformations and used a fixed number of pixels from the source image for every destination pixel (2x2 pixels for `BILINEAR` and 4x4 for `BICUBIC`). This gave an unsatisfactory result for downscaling. At the same time, a high quality convolutions-based algorithm with flexible kernel was used for `ANTIALIAS` filter.

Starting from Pillow 2.7.0, a high quality convolutions-based algorithm is used for all of these three filters.

If you have previously used any tricks to maintain quality when downscaling with `BILINEAR` and `BICUBIC` filters (for example, reducing within several steps), they are unnecessary now.

Antialias renamed to Lanczos

A new `PIL.Image.LANCZOS` constant was added instead of `ANTIALIAS`.

When `ANTIALIAS` was initially added, it was the only high-quality filter based on convolutions. It's name was supposed to reflect this. Starting from Pillow 2.7.0 all resize method are based on convolutions. All of them are antialias from now on. And the real name of the `ANTIALIAS` filter is Lanczos filter.

The `ANTIALIAS` constant is left for backward compatibility and is an alias for `LANCZOS`.

Lanczos upscaling quality

The image upscaling quality with LANCZOS filter was almost the same as BILINEAR due to bug. This has been fixed.

Bicubic upscaling quality

The BICUBIC filter for affine transformations produced sharp, slightly pixelated image for upscaling. Bicubic for convolutions is more soft.

Resize performance

In most cases, convolution is more a expensive algorithm for downscaling because it takes into account all the pixels of source image. Therefore BILINEAR and BICUBIC filters' performance can be lower than before. On the other hand the quality of BILINEAR and BICUBIC was close to NEAREST. So if such quality is suitable for your tasks you can switch to NEAREST filter for downscaling, which will give a huge improvement in performance.

At the same time performance of convolution resampling for downscaling has been improved by around a factor of two compared to the previous version. The upscaling performance of the LANCZOS filter has remained the same. For BILINEAR filter it has improved by 1.5 times and for BICUBIC by four times.

Default filter for thumbnails

In Pillow 2.5 the default filter for `thumbnail()` was changed from NEAREST to ANTIALIAS. Antialias was chosen because all the other filters gave poor quality for reduction. Starting from Pillow 2.7.0, ANTIALIAS has been replaced with BICUBIC, because it's faster and ANTIALIAS doesn't give any advantages after downscaling with libjpeg, which uses supersampling internally, not convolutions.

6.7.4 Image transposition

A new method `PIL.Image.TRANSPOSE` has been added for the `transpose()` operation in addition to `FLIP_LEFT_RIGHT`, `FLIP_TOP_BOTTOM`, `ROTATE_90`, `ROTATE_180`, `ROTATE_270`. TRANSPOSE is an algebra transpose, with an image reflected across its main diagonal.

The speed of `ROTATE_90`, `ROTATE_270` and `TRANSPOSE` has been significantly improved for large images which don't fit in the processor cache.

6.7.5 Gaussian blur and unsharp mask

The `GaussianBlur()` implementation has been replaced with a sequential application of box filters. The new implementation is based on "Theoretical foundations of Gaussian convolution by extended box filtering" from the Mathematical Image Analysis Group. As `UnsharpMask()` implementations use Gaussian blur internally, all changes from this chapter are also applicable to it.

Blur radius

There was an error in the previous version of Pillow, where blur radius (the standard deviation of Gaussian) actually meant blur diameter. For example, to blur an image with actual radius 5 you were forced to use value 10. This has been fixed. Now the meaning of the radius is the same as in other software.

If you used a Gaussian blur with some radius value, you need to divide this value by two.

Blur performance

Box filter computation time is constant relative to the radius and depends on source image size only. Because the new Gaussian blur implementation is based on box filter, its computation time also doesn't depend on the blur radius.

For example, previously, if the execution time for a given test image was 1 second for radius 1, 3.6 seconds for radius 10 and 17 seconds for 50, now blur with any radius on same image is executed for 0.2 seconds.

Blur quality

The previous implementation takes into account only source pixels within $2 * \text{standard deviation radius}$ for every destination pixel. This was not enough, so the quality was worse compared to other Gaussian blur software.

The new implementation does not have this drawback.

6.7.6 TIFF Parameter Changes

Several kwarg parameters for saving TIFF images were previously specified as strings with included spaces (e.g. 'x resolution'). This was difficult to use as kwargs without constructing and passing a dictionary. These parameters now use the underscore character instead of space. (e.g. 'x_resolution')

Indices and tables

- `genindex`
- `modindex`
- `search`

p

PIL._binary, 107
PIL.BdfFontFile, 101
PIL.BmpImagePlugin, 107
PIL.BufrStubImagePlugin, 108
PIL.ContainerIO, 101
PIL.CurImagePlugin, 108
PIL.DcxImagePlugin, 108
PIL.EpsImagePlugin, 108
PIL.ExifTags, 88
PIL.FitsStubImagePlugin, 109
PIL.FliImagePlugin, 109
PIL.FontFile, 102
PIL.FpxImagePlugin, 109
PIL.GbrImagePlugin, 110
PIL.GdImageFile, 102
PIL.GifImagePlugin, 110
PIL.GimpGradientFile, 102
PIL.GimpPaletteFile, 102
PIL.GribStubImagePlugin, 110
PIL.Hdf5StubImagePlugin, 110
PIL.IcnsImagePlugin, 111
PIL.IcoImagePlugin, 111
PIL.Image, 37
PIL.ImageChops, 49
PIL.ImageCms, 53
PIL.ImageColor, 52
PIL.ImageDraw, 66
PIL.ImageDraw2, 103
PIL.ImageEnhance, 71
PIL.ImageFile, 72
PIL.ImageFilter, 73
PIL.ImageFont, 75
PIL.ImageGrab, 77
PIL.ImageMath, 77
PIL.ImageMorph, 79
PIL.ImageOps, 80
PIL.ImagePalette, 83
PIL.ImagePath, 84
PIL.ImageQt, 84
PIL.ImageSequence, 85
PIL.ImageShow, 103
PIL.ImageStat, 85
PIL.ImageTk, 86
PIL.ImageTransform, 104
PIL.ImageWin, 87
PIL.ImImagePlugin, 112
PIL.ImtImagePlugin, 112
PIL.IptcImagePlugin, 112
PIL.Jpeg2KImagePlugin, 113
PIL.JpegImagePlugin, 113
PIL.JpegPresets, 104
PIL.McIdasImagePlugin, 113
PIL.MicImagePlugin, 114
PIL.MpegImagePlugin, 114
PIL.MspImagePlugin, 114
PIL.OleFileIO, 89
PIL.PaletteFile, 105
PIL.PalmImagePlugin, 114
PIL.PcdImagePlugin, 114
PIL.PcfFontFile, 106
PIL.PcxImagePlugin, 115
PIL.PdfImagePlugin, 115
PIL.PixarImagePlugin, 115
PIL.PngImagePlugin, 115
PIL.PpmImagePlugin, 116
PIL.PsdImagePlugin, 116
PIL.PSDraw, 99
PIL.PyAccess, 101
PIL.SgiImagePlugin, 117
PIL.SpiderImagePlugin, 117
PIL.SunImagePlugin, 117
PIL.TarIO, 107
PIL.TgaImagePlugin, 117
PIL.TiffImagePlugin, 118
PIL.TiffTags, 89
PIL.WalImageFile, 107
PIL.WebPImagePlugin, 120
PIL.WmfImagePlugin, 120
PIL.XbmImagePlugin, 121
PIL.XpmImagePlugin, 121

PIL.XVThumbImagePlugin, 121

Symbols

`__init__()` (PIL.TiffTags.TagInfo), 89
`__new__()` (PIL.PcfFontFile.iTXt), 106

A

`add()` (PIL.PngImagePlugin.PngInfo), 106
`add_itxt()` (PIL.PngImagePlugin.PngInfo), 106
`add_text()` (PIL.PngImagePlugin.PngInfo), 106
`arc()` (PIL.ImageDraw.PIL.ImageDraw.Draw), 68
`arc()` (PIL.ImageDraw2.Draw), 103
`as_dict()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
`attributes` (PIL.ImageCms.CmsProfile), 63

B

`begin_document()` (PIL.PSDraw.PSDraw), 99
`bestsize()` (PIL.IcnsImagePlugin.IcnsFile), 111
`BITFIELDS` (PIL.BmpImagePlugin.BmpImageFile), 107
`bitmap` (PIL.FontFile.FontFile), 102
`bitmap()` (PIL.ImageDraw.PIL.ImageDraw.Draw), 68
`blue_colorant` (PIL.ImageCms.CmsProfile), 63
`blue_primary` (PIL.ImageCms.CmsProfile), 65

C

`call()` (PIL.PngImagePlugin.ChunkStream), 115
`check_text_memory()` (PIL.PngImagePlugin.PngStream), 116
`chord()` (PIL.ImageDraw.PIL.ImageDraw.Draw), 69
`chord()` (PIL.ImageDraw2.Draw), 103
`chromatic_adaption` (PIL.ImageCms.CmsProfile), 64
`chromaticity` (PIL.ImageCms.CmsProfile), 64
`chunk_gAMA()` (PIL.PngImagePlugin.PngStream), 116
`chunk_iCCP()` (PIL.PngImagePlugin.PngStream), 116
`chunk_IDAT()` (PIL.PngImagePlugin.PngStream), 116
`chunk_IEND()` (PIL.PngImagePlugin.PngStream), 116
`chunk_IHDR()` (PIL.PngImagePlugin.PngStream), 116
`chunk_iTXt()` (PIL.PngImagePlugin.PngStream), 116
`chunk_pHYs()` (PIL.PngImagePlugin.PngStream), 116
`chunk_PLTE()` (PIL.PngImagePlugin.PngStream), 116

`chunk_tEXt()` (PIL.PngImagePlugin.PngStream), 116
`chunk_tRNS()` (PIL.PngImagePlugin.PngStream), 116
`chunk_zTXt()` (PIL.PngImagePlugin.PngStream), 116
`close()` (PIL.Image.Image), 48
`close()` (PIL.ImageFile.Parser), 73
`close()` (PIL.PngImagePlugin.ChunkStream), 115
`clut` (PIL.ImageCms.CmsProfile), 65
`color_space` (PIL.ImageCms.CmsProfile), 66
`colorant_table` (PIL.ImageCms.CmsProfile), 64
`colorant_table_out` (PIL.ImageCms.CmsProfile), 64
`colorimetric_intent` (PIL.ImageCms.CmsProfile), 64
`compact()` (PIL.ImagePath.PIL.ImagePath.Path), 84
`compile()` (PIL.FontFile.FontFile), 102
`COMPRESSIONS` (PIL.BmpImagePlugin.BmpImageFile), 107
`connection_space` (PIL.ImageCms.CmsProfile), 62
`convert()` (PIL.Image.Image), 41
`convert2byte()` (PIL.SpiderImagePlugin.SpiderImageFile), 117
`copy()` (PIL.Image.Image), 42
`copyright` (PIL.ImageCms.CmsProfile), 63
`count` (PIL.ImageStat.PIL.ImageStat.Stat), 86
`crc()` (PIL.PngImagePlugin.ChunkStream), 115
`crc_skip()` (PIL.PngImagePlugin.ChunkStream), 115
`creation_date` (PIL.ImageCms.CmsProfile), 62
`crop()` (PIL.Image.Image), 42
`cvt_enum()` (PIL.TiffTags.TagInfo), 89

D

`data()` (PIL.GifImagePlugin.GifImageFile), 110
`dataforsize()` (PIL.IcnsImagePlugin.IcnsFile), 111
`denominator` (PIL.TiffImagePlugin.IFDRational), 118
`device_class` (PIL.ImageCms.CmsProfile), 62
`Dib` (PIL.ImageWin), 87
`draft()` (PIL.Image.Image), 42
`draft()` (PIL.JpegImagePlugin.JpegImageFile), 113
`draw()` (PIL.ImageWin.Dib), 87

E

`ellipse()` (PIL.ImageDraw.PIL.ImageDraw.Draw), 69

ellipse() (PIL.ImageDraw2.Draw), 103
end_document() (PIL.PSDraw.PSDraw), 99
enhance() (PIL.ImageEnhance._Enhance), 72
expose() (PIL.ImageWin.Dib), 88
extrema (PIL.ImageStat.PIL.ImageStat.Stat), 85

F

feed() (PIL.ImageFile.Parser), 73
field() (PIL.IptcImagePlugin.IptcImageFile), 112
filter() (PIL.Image.Image), 42
flush() (PIL.ImageDraw2.Draw), 103
format (PIL.BmpImagePlugin.BmpImageFile), 108
format (PIL.BmpImagePlugin.DibImageFile), 108
format (PIL.BufrStubImagePlugin.BufrStubImageFile), 108
format (PIL.CurImagePlugin.CurImageFile), 108
format (PIL.DcxImagePlugin.DcxImageFile), 108
format (PIL.EpsImagePlugin.EpsImageFile), 108
format (PIL.FitsStubImagePlugin.FITSSubImageFile), 109
format (PIL.FliImagePlugin.FliImageFile), 109
format (PIL.FpxImagePlugin.FpxImageFile), 109
format (PIL.GbrImagePlugin.GbrImageFile), 110
format (PIL.GdImageFile.GdImageFile), 102
format (PIL.GifImagePlugin.GifImageFile), 110
format (PIL.GribStubImagePlugin.GribStubImageFile), 110
format (PIL.Hdf5StubImagePlugin.HDF5StubImageFile), 110
format (PIL.IcnsImagePlugin.IcnsImageFile), 111
format (PIL.IcoImagePlugin.IcoImageFile), 112
format (PIL.ImageShow.Viewer), 103
format (PIL.ImImagePlugin.ImImageFile), 112
format (PIL.ImtImagePlugin.ImtImageFile), 112
format (PIL.IptcImagePlugin.IptcImageFile), 112
format (PIL.Jpeg2KImagePlugin.Jpeg2KImageFile), 113
format (PIL.JpegImagePlugin.JpegImageFile), 113
format (PIL.McIdasImagePlugin.McIdasImageFile), 113
format (PIL.MicImagePlugin.MicImageFile), 114
format (PIL.MpegImagePlugin.MpegImageFile), 114
format (PIL.MspImagePlugin.MspImageFile), 114
format (PIL.PcdImagePlugin.PcdImageFile), 114
format (PIL.PcxImagePlugin.PcxImageFile), 115
format (PIL.PixarImagePlugin.PixarImageFile), 115
format (PIL.PngImagePlugin.PngImageFile), 115
format (PIL.PpmImagePlugin.PpmImageFile), 116
format (PIL.PsdImagePlugin.PsdImageFile), 116
format (PIL.SgiImagePlugin.SgiImageFile), 117
format (PIL.SpiderImagePlugin.SpiderImageFile), 117
format (PIL.SunImagePlugin.SunImageFile), 117
format (PIL.TgaImagePlugin.TgaImageFile), 117
format (PIL.TiffImagePlugin.TiffImageFile), 120
format (PIL.WebPImagePlugin.WebPImageFile), 120
format (PIL.WmfImagePlugin.WmfStubImageFile), 120
format (PIL.XbmImagePlugin.XbmImageFile), 121
format (PIL.XpmImagePlugin.XpmImageFile), 121
format (PIL.XVThumbImagePlugin.XVThumbImageFile), 121
format_description (PIL.BmpImagePlugin.BmpImageFile), 108
format_description (PIL.BmpImagePlugin.DibImageFile), 108
format_description (PIL.BufrStubImagePlugin.BufrStubImageFile), 108
format_description (PIL.CurImagePlugin.CurImageFile), 108
format_description (PIL.DcxImagePlugin.DcxImageFile), 108
format_description (PIL.EpsImagePlugin.EpsImageFile), 109
format_description (PIL.FitsStubImagePlugin.FITSSubImageFile), 109
format_description (PIL.FliImagePlugin.FliImageFile), 109
format_description (PIL.FpxImagePlugin.FpxImageFile), 109
format_description (PIL.GbrImagePlugin.GbrImageFile), 110
format_description (PIL.GdImageFile.GdImageFile), 102
format_description (PIL.GifImagePlugin.GifImageFile), 110
format_description (PIL.GribStubImagePlugin.GribStubImageFile), 110
format_description (PIL.Hdf5StubImagePlugin.HDF5StubImageFile), 110
format_description (PIL.IcnsImagePlugin.IcnsImageFile), 111
format_description (PIL.IcoImagePlugin.IcoImageFile), 112
format_description (PIL.ImImagePlugin.ImImageFile), 112
format_description (PIL.ImtImagePlugin.ImtImageFile), 112
format_description (PIL.IptcImagePlugin.IptcImageFile), 112
format_description (PIL.Jpeg2KImagePlugin.Jpeg2KImageFile), 113
format_description (PIL.JpegImagePlugin.JpegImageFile), 113
format_description (PIL.McIdasImagePlugin.McIdasImageFile), 113
format_description (PIL.MicImagePlugin.MicImageFile), 114
format_description (PIL.MpegImagePlugin.MpegImageFile), 114
format_description (PIL.MspImagePlugin.MspImageFile), 114
format_description (PIL.PcdImagePlugin.PcdImageFile), 114
format_description (PIL.PcxImagePlugin.PcxImageFile), 115
format_description (PIL.PixarImagePlugin.PixarImageFile), 115
format_description (PIL.PngImagePlugin.PngImageFile), 115
format_description (PIL.PpmImagePlugin.PpmImageFile), 116
format_description (PIL.PsdImagePlugin.PsdImageFile), 116
format_description (PIL.SgiImagePlugin.SgiImageFile), 117
format_description (PIL.SpiderImagePlugin.SpiderImageFile), 117
format_description (PIL.SunImagePlugin.SunImageFile), 117
format_description (PIL.TgaImagePlugin.TgaImageFile), 117
format_description (PIL.TiffImagePlugin.TiffImageFile), 120
format_description (PIL.WebPImagePlugin.WebPImageFile), 120
format_description (PIL.WmfImagePlugin.WmfStubImageFile), 120
format_description (PIL.XbmImagePlugin.XbmImageFile), 121
format_description (PIL.XpmImagePlugin.XpmImageFile), 121
format_description (PIL.XVThumbImagePlugin.XVThumbImageFile), 121

- format_description (PIL.PcdImagePlugin.PcdImageFile), 114
- format_description (PIL.PcxImagePlugin.PcxImageFile), 115
- format_description (PIL.PixarImagePlugin.PixarImageFile), 115
- format_description (PIL.PngImagePlugin.PngImageFile), 115
- format_description (PIL.PpmImagePlugin.PpmImageFile), 116
- format_description (PIL.PsdImagePlugin.PsdImageFile), 116
- format_description (PIL.SgiImagePlugin.SgiImageFile), 117
- format_description (PIL.SpiderImagePlugin.SpiderImageFile), 117
- format_description (PIL.SunImagePlugin.SunImageFile), 117
- format_description (PIL.TgaImagePlugin.TgaImageFile), 117
- format_description (PIL.TiffImagePlugin.TiffImageFile), 120
- format_description (PIL.WebPImagePlugin.WebPImageFile), 120
- format_description (PIL.WmfImagePlugin.WmfStubImageFile), 120
- format_description (PIL.XbmImagePlugin.XbmImageFile), 121
- format_description (PIL.XpmImagePlugin.XpmImageFile), 121
- format_description (PIL.XVThumbImagePlugin.XVThumbImageFile), 121
- frame() (PIL.IcoImagePlugin.IcoFile), 111
- frombytes() (PIL.ImageWin.Dib), 88
- fromstring() (PIL.Image.Image), 48
- ## G
- get_command() (PIL.ImageShow.Viewer), 103
- get_command_ex() (PIL.ImageShow.DisplayViewer), 103
- get_command_ex() (PIL.ImageShow.XVViewer), 104
- get_format() (PIL.ImageShow.Viewer), 103
- getbands() (PIL.Image.Image), 43
- getbbox() (PIL.Image.Image), 43
- getbbox() (PIL.ImagePath.PIL.ImagePath.Path), 84
- getcolor() (PIL.ImagePalette.ImagePalette), 83
- getcolors() (PIL.Image.Image), 43
- getdata() (PIL.Image.Image), 43
- getdata() (PIL.ImagePalette.ImagePalette), 83
- getdata() (PIL.ImageTransform.Transform), 104
- getextrema() (PIL.Image.Image), 43
- getimage() (PIL.IcnsImagePlugin.IcnsFile), 111
- getimage() (PIL.IcoImagePlugin.IcoFile), 111
- getint() (PIL.IptcImagePlugin.IptcImageFile), 112
- getmask() (PIL.ImageFont.PIL.ImageFont.ImageFont), 76
- getpalette() (PIL.GimpGradientFile.GradientFile), 102
- getpalette() (PIL.GimpPaletteFile.GimpPaletteFile), 102
- getpalette() (PIL.Image.Image), 43
- getpalette() (PIL.PaletteFile.PaletteFile), 105
- getpixel() (PIL.Image.Image), 43
- getsize() (PIL.ImageFont.PIL.ImageFont.ImageFont), 76
- global_palette (PIL.GifImagePlugin.GifImageFile), 110
- gradient (PIL.GimpGradientFile.GradientFile), 102
- green_colorant (PIL.ImageCms.CmsProfile), 63
- green_primary (PIL.ImageCms.CmsProfile), 65
- ## H
- HDC (PIL.ImageWin), 88
- header_flags (PIL.ImageCms.CmsProfile), 62
- header_manufacturer (PIL.ImageCms.CmsProfile), 62
- header_model (PIL.ImageCms.CmsProfile), 62
- height() (PIL.ImageTk.BitmapImage), 86
- height() (PIL.ImageTk.PhotoImage), 87
- histogram() (PIL.Image.Image), 43
- HWND (PIL.ImageWin), 88
- ## I
- icc_version (PIL.ImageCms.CmsProfile), 62
- Image (PIL.Image), 41
- image() (PIL.PSDraw.PSDraw), 99
- intent_supported (PIL.ImageCms.CmsProfile), 65
- is_animated (PIL.DcxImagePlugin.DcxImageFile), 108
- is_animated (PIL.FliImagePlugin.FliImageFile), 109
- is_animated (PIL.GifImagePlugin.GifImageFile), 110
- is_animated (PIL.ImImagePlugin.ImImageFile), 112
- is_animated (PIL.MicImagePlugin.MicImageFile), 114
- is_animated (PIL.PsdImagePlugin.PsdImageFile), 116
- is_animated (PIL.SpiderImagePlugin.SpiderImageFile), 117
- is_animated (PIL.TiffImagePlugin.TiffImageFile), 120
- is_intent_supported() (PIL.ImageCms.CmsProfile), 66
- is_matrix_shaper (PIL.ImageCms.CmsProfile), 65
- isatty() (PIL.ContainerIO.ContainerIO), 101
- itersizes() (PIL.IcnsImagePlugin.IcnsFile), 111
- ## J
- JPEG (PIL.BmpImagePlugin.BmpImageFile), 107
- ## L
- legacy_api (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- limit_rational() (PIL.TiffImagePlugin.IFDRational), 118
- line() (PIL.ImageDraw.PIL.ImageDraw.Draw), 69
- line() (PIL.ImageDraw2.Draw), 103
- line() (PIL.PSDraw.PSDraw), 99
- load() (PIL.EpsImagePlugin.EpsImageFile), 109

- load() (PIL.FpxImagePlugin.FpxImageFile), 109
- load() (PIL.GbrImagePlugin.GbrImageFile), 110
- load() (PIL.IcnsImagePlugin.IcnsImageFile), 111
- load() (PIL.IcoImagePlugin.IcoImageFile), 112
- load() (PIL.Image.Image), 48
- load() (PIL.IptcImagePlugin.IptcImageFile), 113
- load() (PIL.Jpeg2KImagePlugin.Jpeg2KImageFile), 113
- load() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load() (PIL.TiffImagePlugin.TiffImageFile), 120
- load_byte() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_djpeg() (PIL.JpegImagePlugin.JpegImageFile), 113
- load_double() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_end() (PIL.GifImagePlugin.GifImageFile), 110
- load_end() (PIL.PngImagePlugin.PngImageFile), 115
- load_float() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_long() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_prepare() (PIL.PngImagePlugin.PngImageFile), 116
- load_prepare() (PIL.PsdImagePlugin.PsdImageFile), 116
- load_rational() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_read() (PIL.PngImagePlugin.PngImageFile), 116
- load_read() (PIL.XpmImagePlugin.XpmImageFile), 121
- load_seek() (PIL.EpsImagePlugin.EpsImageFile), 109
- load_seek() (PIL.IcoImagePlugin.IcoImageFile), 112
- load_short() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_signed_byte() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_signed_long() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_signed_rational() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_signed_short() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_string() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- load_undefined() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- luminance (PIL.ImageCms.CmsProfile), 64
- ## M
- manufacturer (PIL.ImageCms.CmsProfile), 63
- map() (PIL.ImagePath.PIL.ImagePath.Path), 84
- mean (PIL.ImageStat.PIL.ImageStat.Stat), 86
- media_black_point (PIL.ImageCms.CmsProfile), 64
- media_white_point_temperature (PIL.ImageCms.CmsProfile), 65
- median (PIL.ImageStat.PIL.ImageStat.Stat), 86
- method (PIL.ImageTransform.AffineTransform), 104
- method (PIL.ImageTransform.ExtentTransform), 104
- method (PIL.ImageTransform.MeshTransform), 104
- method (PIL.ImageTransform.QuadTransform), 104
- mode_map (PIL.EpsImagePlugin.EpsImageFile), 109
- model (PIL.ImageCms.CmsProfile), 63
- multiline_text() (PIL.ImageDraw.PIL.ImageDraw.Draw), 70
- multiline_textsize() (PIL.ImageDraw.PIL.ImageDraw.Draw), 71
- ## N
- n_frames (PIL.DcxImagePlugin.DcxImageFile), 108
- n_frames (PIL.FliImagePlugin.FliImageFile), 109
- n_frames (PIL.GifImagePlugin.GifImageFile), 110
- n_frames (PIL.ImImagePlugin.ImImageFile), 112
- n_frames (PIL.MicImagePlugin.MicImageFile), 114
- n_frames (PIL.PsdImagePlugin.PsdImageFile), 116
- n_frames (PIL.SpiderImagePlugin.SpiderImageFile), 117
- n_frames (PIL.TiffImagePlugin.TiffImageFile), 120
- name (PIL.PcfFontFile.PcfFontFile), 106
- named() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- next() (PIL.MpegImagePlugin.BitStream), 114
- numerator (PIL.TiffImagePlugin.IFDRational), 118
- ## O
- offset (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
- offset() (PIL.Image.Image), 44
- ## P
- paste() (PIL.Image.Image), 44
- paste() (PIL.ImageTk.PhotoImage), 87
- paste() (PIL.ImageWin.Dib), 88
- pcs (PIL.ImageCms.CmsProfile), 66
- peek() (PIL.MpegImagePlugin.BitStream), 114
- perceptual_rendering_intent_gamut (PIL.ImageCms.CmsProfile), 64
- pieslice() (PIL.ImageDraw.PIL.ImageDraw.Draw), 69
- pieslice() (PIL.ImageDraw2.Draw), 103
- PIL_binary (), 107
- PIL.BdfFontFile (), 101
- PIL.BmpImagePlugin (), 107
- PIL.BufrStubImagePlugin (), 108
- PIL.ContainerIO (), 101
- PIL.CurImagePlugin (), 108
- PIL.DcxImagePlugin (), 108
- PIL.EpsImagePlugin (), 108
- PIL.ExifTags (), 88
- PIL.FitsStubImagePlugin (), 109
- PIL.FliImagePlugin (), 109
- PIL.FontFile (), 102

- PIL.FpxImagePlugin (), 109
 - PIL.GbrImagePlugin (), 110
 - PIL.GdImageFile (), 102
 - PIL.GifImagePlugin (), 110
 - PIL.GimpGradientFile (), 102
 - PIL.GimpPaletteFile (), 102
 - PIL.GribStubImagePlugin (), 110
 - PIL.Hdf5StubImagePlugin (), 110
 - PIL.IcnsImagePlugin (), 111
 - PIL.IcoImagePlugin (), 111
 - PIL.Image (), 37
 - PIL.ImageChops (), 49
 - PIL.ImageCms (), 53
 - PIL.ImageColor (), 52
 - PIL.ImageDraw (), 66
 - PIL.ImageDraw2 (), 103
 - PIL.ImageEnhance (), 71
 - PIL.ImageFile (), 72
 - PIL.ImageFilter (), 73
 - PIL.ImageFont (), 75
 - PIL.ImageGrab (), 77
 - PIL.ImageMath (), 77
 - PIL.ImageMorph (), 79
 - PIL.ImageOps (), 80
 - PIL.ImagePalette (), 83
 - PIL.ImagePath (), 84
 - PIL.ImageQt (), 84
 - PIL.ImageSequence (), 85
 - PIL.ImageShow (), 103
 - PIL.ImageStat (), 85
 - PIL.ImageTk (), 86
 - PIL.ImageTransform (), 104
 - PIL.ImageWin (), 87
 - PIL.ImImagePlugin (), 112
 - PIL.ImtImagePlugin (), 112
 - PIL.IptcImagePlugin (), 112
 - PIL.Jpeg2KImagePlugin (), 113
 - PIL.JpegImagePlugin (), 113
 - PIL.JpegPresets (), 104
 - PIL.McIdasImagePlugin (), 113
 - PIL.MicImagePlugin (), 114
 - PIL.MpegImagePlugin (), 114
 - PIL.MspImagePlugin (), 114
 - PIL.OleFileIO (), 89
 - PIL.PaletteFile (), 105
 - PIL.PalmImagePlugin (), 114
 - PIL.PcdImagePlugin (), 114
 - PIL.PcfFontFile (), 106
 - PIL.PcxImagePlugin (), 115
 - PIL.PdfImagePlugin (), 115
 - PIL.PixarImagePlugin (), 115
 - PIL.PngImagePlugin (), 115
 - PIL.PpmImagePlugin (), 116
 - PIL.PsdImagePlugin (), 116
 - PIL.PSDraw (), 99
 - PIL.PyAccess (), 101
 - PIL.SgiImagePlugin (), 117
 - PIL.SpiderImagePlugin (), 117
 - PIL.SunImagePlugin (), 117
 - PIL.TarIO (), 107
 - PIL.TgaImagePlugin (), 117
 - PIL.TiffImagePlugin (), 118
 - PIL.TiffTags (), 89
 - PIL.WallImageFile (), 107
 - PIL.WebPImagePlugin (), 120
 - PIL.WmfImagePlugin (), 120
 - PIL.XbmImagePlugin (), 121
 - PIL.XpmImagePlugin (), 121
 - PIL.XVThumbImagePlugin (), 121
 - PixelAccess (), 100
 - PNG (PIL.BmpImagePlugin.BmpImageFile), 107
 - point() (PIL.Image.Image), 44
 - point() (PIL.ImageDraw.PIL.ImageDraw.Draw), 69
 - polygon() (PIL.ImageDraw.PIL.ImageDraw.Draw), 70
 - polygon() (PIL.ImageDraw2.Draw), 103
 - prefix (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
 - product_copyright (PIL.ImageCms.CmsProfile), 66
 - product_desc (PIL.ImageCms.CmsProfile), 66
 - product_description (PIL.ImageCms.CmsProfile), 66
 - product_manufacturer (PIL.ImageCms.CmsProfile), 66
 - product_model (PIL.ImageCms.CmsProfile), 66
 - profile_description (PIL.ImageCms.CmsProfile), 63
 - profile_id (PIL.ImageCms.CmsProfile), 63
 - PSDraw (PIL.PSDraw), 99
 - push() (PIL.PngImagePlugin.ChunkStream), 115
 - putalpha() (PIL.Image.Image), 44
 - putdata() (PIL.Image.Image), 44
 - putpalette() (PIL.Image.Image), 45
 - putpixel() (PIL.Image.Image), 45
- ## Q
- quantize() (PIL.Image.Image), 45
 - query_palette() (PIL.ImageWin.Dib), 88
- ## R
- RAW (PIL.BmpImagePlugin.BmpImageFile), 107
 - rawmode (PIL.GimpPaletteFile.GimpPaletteFile), 103
 - rawmode (PIL.PaletteFile.PaletteFile), 105
 - read() (PIL.ContainerIO.ContainerIO), 101
 - read() (PIL.MpegImagePlugin.BitStream), 114
 - read() (PIL.PngImagePlugin.ChunkStream), 115
 - readline() (PIL.ContainerIO.ContainerIO), 101
 - readline() (PIL.EpsImagePlugin.PSFile), 109
 - readlines() (PIL.ContainerIO.ContainerIO), 101
 - rectangle() (PIL.ImageDraw.PIL.ImageDraw.Draw), 70
 - rectangle() (PIL.ImageDraw2.Draw), 103
 - rectangle() (PIL.PSDraw.PSDraw), 99

red_colorant (PIL.ImageCms.CmsProfile), 63
red_primary (PIL.ImageCms.CmsProfile), 65
render() (PIL.ImageDraw2.Draw), 103
rendering_intent (PIL.ImageCms.CmsProfile), 63
reset() (PIL.ImageFile.Parser), 73
reset() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
resize() (PIL.Image.Image), 45
RLE4 (PIL.BmpImagePlugin.BmpImageFile), 108
RLE8 (PIL.BmpImagePlugin.BmpImageFile), 108
rms (PIL.ImageStat.PIL.ImageStat.Stat), 86
rotate() (PIL.Image.Image), 46

S

saturation_rendering_intent_gamut (PIL.ImageCms.CmsProfile), 64
save() (PIL.FontFile.FontFile), 102
save() (PIL.Image.Image), 46
save() (PIL.ImagePalette.ImagePalette), 83
save() (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
save_image() (PIL.ImageShow.Viewer), 103
screening_description (PIL.ImageCms.CmsProfile), 65
seek() (PIL.ContainerIO.ContainerIO), 102
seek() (PIL.DcxImagePlugin.DcxImageFile), 108
seek() (PIL.EpsImagePlugin.PSFile), 109
seek() (PIL.FliImagePlugin.FliImageFile), 109
seek() (PIL.GifImagePlugin.GifImageFile), 110
seek() (PIL.Image.Image), 46
seek() (PIL.ImImagePlugin.ImImageFile), 112
seek() (PIL.MicImagePlugin.MicImageFile), 114
seek() (PIL.PsdImagePlugin.PsdImageFile), 116
seek() (PIL.SpiderImagePlugin.SpiderImageFile), 117
seek() (PIL.TiffImagePlugin.TiffImageFile), 120
setfont() (PIL.ImageDraw.PIL.ImageDraw.Draw), 71
setfont() (PIL.PSDraw.PSDraw), 99
settransform() (PIL.ImageDraw2.Draw), 103
shape() (PIL.ImageDraw.PIL.ImageDraw.Draw), 70
show() (PIL.Image.Image), 47
show() (PIL.ImageShow.Viewer), 104
show_file() (PIL.ImageShow.UnixViewer), 103
show_file() (PIL.ImageShow.Viewer), 104
show_image() (PIL.ImageShow.Viewer), 104
SIZES (PIL.IcnsImagePlugin.IcnsFile), 111
sizes() (PIL.IcoImagePlugin.IcoFile), 111
skip() (PIL.MpegImagePlugin.BitStream), 114
split() (PIL.Image.Image), 47
stddev (PIL.ImageStat.PIL.ImageStat.Stat), 86
sum (PIL.ImageStat.PIL.ImageStat.Stat), 86
sum2 (PIL.ImageStat.PIL.ImageStat.Stat), 86
symbol() (PIL.ImageDraw2.Draw), 103

T

tagdata (PIL.TiffImagePlugin.ImageFileDirectory_v1), 118
tags (PIL.TiffImagePlugin.ImageFileDirectory_v1), 118
TAGS (PIL.TiffTags.PIL.TiffTags), 89
TAGS_V2 (PIL.TiffTags.PIL.TiffTags), 89
target (PIL.ImageCms.CmsProfile), 63
TarIO (PIL.TarIO), 107
technology (PIL.ImageCms.CmsProfile), 64
tell() (PIL.ContainerIO.ContainerIO), 102
tell() (PIL.DcxImagePlugin.DcxImageFile), 108
tell() (PIL.FliImagePlugin.FliImageFile), 109
tell() (PIL.GifImagePlugin.GifImageFile), 110
tell() (PIL.Image.Image), 47
tell() (PIL.ImImagePlugin.ImImageFile), 112
tell() (PIL.MicImagePlugin.MicImageFile), 114
tell() (PIL.PsdImagePlugin.PsdImageFile), 116
tell() (PIL.SpiderImagePlugin.SpiderImageFile), 117
tell() (PIL.TiffImagePlugin.TiffImageFile), 120
text() (PIL.ImageDraw.PIL.ImageDraw.Draw), 70
text() (PIL.ImageDraw2.Draw), 103
text() (PIL.PSDraw.PSDraw), 99
textsize() (PIL.ImageDraw.PIL.ImageDraw.Draw), 71
textsize() (PIL.ImageDraw2.Draw), 103
thumbnail() (PIL.Image.Image), 47
tkPhotoImage() (PIL.SpiderImagePlugin.SpiderImageFile), 117
to_v2() (PIL.TiffImagePlugin.ImageFileDirectory_v1), 118
tobitmap() (PIL.Image.Image), 47
tobytes() (PIL.Image.Image), 47
tobytes() (PIL.ImagePalette.ImagePalette), 83
tobytes() (PIL.ImageWin.Dib), 88
tolist() (PIL.ImagePath.PIL.ImagePath.Path), 84
tostring() (PIL.Image.Image), 48
tostring() (PIL.ImagePalette.ImagePalette), 84
transform() (PIL.Image.Image), 48
transform() (PIL.ImagePath.PIL.ImagePath.Path), 84
transform() (PIL.ImageTransform.Transform), 104
transpose() (PIL.Image.Image), 48
TYPES (PIL.TiffTags.PIL.TiffTags), 89

V

var (PIL.ImageStat.PIL.ImageStat.Stat), 86
verify() (PIL.Image.Image), 48
verify() (PIL.PngImagePlugin.ChunkStream), 115
verify() (PIL.PngImagePlugin.PngImageFile), 116
version (PIL.ImageCms.CmsProfile), 62
viewing_condition (PIL.ImageCms.CmsProfile), 65

W

width() (PIL.ImageTk.BitmapImage), 86
width() (PIL.ImageTk.PhotoImage), 87

`write_byte()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 119
`write_double()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_float()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_long()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_rational()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_short()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_signed_byte()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_signed_long()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_signed_rational()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_signed_short()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_string()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120
`write_undefined()` (PIL.TiffImagePlugin.ImageFileDirectory_v2), 120

X

`xcolor_space` (PIL.ImageCms.CmsProfile), 62